

#### **Enterprise Architect**

**User Guide Series** 

# **Model Repository**

Sparx Systems Enterprise Architect models are held in relational databases. A simple project with a file-based repository (MS JET or Firebird) can be seamlessly scaled up to a global project on DBMS servers (such as MySQL) and a Cloud-based repository.

Author: Sparx Systems

Date: 7/08/2019

Version: 1.0



# **Table of Contents**

Model Repository	15
Repository Overview	23
Projects Defined	30
Managing Connections to Projects	34
Obtain Repository Connection String	39
Project Shortcuts	40
Create Project Shortcut	45
Capture Current Work Environment	49
Encrypt Repository Password	52
File Based Projects	53
Copy a Base Project	61
Sharing File Based Projects	64
Share Enterprise Architect Projects	67
Refresh View of Shared Project	69
Share a Project	71
Distributed Development	73
Replication	75
Design Masters	79
Create Replicas	81
Synchronize Replicas	83
Remove Replication	85
Upgrade Replicas	88
Resolve Conflicts	90

Server Based Repositories	94
Create a Project in a MariaDB Database	97
Create a MariaDB Repository	103
Set up a MariaDB ODBC Driver	104
Connect to a MariaDB Repository	107
Create a Project in a MS Access 2007 Database	112
Create a Project in a MySQL Database	117
Create a MySQL Repository	123
Set up a MySQL ODBC Driver	124
Connect to a MySQL Repository	127
Create a Project in an Oracle Database	132
Create an Oracle Repository	138
Set up an Oracle ODBC Driver	140
Connect to an Oracle Repository (ODBC)	143
Connect to an Oracle Repository (OLE DB)	148
Create a Project in a PostgreSQL Database	153
Create a PostgreSQL Repository	160
Set up a PostgreSQL ODBC Driver	161
Connect to a PostgreSQL Repository	165
Create a Project in a SQL Server Database	169
Create a SQL Server Repository	175
SQL Server Security Permissions	178
Connect to a SQL Server Repository	181
Create a Project in a Sybase ASA/SQL Anywhere	
Database	186
Create an Adaptive Server Anywhere Repository	191
Set up an ASA ODBC Driver	192

Connect to an ASA Data Repository	195
The WAN Optimizer	199
Cloud Based Repositories	202
Introducing Cloud Repositories	204
Pro Cloud Server Setup	209
Pro Cloud Server Installation	211
Pro Cloud Server Configuration	219
Pro Cloud Server Configuration Client -	
Application	226
Pro Cloud Server Logon Screen	231
Database Managers	233
Add Database Manager	236
Add Database Manager - Firebird	240
Add Database Manager - ODBC	242
Add Database Manager - SQL Server	245
Add Database Manager - Oracle	251
Configure Database Manager	253
Obtain Database Manager Connection String	259
Extended Server Properties	262
Pro Cloud Server Licensing	266
Create Request	271
Add a new License	274
Remove a License	276
Renew a License	277
Manage Allocations	278
Port Configuration	281
Add a Port Definition	284

Advanced SSL	296
Self-Signed SSL Certificates	297
Add Trust with a Certificate Authority (CA)	299
Pro Cloud Server Configuration Client - Web	306
WebConfig - Login	311
WebConfig - Home Screen	313
WebConfig - Server Settings	319
WebConfig - Pro Cloud Server Licenses	324
WebConfig - New License Request	329
WebConfig - Add a License	332
WebConfig - Remove a License	334
WebConfig - Renew a License	335
WebConfig - Token Allocations	336
WebConfig - Configure Ports	339
WebConfig - Add or Edit a Port	342
WebConfig - Integration Plugins	347
WebConfig - Add or Edit an Integration Data	
Provider	355
WebConfig - Edit Model Bindings	365
WebConfig - Manage EA Floating Licenses	367
WebConfig - Adding a Model Connection	374
WebConfig - Edit Model Connection	379
Firewall Settings	384
Using Multiple Configurations	386
Pro Cloud Server using IIS (Optional)	389
Connecting Enterprise Architect to a Cloud Model	400
Pro Cloud Server Features	403

WebEA	406
WebEA Quick Start Guide	408
WebEA Quick Start Guide - IIS	421
WebEA Installation and Configuration	434
How to configure automatic viewable	
components	446
How to configure WebEA models	450
Configure WebEA models - via Web Browser	453
Edit WebEA Model Connection settings	458
Configure WebEA models - via Text Editor	477
How to configure WebEA Localization	516
Advanced SSL	519
Single Sign-On (SSO) with WebEA	521
WebEA User Guide	525
Login	528
WebEA's layout	533
Content Area	545
Main View - Object List	547
Main View - Diagram	551
Main View - Object Properties	553
WebEA - Browser	560
WebEA - Properties View	563
Object Creation in WebEA	567
Add Test Records	574
Add Resource Records	580
Add a Feature	584
Add Change Requests	588

Add a Document	593
Add a Defect	598
Add an Issue Notification	603
Add a Task	608
Add a Risk	613
Edit Objects	616
Reviews in WebEA	628
Discussions in WebEA	637
Create and check Watch Lists	642
Relationship Matrix	648
Search the model	653
Troubleshooting WebEA	657
Prolaborate	673
Integration Plugins	676
Install and Configure	677
User Guide	696
Add/Edit Data Provider	705
Integrate Data from External Providers	716
Navigate External Data	722
External Item Details	725
Linking Items	728
Configuration	733
Troubleshooting	736
Visibility Levels	743
Install and Configure	747
User Guide	753
Troubleshooting	757

Floating License Server	759
Install and Config	760
User Guide	766
Floating License Configuration Client	767
Floating License Server Connections	769
Set Shared Key Lease Periods	773
Migrate Shared Keys between Stores	775
Add Shared Keys	777
Release Shared Keys	778
Delete Shared Keys	780
Troubleshooting	781
Additional Functionality Using the Cloud	788
Reuseable Asset Service (RAS)	791
Connect to the Asset Service	794
Browse Assets	797
Asset Properties	802
Package Contents	805
Package Dependencies	808
Package Technologies	811
Storage Files	815
Compare an Asset to the Model	818
Import an Asset into the Model	820
Set Up Registry Password	826
Set Up the Asset Service	828
Register New Assets	840
Check Package Dependencies	852
Update an Asset	857

Pro Cloud Server Troubleshooting	863
Change Management	875
Version Control	878
Introduction	880
Version Control Usage	884
Version Control of Model Data	886
Version Control and Reference Data	888
Version Controlling Packages	889
Applying Version Control in a Team Environment	891
Version Control Nested Packages	894
Add Connectors To Locked Elements	896
Browser Window Indicators	898
Offline Version Control	900
Version Control Branching	906
Version Control Product Setup	907
System Requirements	910
Create a Subversion Environment	914
Create a new Repository Sub-tree	918
Create a Local Working Copy	920
Verify the SVN Workspace	923
Subversion Under Wine-Crossover	925
Preparing a Subversion Environment Under	
Wine	927
TortoiseSVN	931
Create a TFS Environment	932
TFS Workspaces	937
TFS Exclusive Check Outs	941


Verify the TFS Workspace	943
Create a CVS Environment	946
Prepare a CVS Local Workspace	950
Verify the CVS Workspace	953
TortoiseCVS	955
Create an SCC Environment	956
Upgrade at Enterprise Architect Version 4.5,	
Under SCC Version Control	959
Version Control Set Up	961
Re-use an Existing Configuration	964
Version Control Settings	966
SCC Settings	971
CVS Settings	975
SVN Settings	978
TFS Settings	981
Use Version Control	986
Configure Controlled Package	991
Apply Version Control To Branches	995
Package Version Control Options	997
Check Out a Package	1006
Undo Check Out of a Package	1008
Check In a Package	1010
Check Out a Model Branch	1012
Check In a Model Branch	1014
Update to the Latest Revision of Selected Packa	age1017
Update to the Latest Revision of All Packages	1020
Include Other Users' Packages	1023

Export Controlled Model Branch	1025
Import Controlled Model Branch	1028
Manually Locating Model Branch Files	1032
Review Package History	1035
Review Package History - SCC Client	_1038
Retrieve Prior Revision - SCC Client	1041
Validate Package Configurations	1044
Resynchronize the Status of Version Controlled	
Packages	1046
Tracking Changes	1049
Auditing	1051
Auditing Quickstart	1054
Auditing Settings	1056
The Audit View	1063
Audit View Controls	1067
Audit History Tab	1072
Auditing Performance Issues	1074
Audit View Performance Issues	1076
Package Baselines	1078
Baselines	1082
Manage Baselines	1086
Create Baselines	1090
The Compare Utility (Diff)	1093
Compare Options	1096
Check Visual Changes to Diagrams	1099
Example Comparison	1108
Baseline Comparison Tab Options	1111

Compare Projects	1117
Project Maintenance	1120
Check Project Data Integrity	1123
Reset Table Auto Increment or Identity Columns_	1127
Upgrade a Project	1131
Upgrade Replicas	1133
Run SQL Patches	1134
Rename a Project	1136
Compact a Project	1137
Repair a Project	1139
Reference Data	1142
UML Types	1144
Stereotype Settings	1145
Shape Editor	1150
Tagged Value Types	1153
Cardinality	1156
People	1159
Project Authors	1160
Select Users	1163
Project Roles	1165
Project Resources	1168
Project Clients	1171
General Types	1174
Status Types	1176
Constraint Types	1180
Constraint Status Types	1183
Difficulty Types	1186

Priority Types	1189
Test Status Types	1192
Requirement Types	1195
Scenario Types	1198
Maintenance Status Types	1201
Metrics and Estimation	1205
Maintenance	1206
Problem Types	1207
Testing Types	1210
Data Types	1212
Resources Window	1215
Favorites	1225
Sharing Reference Data	1228
Link Reference Data to a Shared Repositor	y1229
Export Reference Data	1233
Import Reference Data	1236

# **Model Repository**



Enterprise Architect is a rich modeling platform that can be used in a wide range of modeling and design situations, from a single user accessing a file based repository to a large and distributed team of thousands of modelers working all over the world using a Cloud Based Repository. The repositories can be scaled up and down, and a project that started with a single user can be seamlessly scaled up to a large multi-user repository.

Enterprise Architect has been built to support inter-disciplinary modelers collaborating to create a single and unified view of a system or enterprise, and the platform has numerous built in features to support this team development. By taking advantage of the base UML modeling language, in addition to the numerous extension languages such as BPMN and SysML, plus highly effective frameworks such as TOGAF and UAF/UPDM, modelers, designers, managers and others can build comprehensive, inter-connected models that fully expresses the capabilities, structure and behavior of fully functioning, multi-layered, complex systems and/or enterprises.

In addition, there are features that allow modelers to discuss the model, such as the Collaborate window, and review work that has been in progress in the Team Library window. Modelers can even send Model Mail to communicate ideas. Model Security can be implemented, which facilitates collaboration and prevents work accidentally being overridden.

There are a range of project management features, such as tasks and resource allocation and a Gantt Chart to view progress on tasks over time, and a Project Calendar that keeps track of important project events.

Integration is so easy and the feature sets so powerful that strategic thinkers, business managers, architects, information and data modelers, testers, software engineers and many others will derive great benefit from using the tool and incorporating their models into the overall vision.

## **Key Concepts**

# **Repository** Format

Enterprise Architect models are stored in **standard relational databases**. This approach has been built into Enterprise Architect from the very first version. Using a relational database provides a huge advantage over other tools that are limited in scope and capability by relying on a simple text file based model storage system. With support for two file based

repository formats (MS JET and Firebird) plus a number of industry standard DBMS servers (such as SQL Server, MySQL and Oracle) plus Cloud based storage, Enterprise Architect provides fast, scalable, flexible and transparent access to models in a wide range of deployment scenarios.

# Modeling Languages

Enterprise Architect is based on industry standard UML, a specification maintained by the Object Management Group (OMG). Although initially conceived as a modeling language primarily for software development, over the years the capabilities and formal (standard) extensions have allowed the UML to develop into a rich set of constructs and modeling behaviors that provide very rich and detailed support for everything from software, to business processes, embedded software, enterprise architecture, organizational charts, strategic model, mind mapping, requirements management and much more. The success of UML has been proven over and over again in the real world and the number of new technologies and modeling profiles that use UML as the underlying

'meta-language' are tribute to the power and effectiveness of UML.

# Team **Development**

From the very first version of Enterprise Architect the goal has been to provide the best and most accessible support for Team based development. A wealth of tools and capabilities have been designed into the platform over the years to support security, scalability, information sharing, concurrent access, management, reporting and querying. With the growth of the internet and distributed development scenarios, Enterprise Architect has evolved to be the pre-eminent platform for developing models and designs in a globally distributed situation. The Cloud Server based deployment offers high availability, excellent performance and simple configuration to rapidly bring diverse and distributed teams into a single, living repository where work can be easily shared, reviewed, discussed and managed.

#### **Scalability**

By leveraging the power of today's DBMS servers and Cloud Based technologies, Enterprise Architect can be easily scaled up to truly epic proportions.

Millions of objects can be stored and accessed by large and dispersed teams in real time. The level of scalability is limited solely by the choice of DBMS or Cloud Technology and the capabilities of the network and server infrastructure the model is deployed on. In practice, over the many years that Enterprise Architect has been used in industry, modelers and designers have taken advantage of the powerful in-built scalability to construct stunning and often huge models that capture an enormous amount of information about complex and highly inter-connected systems and enterprises.

#### Security

Due to the nature of the Repository used by Enterprise Architect and the possible deployment scenarios, security can be managed in a number of ways. In the Corporate, Unified and Ultimate editions of Enterprise Architect, there is built-in support for defining users and groups that permit locking and management of elements and Packages within the model. This will be discussed later in the section on Security. In addition, it is also possible to restrict general access to models by using file-based security access for the MS JET and Firebird-based models (.EAP and FDB) and DBMS server authentication and access for the larger database server-based systems. As a further refinement it is also possible to restrict access to a model using the HTTPS protocol when connecting to a Cloud Based server.

#### Versioning

Enterprise Architect uses industry standard XMI (XML Interchange) format files to store and version model Packages. By integrating the import and export of XMI model fragments into a Version Control system (such as SVN) supported by Enterprise Architect, you can maintain multiple versions of the same model in different repositories and exercise fine control over the development and design process. Given the nature of this versioning system, there are several different scenarios that can be used to maintain different models and how teams access information. For example, where the versioning system is used as the single point of truth and de-facto Repository, it could be convenient to use many workgroup or single user based Repositories that reflect the actual model at a particular

point in time. In contrast, where the versioned files are mainly held for backup and baseline purposes only, a larger, Team based DBMS server would be used to provide the model sharing and collaboration capabilities. So whatever the actual needs are, Enterprise Architect has a number of solution scenarios that can be adapted to provide the right level of change management and collaborative development.

## **Example Repository Tasks**

#### Task

Create a project in a simple, file-based repository (.EAP and .FEAP files)

Create the project in one of a range of DBMS repositories - these provide for larger models with more concurrently connected users (Corporate and extended editions)

Manage change within the model

Maintain the integrity of the project data

Share the reference data used across the project, between models and between projects

Allow each user to configure their personal preferences for how project tools display and behave on their workstation

Document your model through document or web reports, which you can tailor to your purposes

## **Repository Overview**



An Enterprise Architect repository is stored in a relational database; this can be a file based database such as MS Access or Firebird, or a database management system (DBMS) such as Oracle or MS SQL Server. Enterprise Architect can connect to DBMS based repositories via a direct connection or with the use of the Pro Cloud Server, such repositories are referred to as Cloud Based Repositories. It is common to start with a File Based Repository and, when the project gets some momentum and there are a number of modelers accessing the repository, to transfer it to a DBMS. Whichever type of repository is implemented, the user interface remains the same and users can seamlessly move from one type of repository to another and continue to contribute as a team member on this powerful modeling platform.

### **Concepts**

Concept	Description
Repository as a File	In any version of Enterprise Architect you can store a project in a single file

	<ul> <li>with a .eap or .feap extension.</li> <li>A .eap file is a Microsoft JET database, so you can also open it using MS Access 97, 2000, 2003 or 2013, or any other reporting tool that can work with JET databases</li> <li>A .feap file is a Firebird project file</li> </ul>
Repository in a DBMS (Database Management System)	In the Enterprise Architect Corporate, Unified and Ultimate editions you can also use a suitable DBMS repository for projects.  DBMS projects have the same logical structure as .eap and .feap files, but provide much greater scalability and concurrent access. You connect to a DBMS using ADO/ODBC (see <i>Connect to a Data Repository</i> ). Note that when configuring an ODBC data source on a 64 bit machine, you should access the ODBC data manager using the 'Configure > User Tools > ODBC Data Sources' ribbon option, as this will load the correct ODBC manager to access 32 bit data sources as used by Enterprise Architect.
Repository in the Cloud	In the Corporate, Unified and Ultimate editions of Enterprise Architect you can further enable the distributed capabilities

of Enterprise Architect and use the Internet or local network to connect to a Pro Cloud Server on which one or more Repositories have been installed and configured for access. The Pro Cloud Server is free software available from Sparx Systems, and is relatively simple to set up and configure on a suitable Windows-based machine. Firebird files or any DBMS server are the required Repository types supported by the Pro Cloud Server, and these can reside on the same machine for best performance, or on another machine to maximize local and network access. Cloud-based repositories provide the ultimate in distributed development and minimal client configuration. It is, in fact, much easier to deploy a Firebird-based repository on a Pro Cloud Server for distributed development than to set up and manage a full DBMS solution.

#### Models

Enterprise Architect uses this terminology when discussing Repositories and their contents.

1. A Model is a related group of content that expresses some focused aspect of a system or enterprise that is related by the modeling tools and paradigm used.

- For example, you might build a 'Usecase Model' that describes behavior and scenarios using UML Use Cases. Process models, architectural models, behavioral models, structural models, Class models and so on are all Models within the current Project.
- 2. A Project is a group of models that has a single unifying purpose. For example, a Project to design the navigation systems for a new aircraft or automobile would be considered a single Project. Within this Project there would be multiple models. Projects typically define levels of security, necessary types of views and models, necessary procedures and other management tasks to deliver the product. Project management capabilities in Enterprise Architect are quite rich and allow for resource management, security, change management, testing and other typical project management tasks.
- 3. A Repository is a single File, DBMS database or Cloud Server address that contains one or more Projects.

  Typically, file based repositories such as MS JET and Firebird models contain

a single Project with multiple models that can be shared by a small workgroup or only accessed by a single modeler. DBMS and Cloud based Repositories will often contain more than one Project, especially where the Projects are in some way inter-related or co-dependent.

# Adding Initial Content

After creating and accessing your new project in whatever form the Repository takes, you can now use the Model Wizard to create Model Packages that range from generic and simple views to more complex and pattern based content.

You can add Models to a project from the Browser window by:

- Right-clicking on an existing model and selecting the 'New Model' or 'Add a New Model using Wizard' options
- Right-clicking on a Package and selecting the 'Add | Add a New Model using Wizard' option
- Clicking on an existing model, pressing the Insert key and selecting the 'New Model' or 'Add a New Model using Wizard' menu options
- Clicking on a Package, pressing the Insert key and selecting the 'Add a New

	Model using Wizard' menu option
Opening Existing Projects	Existing Projects are accessible via the 'Recent Documents' list under the 'File Management' icon ( ), the 'Recent' list on the Start Page, and through the 'Open Project' option under the 'File Management' icon.
	Connecting to an existing DBMS or Cloud based Repository is discussed in more detail under the relevant sections on working with those Repository types.
	For new users, you can use the 'Start > Help > Help > Open the Example Model' ribbon option to open and explore the Enterprise Architect Example Repository supplied with Enterprise Architect. This example is not so much a fully worked example as a collection of models that show how you can leverage the power of the Enterprise Architect platform and the UML to create a wide range of visual and text based models.
DBMS Repositories	You can connect to any of these data repositories:  • MS Access 2007 onwards
	<ul><li> Wis Access 2007 onwards</li><li> Firebird</li><li> SQL Server 2000 onwards</li></ul>

- SQL Server Express 2005 onwards
- . MySQL
- MariaDB
- Oracle 9i, 10g, 11g and 12c
- PostgreSQL

In brief, to create a new database repository, you first create a new database with the DBMS management software, then run supplied scripts to create the logical structure.

You then use Enterprise Architect data transfer functions to move a project from a .eap, .feap or DBMS model into the new project. Details are available under the *Server Based Repositories* section.

## **Projects Defined**

An Enterprise Architect Project is a repository for storing, manipulating and managing one or more Models. A single repository can contain many models, and a Repository can be either file based, hosted in a larger DBMS system or based in the Cloud.

### **Concepts**

Concept	Detail
Project	A project can contain a single model, or a number of models, each of which defines a particular system or process. A model contains the diagrams, elements, relationships and associated metadata that define the structure and function of the system or process. These components are organized into a hierarchy of Packages, which help to group and manage related components.
Model	Different aspects of the process or system - or their development - are defined by Model Packages, which you generate from templates specifically structured to


support the aspects that the Model Packages represent, such as requirements or deployment. You can generate these templated Packages at any level of the hierarchy, but as they are created with their own content they are more useful at the top levels.

#### View

The top-level Packages in a model can also be Views, which represent partitions of the model that you define yourself.

You can start with standard Views such as Class or Component, or create whatever partitions are appropriate to your model.

# Example Project Structure



Each View or Model Package contains Packages; Use Case Model Package contains:

- Actors and
- Primary Use Cases

It also contains the Use Case diagram,

which could be an overview of the Package structure or function.

Each Package itself can contain one or more diagrams, one or more Packages, and several elements; the Primary Use Cases Package contains the:

- Primary UCDiagram
- Customer Setup Package
- Use Case1 element
- Use Case2 element

Each subordinate Package also contains diagrams, elements and (if necessary) further Packages; the elements are related by connectors created in the diagrams, and each element and connector has properties, attributes, operations and extensions defined in the respective 'Properties' dialogs.

Note that models do not have to be constructed this way. Depending on the methodology you are following and information you need to model, the project structure might look completely different. In addition, many architectural frameworks such as TOGAF and ArchiMate specify their own project structure as part of their overall solution architecture.

# **Managing Connections to Projects**

An Enterprise Architect project is used for storing and managing the components of one or more UML models. The Professional edition of Enterprise Architect works on file-based projects (.eap files). If you are using the Corporate edition (or above), you can also use one of a number of DBMSs such as Oracle or MySQL, or a Cloud Based server to host the project repository.

When you select to open a project, you can:

- Select a shortcut to a recent project, to open it
- Browse for another existing project to open
- Remove a shortcut from the list of recently-opened projects
- Specify connection details for opening a project hosted on a DBMS
- Connect to a project via the Cloud
- Create a new Enterprise Architect project file

#### Access

Ribbon	> Open Project
Keyboard Shortcuts	Ctrl+O

Other	Start Page   New   Manage projects

# **Options**

Field/Button	Action
Local File	Click on this button to open a file browser dialog, and locate and select an existing .EAP, .EAPX or .FEAP file; the .EAP file can be a project file or a shortcut to a project hosted on a DBMS. Alternatively, click on the drop-down arrow and select the 'New Project' option to create a new project.
Connect to Server	Click on this button to specify connection details for opening an Enterprise Architect project that is hosted on a DBMS. The 'Windows Data Link Properties' dialog displays; start to define the connection to the project's server-based repository.  You can also click on the drop-down arrow and select:  'Connection Wizard' - the 'Data Link

	Properties' dialog again displays  • 'Connection String' - the 'Connection String' dialog displays; type in or paste the connection string and click on the OK button to connect directly to the project
Connect to Cloud	Click on this button to connect to a project through the Cloud. The 'Cloud Connection' dialog displays, on which you specify the server, URL and model name to access via the Cloud.
Recent Projects	This panel lists the most recently opened projects, up to a maximum of ten. To open one of these projects either double-click on the name, or click on it and then click on the Open button.  Each project name is shown with its access path. You can edit the access path by right-clicking on it and selecting the 'Edit Connection String' context menu option; make the changes on the 'Connection String' dialog, and click on the OK button.  Similarly, if the project has a connection string (not a shortcut), you can change the name of the project by right-clicking on it and selecting the 'Edit Project Name'

	<ul> <li>menu option; type a new name in the 'Edit Project Name' dialog and click on the OK button.</li> <li>The list of recent projects is also displayed:</li> <li>On the Start Page, under the 'Recent' heading</li> <li>As a drop-down menu under the Open Project button on the Default Tools toolbar</li> <li>With the list of options</li> </ul>
Remove Selection from List	Click on a project name and click on this button to remove that project name from the 'Recent' list.
Show this Dialog at Startup	Select the checkbox to show this 'Open Enterprise Architect Project' dialog automatically upon starting Enterprise Architect. Deselect the checkbox to hide the dialog.
Default Project to Open	Click on a project name in the 'Recent' list and select this checkbox to open the selected project automatically whenever you start up Enterprise Architect.
Open	Click on this button to open the currently selected project in the 'Recent Projects'

	list.
Cancel	Click on this button to close this dialog without any further action.
Help	Click on this button to display this Help topic.

- Use of a DBMS and/or Cloud for hosting the model repository is available in the Corporate, Unified and Ultimate editions of Enterprise Architect
- Enterprise Architect supports these DBMS products for hosting model repositories:
  - SQL Server and SQL Server Express;
  - MySQL
  - Oracle 9i, 10g, 11g or 12c
  - Postgre SQL and
  - ASA

# **Obtain Repository Connection String**

A 'connection string' defines all the connection information that Enterprise Architect requires to open a repository.

Connection strings are typically only available from 'Manage Projects'.

- 1. You can open the 'Manage Projects' dialog by:
  - Pressing Ctrl+O, or
  - Clicking on Some > Open Project... or
  - Selecting Start Page | New | Manage projects
- 2. Find the repository in the 'Recent Projects' list. Note the 'Path' column will show the connection string; however, if it is too long for the screen it will be abbreviated and '...' shown.
- 3. Right-click on the repository and select the 'Edit Connection String' context menu option. This will show the 'Connection String' dialog.

When the 'Connection String' dialog is first shown the complete text of the connection string will be automatically selected. Press Ctrl+C to copy it to the clipboard.

It is usually a good idea to include this connection string in communications with Sparx Systems as it provides useful information about how you connect to the model, which can help Sparx Systems understand your environment.

# **Project Shortcuts**

Enterprise Architect enables you to create a desktop shortcut (or proxy file) to an Enterprise Architect project (Cloud, DBMS or file-based). Each shortcut is a file containing the connection string for the model. In addition, the shortcut also defines views that Enterprise Architect should open when it opens the model, as outlined here. In this manner it is a convenient and customizable way of quickly sharing a connection to a Cloud based model without requiring other users to know the details of the connections string, model name and other parameters.

### **Access**

Ribbon	Save As Shortcut
--------	------------------

## **Topics**

View	Detail
Diagrams	Define one or more specific diagram(s) to be loaded on opening the project.

Model Search	Open the Model Search with a specific text string and search type.  For searches operating on the current tree selection, a diagram in the target Package must be opened first.  If you use a custom SQL search, the SQL must include ea_guid AS CLASSGUID and the object type.  You specify a single Model Search to
	open.
The Relationship Matrix with a saved profile	Open the Relationship Matrix with a saved profile. You specify a single Relationship Matrix profile to open.
The default Team Library	Open the default Team Library document. You specify the Team Library once.
Working Set	Open a working set. You specify a single Working Set to open. This is very similar to the shortcut itself, opening a defined set of diagrams and views. However, the working set can also open source code editors, therefore

widening the capabilities of the shortcut alone.

Working sets make it easy to customize the main views you want to open without having to resave your project short cuts. The working set is easy to tailor to your changing requirements, adding greater flexibility to any short cut that calls the working set.

Also, working sets provide the capability of storing the currently-engaged files when closing a model, and reopening them in the context in which you were last using them. The basic project shortcut can also do this, but once the work environment is captured the shortcut returns to the same set up each time you use it. The working set always captures the current work environment each time the model closes.

This option can be very useful in, for example, a coding environment when you want to return to the last files you were editing.

# Workspace Layout

Apply a selected Workspace Layout, which opens and sets out the appropriate screens and windows for a specific area of work, such as model simulation.

You specify a single Workspace Layout to open. However, by creating and using separate shortcuts you can open Enterprise Architect in exactly the configuration you need for the work you want to do - modeling, coding, or debugging, for example.

# An example shortcut

You might create a shortcut to open, in sequence:

- A Development module
- The Model Search for a simple search on the term Issue
- The module Issues diagram
- The module 'Changes' diagram

Enterprise Architect opens the appropriate windows in the sequence in which you list the options, displaying the last view in the list as the active view.

In this example, the project opens with the Enterprise Architect work area showing the two diagram tabs and the 'Model Search' tab, and with the 'Changes' diagram displayed in the Diagram View.

- If specified, the shortcut views override any default diagram defined for the model or current user
- A shortcut does not affect the original Enterprise Architect .exe file or icon, or any other shortcut you might have defined; you can use all of these independently
- If you are using a database repository other than MS Access 97, 2000, 2003 or 2013, you can configure the shortcut to encrypt the password used to set up the connection between Enterprise Architect and the repository; the Enterprise Architect user does not have the real password, thereby preventing them from accessing the repository using other tools such as Query Analyzer or SQLPlus

# **Create Project Shortcut**

You can create a shortcut to an Enterprise Architect project (either a DBMS project or file based project). The shortcut can specify additional windows and diagrams to open up automatically every time the shortcut is run, to create a working environment in advance for other users.

Shortcuts are stored with a .EAP extension, but are actually small text files that tell Enterprise Architect what project to open and what initial views and windows to display.

### **Access**

Ribbon Save as Shortcut	
-------------------------	--

# Create a project shortcut

Ste	Action
p	
1	Open Enterprise Architect.
2	Open the required project.

3	Select the 'Save as Shortcut' option. The 'Save Project Shortcut' dialog displays.
4	Click on the button at the end of the 'Target File' field.  The 'Save Project As' dialog displays.
5	Browse for the appropriate file location and, in the 'File name' field, type an appropriate filename. All shortcuts are .EAP files, regardless of whether the model itself is a .EAP file or a DBMS model.
6	Click on the Save button to return to the 'Save Project Shortcut' dialog.
7	Click on the Add Other button and select the required option to define:  A diagram to open  A Relationship Matrix profile to open  The Team Library  A Model Search to perform  A working set to apply  A workspace layout to apply
8	The appropriate browser or dialog displays to define the view to display; enter the details and click on the OK button.

	The view is added to the 'Actions when model is opened' field; the entry is automatically selected, with a tick in the checkbox.
9	Repeat steps 7 and 8 for as many additional views as you require.
10	<ul> <li>Review the items in the 'Actions when model is opened' field.</li> <li>If you decide not to have an item in the shortcut, deselect its checkbox</li> <li>If you want to clear all selected items, click on the Include None button</li> <li>Unselected entries are deleted when you save the shortcut.</li> </ul>
11	If you decide to change the sequence and/or make a different view display first in the Diagram View:  Click on the appropriate entry  Click on the 'Up Hand' or 'Down Hand' buttons
12	Click on the OK button to save the shortcut.

• When you subsequently open the 'Save Project Shortcut' dialog, it lists the currently-opened views in the order in which they were opened; you can add further views or remove them from the shortcut

# **Capture Current Work Environment**

You can capture the current Enterprise Architect work environment in your shortcut. This maintains the work environment from that point, and is useful if you intend to close and re-open the model and return to the same configuration many times.

If you simply want to return to whatever work environment you happen to be in each time you close the model, you should use a work set that captures the current environment, either by itself or as part of a broader project shortcut.

### **Access**

Ribbon	Save as Shortcut
--------	------------------

# Capture your current work environment

Ste	Action
p	
1	Open Enterprise Architect.

2	Open the required project and work in it.
3	<ul> <li>At the point at which you decide to capture your work environment in a shortcut, ensure that:</li> <li>You have opened all diagrams you require</li> <li>If necessary, you have opened the Team Library, Model Search (with appropriate search term and type) and/or Relationship Matrix (at the appropriate profile)</li> <li>The view you want to resume work on is the last one opened</li> </ul>
4	Select the 'Save As Shortcut' menu option.  The 'Save Project Shortcut' dialog displays, showing a list of actions derived from the views you currently have open.
5	If you accessed Enterprise Architect via a shortcut, the 'Target File' field displays the file location of that shortcut.  Otherwise, click on the button at the end of the 'Target File' field.  The 'Save Project As' dialog displays.
6	Browse for the appropriate file location and, in the 'File name' field, type an appropriate filename. All shortcuts are .EAP files, regardless of whether the model itself is a .EAP file, .FEAP file or DBMS

	model.
7	Click on the Save button to return to the 'Save Project Shortcut' dialog.
8	In the 'Actions when model is opened' field, click on the Include All button.
9	If you also want to save current window positions click 'Add Other' followed by 'Add Workspace Layout'. The dialog shown allows you to select an existing layout or save the current layout.
10	Click on the OK button to save the shortcut.


# **Encrypt Repository Password**

If your model is developed on a DBMS repository, the 'Save Project Shortcut' dialog has an 'Encrypt Connection String' checkbox.

You can create the shortcut actions and, if necessary, select the checkbox to encrypt the database connection string.

You distribute the shortcut file to the database users who are to access the model. The users then have an encrypted string that prevents them from directly accessing the database using other tools.

# **File Based Projects**



Enterprise Architect provides a convenient light-weight, low-barrier and portable file-based repository out-of-the-box, which is ideal for modelers who want to start work immediately; with the file-based repository you can be modeling within a few minutes. When a number of colleagues want to contribute to the models, the file can be moved to a file-share and it is possible to work with this setup even when the model becomes quite large and the number of users increases to ten or more. All editions of Enterprise Architect support this type of repository in the form of a .eap file in an Access database, or a .feap file in a Firebird repository.

You can create your own repository from scratch, but a default repository (EABase.eap) is conveniently supplied, located in the Enterprise Architect installation directory. The file acts as a template for creating new projects and can be copied to give you a head start in creating a repository. You can tailor this repository to suit your organization or create your own base repository. A File Based Repository can be easily transferred to a DBMS based repository using the Project Transfer feature, allowing a project to be scaled up when the team increases in size or when organizational policy dictates it.

# File-based project tasks

Task	Detail
Create .EAP Project Files	Select one of:  New Project menu option  'Local File   New Project' option on the 'Manage Projects' dialog, or  'Create a new project' option on the Start Page  All of these options display the 'New Project' dialog; select a directory and enter a file name for your project (.eap under JET 3 or .eapx under JET 4).  Once the project has been saved, the Model Wizard displays, which makes a selection of Model Patterns available; select the Model Patterns to use.  Enterprise Architect adds a model containing the selected Model Packages to the Browser window.
Create .FEAP Project Files	As for a .eap/.eapx file, except that in the 'New Project' dialog, in the 'Save as Type' field, click on the drop-down arrow and select the .feap file extension.

Enterprise Architect will check your input and display an error message if:

- Your Firebird repository is not located on the local drive; a Firebird repository is not appropriate for a network shared project
- The file path contains characters that are not in the system codepage

Location of default (EABase.eap ) repository template

The default installation directories, depending on which version you have installed, are:

- Registered version: C:\Program Files\Sparx Systems\EA
- Trial version: C:\Program Files\Sparx Systems\EA Trial
- Lite version: C:\Program Files\Sparx
   Systems\EA Lite

A base project contains templates and reference data from which you can quickly develop your own project.

Note that in addition to deriving a new model from EABase.eap. it is also possible to start a new project by copying an existing one. While it is possible to simply 'copy' the .EAP file at the file system level, this results in two identical models and should only be used when

	that is the required behavior; for example, when distributing a model to a client for verification. If you use the built in functions of Enterprise Architect to create a new model based on an existing one, Enterprise Architect will modify the unique identifiers (GUIDS) for all elements and related constructs so that the new model is essentially unique, and not a simple copy of the existing one.
Configure Project	Having created your project, you can set a range of project parameters to define defaults, tailor the project to particular coding languages, and ensure consistent development and use of the project.
Create Custom Templates	You can customize any Enterprise Architect project as a template project with company standards, tutorials, frameworks and any other common piece of modeling already in-built; with careful planning you can save yourself many hours of work at project start-up.

# **Best Practices for File Based Repositories**

### Single User

Simple file based repositories (.eap and .feap files) are best suited to single user development with the model file placed on the modelers local drive. This is fast, very efficient and provides a powerful means of getting started in modeling a particular solution. Many models will start out as single user repositories and only later be migrated into a DBMS or Cloud based scenario for larger team access. If you need to quickly start work on a project and do some exploratory work, or you are working alone as a consultant, the .eap or .feap file format is ideal.

# Small Workgroup

With all versions of Enterprise Architect it is possible to share a .eap file at the network file level. This is really only a suitable solution for small workgroups (up to, say, five members) who are collaborating on a shared model. This solution is very much at the mercy of the quality of the network connection and could be less than ideal if collaborating users increase in number and/or the model grows very large. As Enterprise Architect on the user's machine is still running all the queries and performing all

database operations on a network file, a slow network will result in less than ideal performance. As team size and model size increases it is best to upsize to either a DBMS or Cloud-based architecture.

One additional scenario in which file

# In Conjunction with Version Control

One additional scenario in which file based repositories can be used to great effect is with a Version Control system such as SVN. If the SVN system holds the master content, then individual developers/modelers can check out the material of interest to them into a local .eap or .feap file. When they have made their changes they can migrate their work back into the shared master. This style of development is quite effective, and as the import and export of model material from the Version Control system works best with single user local project files, it is a good match and a good use of the two technologies.

## Copy of Repository for Storage or Review

A further use of the single file repository is for distribution to clients and others for review and comment, where the original model(s) is located in a DBMS or Cloud that the recipient would not have access to. As it is relatively easy to bulk copy a DBMS model to a local .eap file, this is a

	good method for passing on a model to a client or another interested party. If some of the material is restricted, it is possible to delete sections from this single file repository after the bulk copy is complete and before passing it on.
Replication	If network access is limited and DBMS and Cloud based solutions are not possible, another (less than optimal but still effective) team based solution is to use the built in replication features of the .EAP file format. By creating a design master and distributing replicas to other modelers, it is possible to effectively share and contribute to a model without having direct shared access to the common model. On the down side, someone will have to perform the model merges as required and if there are replication conflicts (two changes to the same item) this will require manual resolution.

• You can also add Model Packages to a project by clicking

on the Browser window header bar and selecting the 'New Model From Pattern' menu option

# **Copy a Base Project**

When you create a new project, you can use the Model Wizard to define the structure and contents. Alternatively, you can copy an existing template or base project which is already largely set up, containing company standards, tutorials, frameworks and any other common modeling structures. You can also copy an operational .EAP or .FEAP project file to a new file location under a new name to, for example:

- Provide separate copies for individual team members
- Create an evaluation or distribution version of the project If you intend to use an existing project file as the template for a new project, it is important to use this method rather than simply copying the .EAP file using Windows Explorer. This process provides the option to reset all the unique identifiers for Packages and elements, so that your new project is truly unique otherwise you create an exact copy of the original project.

#### Access

Open the template project or existing operational project then;

Ribbon Save Project As

# Create a new project from a base project

Option	Action
Target Project	Type the new project filename. You can either type in the file path as well, or click on the Browse button and browse for the required file path. If this is to be a shared project, store the file on a shared network resource such as a Network Server or Workgroup Server.
Source Project	Defaults to the path and name of the currently-open template or project.
Reset New Project GUIDs	If the target project is to be a different project from the source (such as when you copy a base template), select this checkbox to replace all GUIDs from the base model with fresh GUIDs in the new model.  However, if the new project is to be a direct copy of the source, or based on a project that is under Version Control, we recommend that you deselect this checkbox to prevent duplication of

	Packages when the 'Get Latest' facility is used.
Save As	Click on this button to save and open the new project.

# **Sharing File Based Projects**

Enterprise Architect offers a diverse range of functionality designed specifically for sharing projects in team-based and distributed development environments, through network deployment of model repositories, DBMS based repositories, Cloud based models, replication and XMI Import/Export.

### **Features**

Feature	Detail
Network Deployment	<ul> <li>Network deployment is possible under three different schemas:</li> <li>File based repositories</li> <li>DBMS server based repositories, or</li> <li>Cloud based deployment (recommended)</li> <li>DBMS server based repositories offer</li> </ul>
	<ul> <li>Response times than files on networks, due to the inherent structure of the DBMS</li> <li>Solutions when networking problems are encountered, as they have the ability to backtrack transactions caused</li> </ul>

	by external breakdowns
Replication	Replication enables data interchange between .EAP based repositories and is suitable for where many different users work independently in parallel development.  Modelers merge their changes into a Design Master only as required; it is
	recommended that a backup is carried out prior to replication.  Replication cannot be performed on
	repositories stored on a DBMS server.
XMI Import and Export	XMI Import/Export can be used to export and share discrete Packages between developers; XMI enables the export of Packages into XML files that can then be imported into any model.
	Package control can be used to set up Packages for Version Control and to enable batch export of Packages using XMI; Version Control enables a repository to be maintained by a
	third-party source code control application that is used to control access and record revisions.

• DBMS Repository support is available with the Corporate, Unified and Ultimate editions of Enterprise Architect

# **Share Enterprise Architect Projects**

The most efficient way of using Enterprise Architect to manage a team development is to share a project amongst a team of designers, developers and analysts.

### **Facilities**

Facility	Detail
By Sharing a project	<ul> <li>Many people can work on the model at the same time and contribute their particular skill</li> <li>Team members can always see what the latest changes are, keeping the team informed and up to date with the project status</li> </ul>
You can share a project in three ways	<ul> <li>Place the project in a shared network directory</li> <li>Use replication</li> <li>Use a shared DBMS-based repository</li> </ul>

### **Notes**

- Project Sharing and Replication are available in the Professional, Corporate, Unified and Ultimate editions of Enterprise Architect
- DBMS repositories are supported in the Corporate, Unified and Ultimate editions of Enterprise Architect

# **Refresh View of Shared Project**

When a user of a shared model checks out a Package and makes changes, other users can see those changes by refreshing their view of the Package or the changed diagram within the Package, in a number of ways.

### Refresh the view

Object	Options
Project	<ul> <li>Right-click on the Package name in the Browser window and select the 'Contents   Reload Current Package' option, or</li> </ul>
	<ul> <li>Press F5 to refresh the Package, or</li> <li>Select the (Reload Project) icon in the Project Tools toolbar, or</li> </ul>
	<ul><li>Press Ctrl+Shift+F11, or</li><li>Close the project and reopen it</li></ul>
Diagram	<ul> <li>Select the 'Start &gt; Desktop &gt;         Workspaces &gt; Manage Views &gt; Reload         View' ribbon option, or</li> <li>Right-click on the opened diagram tab         in the Diagram View, and select the</li> </ul>

'Reload <diagram name="">' option</diagram>
'Reload <diagram name="">' option</diagram>

# **Share a Project**

The easiest way to share a project amongst a work group of developers and analysts is to place the project file on a shared network drive, to which people connect from their workstations.

Individual developers and analysts can then open and work on the project concurrently.

### **Network Issues**

Enterprise Architect accepts a number of concurrent connections without issue; however, there are points you should consider:

Issue	Description
Lock Outs	There can be occasional 'lock-outs' when one user tries to access or update something another user is in the process of modifying.
Other Changes	Changes to the Browser window (and other project views) are not automatically updated; to compensate for this, users must occasionally reload their project to see changes made by other users.

Diagrams	If two or more people work on the same diagram concurrently, unexpected results can occur; it is best to allow only one analyst to work on a diagram at a time.
System crashes	(.EAPX/.EAP files only) If a user's machine crashes, the network suffers an outage or a machine is turned off unexpectedly, the project file might require repair to compensate for the sudden inconsistency; a repair facility is provided ('Configure > Model > Integrity > Manage .EAPX/.EAP File > Repair .EAPX/.EAP File') to carry out this task.

• Firebird-based projects (.feap files) are not suitable for sharing over a network

# **Distributed Development**

Enterprise Architect supports distributed development using two different techniques.

## Replication

Using replication, geographically separated analysts can update and modify parts of the model in replicas, then merge these back together at a central location.

## XMI Import/Export

Using XML-based import/export, you can export discrete Packages to XML to share among the development team; this has several benefits over replication:

- You can assemble a model from only the parts necessary to get your job done
- You can assemble a full model if required
- You can assemble a model from different Package versions for different purposes (such as customer visible, internal release only)
- · You can roll-back parts of a model as required
- There is less chance of 'collisions' between developers if each works on a discrete Package

• The process is controllable using a Version Control system, or through Package control

XML-based import/export is UML1.3 / XMI1.1 compliant; you can also write XML based tools to manipulate and extract information from XML files to enhance the development process.

XML-based Import/Export is accessed through the 'Publish > Model Exchange > Export-XML' and 'Import-XML' ribbon options.

# Replication

Apart from sharing Enterprise Architect projects in real time over a network, you can also share projects using replication.

### Guide

Facility	Detail
Replication	<ul> <li>Replication is a powerful means of sharing projects between isolated or mobile users; it enables different users to work independently of one another, and to merge their changes at a later time.</li> <li>In Replication:</li> <li>A project is converted to a design master, then replicas are made of the master</li> <li>Users take the replicas away, modify the project, then bring their replicas back to be synchronized with the master file</li> </ul>
Use Replication	To use replication:  1. Convert the base project to a design master.

	<ul><li>2. Create replicas from the design master.</li><li>3. Take the replica away and work on it as required, then bring it back for synchronization with the design master.</li></ul>
	4. Synchronize the replicas, during which all changes to both the master and the replica are propagated in both directions, so they both finally contain the same information.
Enterprise Architect Merge Rules	<ul> <li>Enterprise Architect follows these rules in merging:</li> <li>Additions are cumulative; that is, two replicas each creating three new Classes result in six new Classes after merging</li> <li>Deletions prevail over modifications; if one replica changes a Class name and other deletes the Class, merging replicas results in both files losing the Class</li> <li>Conflicting modifications appear in the 'Resolve Replication Conflicts' dialog.</li> </ul>

# Upgrades and Replicas

When you upgrade your version of Enterprise Architect, you must not open a replica until you have opened the design master and then synchronized the replicas with the master; you cannot directly

	upgrade a replica.
Avoid Change Collisions	If two or more people make changes to the same element, Enterprise Architect arbitrarily overwrites one person's change with the other's; to avoid this, different users should work on different Packages. However, since Enterprise Architect does not enforce this rule, it is possible for users' work to conflict; to minimize difficulties, please note these guidelines:  • If users are likely to have worked in the same area of the model, they should both witness the synchronization and confirm that they are happy with the net result  • If small pieces of information have been lost, they should be typed into one of the merged models after synchronization  • If a large piece of information has been lost (for example, an overwritten large Class note) use the 'Resolve Replication Conflicts' dialog
Disable or Remove Replication Features	If you have converted a project to a design master but now want to disable the replication features, you can remove Replication; ensure that you back up all

your	files	first.
J 0 011		

# **Design Masters**

A design master is the first converted Enterprise Architect project that supports replication. You create the master project from which you create replicas that can be modified independently of the master project and re-merged later.

### **Access**

Ribbon	Configure > Model > Integrity > Manage
	.EAPX/.EAP File > Make Design Master

## Create a design master

Ste	Action
p	
1	Take a back-up of the required Enterprise Architect project.
2	Select the project in the Browser window.
3	Select the 'Make Design Master' menu option and

follow the on-screen instructions.

# **Create Replicas**

A replica is one of several copies of the design master of an Enterprise Architect project. You create the copy of the master project for you or another user to modify independently and re-merge later.

### **Access**

Ribbon	Configure > Model > Integrity > Manage
Kibboli	.EAPX/.EAP File > Create New Replica

## Create a replica

Ste	Action
p	
1	First create a design master, then select the 'Create New Replica' menu option and follow the on-screen instructions.
2	Edit the replica over time and, when required, return the file for merging with the design master.

### **Notes**

• In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Manage Replicas' permission to create a replica

# **Synchronize Replicas**

Synchronizing replicas combines the changes made to each file. You can:

- Merge the changes made to each replica with the design master, so that a new set of replicas with all changes can be generated and distributed
- Combine the changes made to two replicas, should it be necessary for two team members to combine their work

### **Access**

Ribbon	Configure > Model > Integrity > Manage
	.EAPX/.EAP File > Synchronize Replicas

## Synchronize replicas

Ste	Action
p	
1	Open the design master project file (or the first required replica).

2	Select the 'Synchronize Replicas' menu option.
3	Locate and select the (second) required replica to merge the open project and the replica.

### **Notes**

- Information is copied both ways, including deletes, updates and inserts; both projects end up containing identical information
- If this process generates 'conflicting changes' errors, you should review and, if necessary, resolve these conflicts
- In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Manage Replicas' permission to create a replica

# **Remove Replication**

Replication makes many changes to the database structure of your model, so the model file becomes considerably larger with additional information; you might, therefore, decide not to use the replication feature any more.

### **Access**

Ribbon	Configure > Model > Integrity > Manage
Kibboli	Configure > Model > Integrity > Manage .EAPX/.EAP File > Remove Replication

## Remove replication from your model

Ste	Action
p	
1	Open a .EAP file (any .EAP file, other than the one having replication removed) - the menu option is not available if no file is open.
2	Select the 'Remove Replication' menu option. The 'Remove Replication Wizard' dialog displays.

3	Enter the full path and file name of the project to have replication removed.  Click on the Next button.  If the project displays Version Number 7.0 this indicates that Auditing is enabled. Auditing should be disabled before proceeding (see <i>Notes</i> ).
4	Enter the full path and file name of the base Enterprise Architect model (with no replication) to act as template.
	Click on the Next button.
5	Enter the full path and required file name for the output file.
	Click on the Next button.
6	Select whether to have a log file created and, if so, enter a file name for the log file.
7	Click on the Run button to begin removing replication.
	Enterprise Architect creates a new project containing all the model information.
	Your model has now had replication removed, and should be considerably smaller.

### **Notes**

- You cannot remove replication from a model with Auditing enabled if you want to remove replication:
- 1. Disable Auditing.
- 2. If prompted to do so, allow Enterprise Architect to roll back the database version.
- 3. Remove replication.

# **Upgrade Replicas**

A new release of Enterprise Architect might contain changes to the underlying project structure, such as more tables or changed queries. If you use Replication, you must take care with your upgrade.

### **Considerations**

Consideratio n	Detail
Open Design Master Project first	After installing the new version of Enterprise Architect, it is very important that you open the design master before opening any of the replicas with the updated version.
Changes to the database design	Changes to the database design in a replicated project can ONLY be done to the design master; trying to update a replica at best does nothing, and at worst causes the update of the master to fail.
Propagate Changes	Design changes are propagated through to the replicas the next time the replicas are synchronized with the master.

### Alternatively

One other strategy is to remove replication from a copy of the replica set, upgrade that project and convert it into a new design master from which new replicas are created.

### **Resolve Conflicts**

If two or more people each work on the same model object in their respective replicas between synchronizations, the replication engine has problems in resolving which change is the master. You need to select which of two conflicting changes you should save to the Design Master and/or replicas, where a substantial piece of information has been overridden by a user and you want to retrieve it.

### **Access**

Ribbon	Configure > Model > Integrity > Manage .EAPX/.EAP File > Resolve Replication Conflicts
	Confincts

### **Considerations**

Consideratio n	Detail
Avoid the problem	Ensure that each team member always works in a separate area of the model

	within their replica.
Check for conflicts	After synchronizing replicas, open the 'Resolve Conflicts' dialog (see next table) and check if there were any conflicts.
Response to conflicts	When a project record has been modified in different ways by different users, the replication engine selects one of the conflicting values based on rules within the JET replication manager.  However, the replication engine stores the discarded changes and flags the conflict on the 'Resolve Conflicts' dialog so that you can choose to roll in the discarded change instead.  Normally it is not necessary or desirable to examine conflicts, since they represent relatively inconsequential pieces of information that can very easily be modified through the normal Enterprise Architect interface; for example, by moving a diagram element.  The only case in which the 'Resolve Conflicts' dialog should be used is where a substantial piece of information has been overridden by a user, and you want to retrieve it.

# Resolve conflicts in changes to the same model object in two separate replicas

Ste p	Action
1	Synchronize a replica with the Design Master, and display the 'Resolve Conflicts' dialog.
2	In the 'Table with Conflicts' list, click on the entry that is likely to contain the lost information.
3	Click on each entry in the Conflicting Records list. When the lost information appears in the Conflict Details list, click on the Overwrite with Conflict button.
4	In the 'Conflicting Records' list, you can also copy each Row ID to the clipboard by right-clicking on the row and selecting the 'Copy to Clipboard' menu option.  You can locate the object that is in conflict in the Browser window or diagrams, by right-clicking on it and selecting the 'Find in Project Browser' or 'Find in Diagrams' option.

# **Server Based Repositories**



As a Enterprise Architect repository becomes larger, or the number of concurrent users increases or organizational policy dictates, it might be more appropriate to use a database management system (DBMS) to store the repository. A File Based Repository can be created and used in any edition of Enterprise Architect; however, if you decide to use a DBMS based repository you will need to use the Corporate, Unified or Ultimate editions. Enterprise Architect has a function to transfer your repository from a file based repository to a server based one, helping you to get started quickly and with no changes in the user-interface.

Note that the performance of the Repository as experienced by end users will depend very much on the quality and power of the server machine and the network infrastructure on which the DBMS and user are located. Using a DBMS over a very high latency (10ms or higher) network can result in significant delays and visibly inferior performance. When network latency is an issue, Sparx Systems recommends using a Cloud Based Server as the interactions are optimized to reduce the effect of network latency.

Also it is important to note that all models are quite different and although Sparx Systems does its best to maximize performance based on what is expected to be held in a repository, sometimes this is not quite sufficient. In these rare cases a review of the database indexes would be good practice to maximize data retrieval and access. This will ensure that end users receive the best possible performance even when models contain millions of constructs.

## Set up a Project on a DBMS repository

To set up your project on a DBMS repository, you work through these stages:

- 1. Set up your DBMS software and create a database.
- 2. Create the required tables in your database, by running a script supplied on the Sparx Systems website.
- 3. (For certain DBMS products) Set up an ODBC driver to enable connection to the repository.
- 4. Transfer the project from the source file to the DBMS repository; the source file can be:
  - a .EAP or .FEAP base model, to begin a new project from scratch, or
  - a previously-developed project file, to move an existing project into the DBMS repository
- 5. Connect to your repository.

## **DBMS Products you can use**

You can set up your project on a repository in:

- Firebird from v2
- MySQL from v5
- MariaDB
- Microsoft SQL Server from 2005, all editions including Express and Azure
- Microsoft Access from 2007
- Oracle from 9i (all editions)
- PostgreSQL from v8

For information on creating a project on a specific DBMS from this list, see *Learn more*.

### **Notes**

- You cannot move a model from a source .eap file of an Enterprise Architect version earlier than 3.5.0 without updating it first
- Before proceeding, you must have MDAC 2.6 or higher installed on your system
- (Optional, but recommended) before actually transferring the project structure from the file to the repository, perform a Project Data Integrity Check on the file

# Create a Project in a MariaDB Database

To create a project in a MariaDB repository, you work through these stages:

- Stage 1: Create an empty database repository and set up the data tables
- Stage 2: Set up the ODBC Driver
- Stage 3: Set up initial model data

## **Prerequisites**

- A machine with MariaDB version 10.1.2 or higher installed and running,
- MySQL ODBC

## 1. Create a MariaDB Repository

Action
Create a new empty database and configure it to your installation's defaults.
(

1. 2	Open your SQL management console of choice (such as HeidiSQL) and connect to the new database.
1. 3	Load the EASchema_1220_MySQL.sql file from the Sparx Systems website.
1. 4	Run EASchema_1220_MySQL.sql to create the required database schema.

# 2. Set up the ODBC DSN

Ste	Action
p	
2.	Create a suitable ODBC Data Source (using the MySQL ODBC driver and NOT the MariaDB driver), to the new database.  Making sure to select the extended option:  'Return matched rows instead of affected rows'

# 3. Set up Initial Data

Enterprise Architect repositories requires a basic amount of reference data to function correctly.

Setting up this initial data can be achieved in 2 different ways:

- 1. Transferring the entire contents of an existing model into the new database, or
- 2. Load Initial data using a SQL Script

# 3.1. Load Initial Data - Transfer existing model

If you choose to set up your new database with the contents of an existing model, then Sparx Systems recommend that a Project Integrity check is performed on the existing model to ensure it is 'clean' and free from data-related errors before being copied into the new database.

The Enterprise Architect installation provides a model specifically for this purpose; the model is copied into the installation folder and is called EABase.eap. However, if you have customized the various drop-down lists in another model then you might prefer to use that. Regardless of what model you choose to use the process is the same and is outlined here.

Ste	Action
p	

In Enterprise Architect, open the existing repository 3. and select 'Configure > Model > Integrity > Project 1. Integrity' in the ribbon. 1 Ensure that the Action is set to 'Report Only' and that 3. all items in 'Checks to Run' are enabled, then click 1. 2 the Go button. If Enterprise Architect detects that the existing 3. model contains integrity issues then these will be 1. 3 listed, these should be corrected before continuing with the Project Transfer. With Enterprise Architect open, ensure that it there 3. is no Project loaded, by selecting 'Close Project' 1. from the state of the button. 4 Select the 'Configure > Model > Transfer > Project 3. Transfer' ribbon option. 1. 5 The 'Project Transfer' dialog displays. 3. In the 'Transfer Type' panel, select 'File to DBMS'. 1. 6 3. In the 'Source Project' field, click on the — button and browse for the name of the project file to copy to 1. 7 the repository.

If the .EAP file has Replication enabled, this must be

	removed before performing the transfer.
3. 1. 8	At the right of the 'Target Project' field, click on the button.  The 'Datalink Properties' dialog displays.
3. 1. 9	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list. Click on the Next button.
3. 1. 10	In the 'Use Data source name' field, click on the drop-down arrow and select the ODBC Data Source you configured to point to your new database. Click on the OK button. The 'Project Transfer' dialog redisplays.
3. 1. 11	If required, select the 'Logfile' checkbox and type a path and filename for the data transfer log file.
3. 1. 12	Click on the Transfer button to begin the data transfer process.
3. 1. 13	When the process is complete, you have created a project on a MariaDB database and can now connect to it and open it from Enterprise Architect.

## 3.2. Load Initial Data - SQL Script

The Sparx Systems website provides a SQL Script that contains a series of INSERT statements that will load an empty database with all the data needed by Enterprise Architect.

Ste p	Action
3. 2. 1	Open your SQL management console of choice (such as HeidiSQL), connect to the new database.
3. 2. 2	Load the EABase_1220_MySQL.sql file from the Sparx Systems website.
3. 2. 3	Run EABase_1220_MySQL.sql to create the required database schema.

# **Create a MariaDB Repository**

Creating a MariaDB database is fully documented in the product information provided with your MariaDB installer or the MariaDB website.

There are many ways to create a new MariaDB database, probably the most common is to use a SQL based Management Console like HeidiSQL, which provides a convenient graphical user interface to enable the creation of databases, the execution of scripts, and backups and restores. However the exact method used is not important to this discussion, therefore you are free to use the most convenient or familiar method at your disposal.

Having created your MariaDB database, use the MySQL SQL script provided by Sparx Systems to create the required table definitions for Enterprise Architect. The EASchema\_1220\_MySQL.sql script is freely available on the DBMS Based Repositories page on the Sparx Systems website.

### **Notes**

• Ensure that the collation is set to the alphabet you use, such as Latin or Cyrillic

# Set up a MariaDB ODBC Driver

After you have created a MariaDB database, you will need to set up an ODBC DSN to the new database in order for Enterprise Architect to connect to it. Sparx Systems recommend that the MySQL ODBC driver is used to connect to MariaDB based repositories as the native MariaDB ODBC driver is not fully compatible with connection methods employed by Enterprise Architect.

## **Prerequisites**

#### Install:

- MariaDB DBMS and repository
- MySQL ODBC driver software

## Set up the ODBC Driver

Ste	Action
p	
1	Under both 32-bit and 64-bit operating systems,
	Enterprise Architect requires 32-bit ODBC drivers to
	connect to a repository through ODBC. You can
	quickly load the correct 32-bit ODBC Data Source

	Administrator by selecting the 'Configure > User Tools > ODBC Data Sources' ribbon option.
	The ODBC Data Source Administrator window displays.
2	Click on the Add button.  The 'Create New Data Source' dialog displays, enabling you to add a new DSN.
3	Select the appropriate MySQL ODBC Driver from the list.
4	Click on the Finish button. The 'MySQL Connector/ODBC' dialog displays.
5	<ul> <li>Enter these configuration details:</li> <li>A data source name for the connection</li> <li>A description (optional)</li> <li>The host address of the DBMS server</li> <li>User name and password</li> <li>The database name on the selected server</li> </ul>
6	To set the advanced options, click on the Details>> button.
7	Select these checkboxes (where provided):  Return matched rows instead of affected rows

	<ul><li>('Connection' or 'Cursors/Results' tab)</li><li>Allow big result sets ('Connection' tab)</li></ul>
8	Click on the Test Connection button to confirm that the details are correct.
9	If the test succeeds, click on the OK button to complete the configuration.  If the test does not succeed, review your settings.

### **Notes**

• Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions

# **Connect to a MariaDB Repository**

To access your MariaDB repository, you must provide the connection details to Enterprise Architect.

## **Prerequisites**

- The MariaDB repository and the project already exist
- You know the database user credentials that have SELECT, INSERT, UPDATE, DELETE, EXECUTE and SHOW VIEW access permissions
- The MySQL ODBC driver has been set up

#### Access

Ribbon	: Open Project
Keyboard Shortcuts	Ctrl+O

## **Connect to the repository**

Ste p	Action
1	In the 'Open Project' dialog, select the 'Connect to Server' checkbox.
2	Click on the button.  The 'Data Link Properties' dialog displays.
3	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list.
4	Click on the Next>> button. The 'Connection' tab displays.
5	Click on the 'Use data source name' radio button and on the drop-down arrow in its field.  From the list, select the ODBC driver you have set up to connect to your MariaDB repository.
6	If required, type in a User name and Password.
7	If required, type in an initial catalog.
8	Click on the Test Connection button to confirm that the details are correct.
9	If the test does not succeed, revise your settings.

	If the test succeeds, click on the OK button; the 'Connection Name & Type' dialog displays.
10	Give the connection a suitable name so that you can recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
11	If required, select the 'Encrypt Connection String' checkbox.
	This encrypts and hides the connection details of the database from the users that the connection string is given to.
12	If required, select the 'Lazy Load' checkbox to not load the full project view when the model is loaded; instead, only the parts that are necessary to display the visible portion of the tree are loaded.  With this setting, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.
13	If required, select the 'Use WAN Optimization' checkbox.  Note: this option is only included for historical reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.  The WAN Optimizer was originally created to improve performance over a Wide Area Network by

	compressing all database requests from Enterprise Architect to reducing transfer times.
	If you select this checkbox, complete the next two fields (see your administrator for the correct values); otherwise go to step 17.
14	In the 'Server' field, type the network name or address of the optimizer server.
15	In the 'Port' field, type the port on which the server is running on the remote machine.
16	In the 'DSN' field, type the data source name of the database as it appears on the remote machine.
17	Click on the OK button to complete the configuration and open the project.
	This also adds the project name to the 'Recent' list on the 'Start Page'; from now on, you can open the project again just by clicking on this name.

#### **Notes**

 Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions of Enterprise Architect

# Create a Project in a MS Access 2007 Database

Setting up a project in an Microsoft Access 2007 repository typically involves the conversion of an existing .EAP or .EAPX file, which can be achieve in two different ways:

- You have a working copy of MS Access 2007 itself, in which case you can convert your existing .EAP/.EAPX project directly to an MS Access 2007 (.ACCDB)
- or, the existing repository can be Transferred into an empty MS Access 2007 base database

In either case, before you convert or transfer your existing project, you should perform a project integrity check on the source model to ensure that is 'clean' and free from data related errors.

#### **Prerequisites**

• The 'Microsoft Office 12.0 Access Database Engine OLE DB Provider' ODBC driver installed

#### 1. Perform a Project Integrity Check

While this step is optional, Sparx Systems do recommend that it is performed.

Ste	Action
p	
1.	Using Enterprise Architect open the source Project .EAP/.EAPX file.
1. 2	Select 'Configure > Model > Integrity > Project Integrity' in the ribbon.
1. 3	Ensure that the Action is set to 'Report Only' and that all items in 'Checks to Run' are enabled, then click the Go button.
1.	If Enterprise Architect detects that the existing model contains integrity issues then these will be listed, these should be corrected before continuing with the next step.

## 2a. Convert source project with MS Access 2007

Ste	Action
p	
2a	Open MS Access 2007 and load the source

.1 .EAP/.EAPX file within this product.
Allow Access to convert the source project a
.ACCDB file. Once this process is complete your
Project is now a MS Access 2007 repository.

## 2b. Transfer source project to an empty .ACCDB file

Ste	Action
p	
2b	Open Enterprise Architect.  (If the 'Open Project' dialog displays, click on the Cancel button to open with no project loaded.)
2b .2	Select the 'Configure > Model > Transfer > Project Transfer' ribbon option.  The 'Project Transfer' dialog displays.
2b .3	In the 'Transfer Type' panel, select 'File to DBMS'.
2b .4	In the 'Source Project' field, type the name of the .EAP/.EAPX file to copy to the repository.  If the .EAP file has Replication enabled, this must be

	removed before performing the transfer.
2b .5	At the right of the 'Target Project' field, click on the button.  The 'Datalink Properties' dialog displays.
2b .6	Select 'Microsoft Office 12.0 Access Database Engine OLE DB Provider' from the list. Click on the Next button.
2b .7	Obtain an empty MS Access 2007 base project from the Sparx Systems DBMS Based Repositories web page, rename the file name to suit the intended purpose.
2b .8	On the 'Data Source Details' page of the 'Datalink Properties' dialog, type in the full path to the Access 2007 .ACCDB file. Click on the OK button to return to the 'Project Transfer' dialog.
2b .9	If required, select the 'Logfile' checkbox and type a path and filename for the data transfer log file.
2b .1 0	Click on the Transfer button to begin the data transfer process.  When the process is complete, you have created your project in an Access 2007 database and can now

open it directly from Enterprise Architect, browsing for the .ACCDB file location in the 'Open Project' dialog.

#### **Notes**

- Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions
- If you do not have Access 2007, you can download the Access Database Engine from the Microsoft downloads site
- Ensure that the collation is set to the alphabet you use, such as Latin or Cyrillic

## Create a Project in a MySQL Database

To create a project in a MySQL repository, you work through these stages:

- Stage 1: Create an empty database repository and set up the data tables
- Stage 2: Set up the ODBC Driver
- Stage 3: Set up initial model data

#### **Prerequisites**

- A machine with MySQL version 5 or higher installed and running,
- MySQL 32bit ODBC driver, between versions 5.2.4 and 5.3.6 (other versions are not recommended)

#### 1. Create a MySQL Repository

MySQL supports two different storage engines - InnoDB and MyISAM. In older versions of MySQL MyISAM was the default storage engine, but from MySQL v5.5 onwards InnoDB is the default. As of Enterprise Architect v13, Sparx Systems will no longer provide updates to the MyISAM script and recommend all users to choose InnoDB, as it supports transactions and UTF8.

Ste	Action
p	
1.	Create a new empty database and configure it to your installation's defaults.
1. 2	Open your SQL management console of choice (such as MySQL Workbench) and connect to the new database.
1. 3	Load the EASchema_1220_MySQL.sql file from the Sparx Systems website.
1. 4	Run EASchema_1220_MySQL.sql to create the required database schema.

## 2. Set up the ODBC DSN

Ste	Action
p	
2.	Create a suitable ODBC Data Source (using the
1	MySQL ODBC driver) to the new database.
	Making sure to select these extended options:
	• 'Return matched rows instead of affected rows'

• 'Allow big result sets'

#### 3. Set up Initial Data

Enterprise Architect repositories requires a basic amount of reference data to function correctly.

Setting up this initial data can be achieved in 2 different ways:

- 1. Transferring the entire contents of an existing model into the new database, or
- 2. Load Initial data using a SQL Script

## 3.1 Load Initial Data - Transfer existing model

If you choose to set up your new database with the contents of an existing model then Sparx Systems recommend that a Project Integrity check is performed on the existing model to ensure it is 'clean' and free from data-related errors before being copied into the new database.

The Enterprise Architect installation provides a model specifically for this purpose; the model is copied into the installation folder and is called EABase.eap. However, if you have customized the various drop-down lists in another

model then you might prefer to use that. Regardless of what model you choose to use, the process is the same and is outlined here.

Ste p	Action
3. 1. 1	In Enterprise Architect, open the existing repository and select 'Configure > Model > Integrity > Project Integrity' in the ribbon.
3. 1. 2	Ensure that the Action is set to 'Report Only' and that all items in 'Checks to Run' are enabled, then click the Go button.
3. 1. 3	If Enterprise Architect detects that the existing model contains integrity issues then these will be listed, these should be corrected before continuing with the Project Transfer.
3. 1. 4	With Enterprise Architect open, ensure that it there is no Project loaded, by selecting 'Close Project' from the button.
3. 1. 5	Select the 'Configure > Model > Transfer > Project Transfer' ribbon option.  The 'Project Transfer' dialog displays.
3. 1.	In the 'Transfer Type' panel, select 'File to DBMS'.

6	
3. 1. 7	In the 'Source Project' field, click on the button and browse for the name of the project file to copy to the repository.  If the .EAP file has Replication enabled, this must be removed before performing the transfer.
3. 1. 8	At the right of the 'Target Project' field, click on the button.  The 'Datalink Properties' dialog displays.
3. 1. 9	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list. Click on the Next button.
3. 1. 10	In the 'Use Data source name' field, click on the drop-down arrow and select the ODBC Data Source you configured to point to your new database. Click on the OK button. The 'Project Transfer' dialog redisplays.
3. 1. 11	If required, select the 'Logfile' checkbox and type a path and filename for the data transfer log file.
3. 1.	Click on the Transfer button to begin the data transfer process.

12	
1.	When the process is complete, you have created a project on a MySQL database and can now connect to it and open it from Enterprise Architect.

## 3.2 Load Initial Data - SQL Script

Ste	Action
p	
3. 2. 1	Open your SQL management console of choice (such as MySQL Workbench), connect to the new database.
3. 2. 2	Load the EABase_1220_MySQL.sql file from the Sparx Systems website.
3. 2. 3	Run EABase_1220_MySQL.sql to create the required database schema.

## **Create a MySQL Repository**

Creating a MySQL database is fully documented in the product information provided with your MySQL installer.

There are many ways to create a new MySQL database, probably the most common is to use a SQL based Management Console like MySQL Workbench, which provides a convenient graphical user interface to enable the creation of databases, the execution of scripts, and backups and restores. However the exact method used is not important to this discussion, therefore you are free to use the most convenient or familiar method at your disposal.

Having created your MySQL database, use the SQL script provided by Sparx Systems to create the required table definitions for Enterprise Architect. The EASchema\_1220\_MySQL.sql script is freely available on the DBMS Based Repositories page on the Sparx Systems website.

#### **Notes**

• Ensure that the collation is set to the alphabet you use, such as Latin or Cyrillic

## Set up a MySQL ODBC Driver

After you have created a MySQL database, you will need to set up an ODBC DSN to the new database in order for Enterprise Architect to connect to it.

#### **Prerequisites**

#### Install:

- MySQL DBMS and repository
- MySQL 32bit ODBC driver, between versions 5.2.4 and 5.3.6

#### Set up the ODBC Driver

Ste	Action
p	
1	Under both 32-bit and 64-bit operating systems, Enterprise Architect requires 32-bit ODBC drivers to connect to a repository through ODBC. You can quickly load the correct 32-bit ODBC Data Source Administrator by selecting the 'Configure > User Tools > ODBC Data Sources' ribbon option. The ODBC Data Source Administrator window

	displays.
2	Click on the Add button. The 'Create New Data Source' dialog displays, enabling you to add a new DSN.
3	Select the appropriate MySQL ODBC Driver from the list.
4	Click on the Finish button. The 'MySQL Connector/ODBC' dialog displays.
5	<ul> <li>Enter these configuration details:</li> <li>A data source name for the connection</li> <li>A description (optional)</li> <li>The host address of the DBMS server</li> <li>User name and password</li> <li>The database name on the selected server</li> </ul>
6	To set the advanced options, click on the Details>> button.
7	<ul> <li>Select these checkboxes (where provided):</li> <li>Return matched rows instead of affected rows ('Connection' or 'Cursors/Results' tab)</li> <li>Allow big result sets ('Connection' tab)</li> </ul>

8	Click on the Test Connection button to confirm that the details are correct.
9	If the test succeeds, click on the OK button to complete the configuration.  If the test does not succeed, review your settings.

#### **Notes**

• Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions

## Connect to a MySQL Repository

To access a project in your MySQL data repository, you must connect to the data repository from Enterprise Architect.

#### **Prerequisites**

- The MySQL repository and the project already exist
- You know the database user credentials that have SELECT, INSERT, UPDATE, DELETE, EXECUTE and SHOW VIEW access permissions
- The MySQL ODBC driver has been set up

#### Access

Ribbon	: Open Project
Keyboard Shortcuts	Ctrl+O

#### **Connect to the repository**

Ste p	Action
1	In the 'Open Project' dialog, select the 'Connect to Server' checkbox.
2	Click on the button.  The 'Data Link Properties' dialog displays.
3	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list.
4	Click on the Next>> button. The 'Connection' tab displays.
5	Click on the 'Use data source name' radio button and on the drop-down arrow in its field.  From the list, select the ODBC driver you have set up to connect to your MySQL repository.
6	If required, type in a User name and Password.
7	If required, type in an initial catalog.
8	Click on the Test Connection button to confirm that the details are correct.

9	If the test does not succeed, revise your settings.
	If the test succeeds, click on the OK button; the 'Connection Name & Type' dialog displays.
10	Give the connection a suitable name so that you can recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
11	If required, select the 'Encrypt Connection String' checkbox.
	This encrypts and hides the connection details of the database from the users that the connection string is given to.
12	If required, select the 'Lazy Load' checkbox to not load the full project view when the model is loaded; instead, only the parts that are necessary to display the visible portion of the tree are loaded.  With this setting, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.
13	If required, select the 'Use WAN Optimization' checkbox.  Note: this option is only included for historical reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.

	The WAN Optimizer was originally created to improve performance over a Wide Area Network by compressing all database requests from Enterprise Architect to reducing transfer times.  If you select this checkbox, complete the next two fields (see your administrator for the correct values);
	otherwise go to step 17.
14	In the 'Server' field, type the network name or address of the optimizer server.
15	In the 'Port' field, type the port on which the server is running on the remote machine.
16	In the 'DSN' field, type the data source name of the database as it appears on the remote machine.
17	Click on the OK button to complete the configuration and open the project.  This also adds the project name to the 'Recent' list on the Start Page; from now on, you can open the project again just by clicking on this name.

#### **Notes**

• Connecting to DBMS based Repositories is available in

the Corporate, Unified and Ultimate editions of Enterprise Architect

## Create a Project in an Oracle Database

To create a project in a repository on Oracle 9i, 10g, 11g or 12c, you work through these stages:

- Stage 1: Create a new Oracle database user to own the Enterprise Architect tables
- Stage 2: Connect to the Oracle repository; Sparx Systems recommends using Oracle Provider for OLE DB connecting with either Microsoft OLE DB Provider for ODBC or Microsoft OLE DB Provider for Oracle could cause unexpected behavior or performance issues due to known limitations of those drivers
- Stage 3: Set up initial model data

#### **Prerequisites**

- A machine with Oracle 9i, 10g, 11 g or 12c installed and running
- Oracle Client installed on the client machine, please ensure that the OLE/DB drivers are installed (you can download the drivers from the Oracle Technology Network web site, as part of the Oracle Data Access Components (ODAC) package; see *Learn more*)

#### 1. Create Database Repository

Ste	Action
p	
1.	Create a new Oracle database user to own the Enterprise Architect tables.
1. 2	Open your SQL management console of choice (such as Oracle SQL Developer) and connect to the newly create Enterprise Architect repository.
1. 3	Load the EASchema_1220_Oracle.sql file from the Sparx Systems website.
1. 4	Run the script to create the required database schema.

## 2. Set up Oracle connection

2.	In order for a OLE/DB connection to connect to an
1	Oracle based Enterprise Architect repository an entry in each user's local TNSNAMES.ORA needs to be
	defined, stating the server name, port etc of the

Oracle server.

#### 3. Set up Initial Data

Enterprise Architect repositories requires a basic amount of reference data to function correctly.

Setting up this initial data can be achieved in 2 different ways:

- 1. Transferring the entire contents of an existing model into the new repository, or
- 2. Load Initial data using a SQL Script

## 3.1 Load Initial Data - Transfer existing model

Ste	Action
p	
3. 1. 1	In Enterprise Architect, open the existing repository and select 'Configure > Model > Integrity > Project Integrity' in the ribbon.
3.	Ensure that the Action is set to 'Report Only' and that

1. 2	all items in 'Checks to Run' are enabled, then click the Go button.
3. 1. 3	If Enterprise Architect detects that the existing model contains integrity issues then these will be listed, these should be corrected before continuing with the Project Transfer.
3. 1. 4	With Enterprise Architect open, ensure that it there is no Project loaded, by selecting 'Close Project' from the button.
3. 1. 5	Select the 'Configure > Model > Transfer > Project Transfer' ribbon option.  The 'Project Transfer' dialog displays.
3. 1. 6	In the 'Transfer Type' panel, select 'File to DBMS'.
3. 1. 7	At the right of the 'Source Project' field, click on the button and browse for the name of the project file to copy to Oracle.  If the file has Replication enabled, this must be removed before performing the transfer.
3. 1. 8	At the right of the 'Target Project' field, click on the button.

	The 'Datalink Properties' dialog displays.
3. 1. 9	Select 'Oracle Provider for OLE DB' from the list. Click on the Next button.
3. 1. 10	On the 'Connection' page of the 'Datalink Properties' dialog, enter the Oracle service name in the 'Data Source' field, and the user name and password as required.  Click on the OK button. The 'Project Transfer' dialog redisplays.
3. 1. 11	If required, select the 'Logfile' checkbox and type a path and filename for the data transfer log file.
3. 1. 12	Click on the Transfer button to begin the data transfer process.
3. 1. 13	When the process is complete, you have created a project on a Oracle database and can now connect to it and open it from Enterprise Architect.

## 3.2. Load Initial Data - SQL Script

3. 2. 1	Open your SQL management console of choice (such as SQL Developer), log in as the owner of the newly create Enterprise Architect repository.
3. 2. 2	Load the EABase_1220_Oracle.sql file from the Sparx Systems website.
3. 2. 3	Run EABase_1220_Oracle.sql to create the required database schema.

#### **Notes**

• When transferring a project to Oracle you must have access rights to execute the CREATE SEQUENCE command

## **Create an Oracle Repository**

Creating an Oracle database is fully documented in the product information provided with your Oracle installer.

Before creating an Oracle data repository, install the appropriate version of Oracle (9i, 10g, 11g or 12c) and MDAC 2.6 or higher, and obtain access permission to create a new database.

There are many ways to create a new Oracle repository, probably the most common is to use a SQL based Management Console like SQL Developer, which provides a convenient graphical user interface to enable the creation of databases, the execution of scripts, and backups and restores. However the exact method used is not important to this discussion, therefore you are free to use the most convenient or familiar method at your disposal.

Having created your Oracle repository, use the SQL script provided by Sparx Systems to create the required table definitions and indexes for Enterprise Architect. The EASchema\_1220\_Oracle.sql is freely available on the DBMS Based Repositories page on the Sparx Systems website.

#### **Notes**

• Enterprise Architect only supports the 32-bit versions of

#### Oracle's OLE/DB and ODBC drivers

- For performance reasons, Sparx Systems recommends the use of the Oracle's OLE/DB driver over the Oracle ODBC driver
- Enterprise Architect is not compatible with the Microsoft OLE DB Provider for Oracle driver
- Set the collation to the alphabet you use, such as Latin or Cyrillic

## Set up an Oracle ODBC Driver

After you have created an Oracle repository, you can either set up an ODBC DSN to the new database in order for Enterprise Architect to connect to it, or you configure Enterprise Architect to use the Oracle OLE DB provider in connection strings to the new database.

Note: For performance reasons, Sparx Systems recommends using Oracle Provider for OLE DB.

Note: Enterprise Architect does not support the 'Microsoft OLE DB Provider for Oracle' driver.

#### **Prerequisites**

#### Install:

· Oracle DBMS and repository

### Set up the Oracle ODBC driver

Your Oracle driver is now available to connect to the repository from Enterprise Architect.

Ste	Action
p	
1	Under both 32-bit and 64-bit operating systems,

	Enterprise Architect requires 32-bit ODBC drivers to connect to a repository through ODBC. You can quickly load the correct 32-bit ODBC Data Source Administrator by selecting the 'Configure > User Tools > ODBC Data Sources' ribbon option.  The ODBC Data Source Administrator window displays.
2	Click on the Add button.
	The 'Create New Data Source' dialog displays, enabling you to add a new DSN.
3	Select 'Oracle in OraDB11g_home1' from the list (or similar, depending on the ODBC installation).
4	Click on the Finish button.  The 'Oracle ODBC Driver Configuration' dialog displays.
5	<ul> <li>Enter these configuration details:</li> <li>A data source name for the connection</li> <li>A description (optional)</li> <li>The TNS Service Name (click on the drop down arrow and select from the list)</li> <li>User ID</li> </ul>
6	Click on the Test Connection button and enter the Oracle user password to confirm that the details are

	correct.
7	If the test succeeds, click on the OK button to complete the configuration.  If the test does not succeed, review your settings.

# **Connect to an Oracle Repository** (ODBC)

To access a your Oracle repository, you must provide the connection details to Enterprise Architect.

Note: For performance reasons, Sparx Systems recommends using Oracle Provider for OLE DB (see *Connect to an Oracle Data Repository (OLE DB)*).

Note: Enterprise Architect does not support the 'Microsoft OLE DB Provider for Oracle' driver.

#### **Prerequisites**

- The Oracle repository and the project already exist
- You have SELECT, UPDATE, INSERT and DELETE access permissions
- The Oracle ODBC driver has been set up

#### Access

Ribbon	: Open Project
Keyboard	Ctrl+O

|--|

## Connect to an Oracle Data Repository using an ODBC Driver

Ste	Action
p	
1	In the 'Open Project' dialog, select the 'Connect to Server' checkbox.
2	Click on the button.
	The 'Data Link Properties' dialog displays.
3	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list.
4	Click on the Next>> button. The 'Connection' tab displays.
5	In the 'Data source' field, click on the drop-down arrow and select the data source name.
6	Type in the User name and Password.

7	Click on the Test Connection button to confirm that the details are correct.
8	If the test does not succeed, revise your settings.  If the test succeeds, click on the OK button; Oracle prompts you for the password.
9	Type in the password.  The 'Connection Name and Type' dialog displays.
10	Give the connection a suitable name so that you can recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
11	If you want to encrypt and hide the connection details of the database from the users that the connection string is given to, select the 'Encrypt Connection String' checkbox.
12	The Lazy Load facility does not load the full project view when the model is loaded; instead, it loads only the parts that are necessary to display the visible portion of the tree. With this set, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.  If you want to use the Lazy load facility, select the 'Lazy Load' checkbox.

13	If required, select the 'Use WAN Optimization' checkbox.
	Note: this option is only included for historical reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.
	The WAN Optimizer was originally created to improve performance over a Wide Area Network by compressing all database requests from Enterprise Architect to reducing transfer times.
	If you select this checkbox, complete the next two fields (see your administrator for the correct values); otherwise go to step 16.
14	In the 'Server' field, type the network name or address of the optimizer server.
15	In the 'Port' field, type the port on which the server is running on the remote machine.
16	Click on the OK button to complete the configuration and open the project.
	This also adds the project name to the 'Recent' list on the Start Page; from now on, you can open the project again just by clicking on this name.

### **Notes**

• Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions

# Connect to an Oracle Repository (OLE DB)

To access in your Oracle repository, you must provide the connection details to Enterprise Architect.

### **Prerequisites**

- Oracle Client already installed on the client machine, please ensure that the OLE/DB drivers are installed (you can download the drivers from the Oracle Technology Network web site, as part of the Oracle Data Access Components (ODAC) package; see *Learn more*)
- The Oracle repository and the project already exist
- You have SELECT, UPDATE, INSERT and DELETE access permissions

#### Access

Ribbon	: Open Project
Keyboard Shortcuts	Ctrl+O

## **Connect to an Oracle Repository using OLE DB**

Ste p	Action
1	In the 'Open Project' dialog, select the 'Connect to Server' checkbox.
2	Click on the button.  The 'Data Link Properties' dialog displays.
3	Select 'Oracle Provider for OLE DB' from the list. <b>Do not</b> select 'Microsoft OLE DB Provider for Oracle'; Enterprise Architect might not work as expected.
4	Click on the Next>> button. The 'Connection' tab displays.
5	In the 'Data source' field, click on the drop-down arrow and select the data source name (the service name of the Oracle database).
6	Type in the User name and Password.

7	Click on the Test Connection button to confirm that the details are correct.
8	If the test does not succeed, revise your settings.  If the test succeeds, click on the OK button; the 'Connection Name and Type' dialog displays.
9	Give the connection a suitable name so that you can recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
10	If you want to encrypt and hide the connection details of the database from the users that the connection string is given to, select the 'Encrypt Connection String' checkbox.
11	If required, select the 'Lazy Load' checkbox to not load the full project view when the model is loaded; instead, only the parts that are necessary to display the visible portion of the tree are loaded.  With this setting, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.
12	If required, select the 'Use WAN Optimization' checkbox.  Note: this option is only included for historical

	reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.
	The WAN Optimizer was originally created to improve performance over a Wide Area Network by compressing all database requests from Enterprise Architect to reducing transfer times.
	If you select this checkbox, complete the next two fields (see your administrator for the correct values); otherwise go to step 15.
13	In the 'Server' field, type the network name or address of the optimizer server.
14	In the 'Port' field, type the port on which the server is running on the remote machine.
15	Click on the OK button to complete the configuration and open the project.  This also adds the project name to the 'Recent' list on the Start Page; from now on, you can open the project again just by clicking on this name.

#### **Notes**

• This feature is available in the Corporate, Unified and Ultimate editions

# Create a Project in a PostgreSQL Database

To create a project in a repository on PostgreSQL, you work through these stages:

- Stage 1: Create an empty database repository and set up the data tables
- Stage 2: Set up the PostgreSQL ODBC Driver
- Stage 3: Set up initial model data

#### **Prerequisites**

- A machine with PostgreSQL 9 or higher installed and running
- psqlODBC, version 8.03 or higher has been installed (do not use version 8.3.4 or 8.4.1)

### 1. Create Database Repository

Ste p	Action
1.	Create the empty database and configure it to your installation's defaults.

1. 2	Open your SQL management console of choice (such as pgAdmin) and connect to the new database.
1. 3	Load the EASchema_1220_PostgreSQL.sql file from the Sparx Systems website.
1. 4	Run the EASchema_1220_PostgreSQL.sql to create the required database schema.

## 2. Set up the ODBC DSN

Ste p	Action
P	
2.	Create a suitable ODBC Data Source to the new
1	database.
	Making sure to select these extended options:
	Page 1:
	Disable Genetic Optimizer - Uncheck
	Use Declare/Fetch - Check
	Unknowns as LongVarChar - Check
	Bools as Char - Uncheck
	Max Varchar - 1024

Max LongVarChar - 1000000

Page 2:

bytea as LO - Check

Disallow Premature - Check

Protocol - 7.4+

## 3. Set up Initial Data

Enterprise Architect repositories requires a basic amount of reference data to function correctly.

Setting up this initial data can be achieved in 2 different ways:

- 1. Transferring the entire contents of an existing model into the new database, or
- 2. Load Initial data using a SQL Script

## 3.1 Load Initial Data - Transfer existing model

If you choose to set up your new database with the contents of an existing model then Sparx Systems recommend that a Project Integrity check is performed on the existing model to ensure it is 'clean' and free from data-related errors before being copied into the new database.

The Enterprise Architect installation provides a model specifically for this purpose; the model is copied into the installation folder and is called EABase.eap. However, if you have customized the various drop-down lists in another model then you might prefer to use that. Regardless of what model you choose to use, the process is the same and is outlined here.

Ste p	Action
3. 1. 1	In Enterprise Architect, open the existing repository and select 'Configure > Model > Integrity > Project Integrity' in the ribbon.
3. 1. 2	Ensure that the Action is set to 'Report Only' and that all items in 'Checks to Run' are enabled, then click the Go button.
3. 1. 3	If Enterprise Architect detects that the existing model contains integrity issues then these will be listed, these should be corrected before continuing with the Project Transfer.
3. 1. 4	With Enterprise Architect open, ensure that it there is no Project loaded, by selecting 'Close Project' from the button.

Select the 'Configure > Model > Transfer > Project 3. Transfer' ribbon option. 1. 5 The 'Project Transfer' dialog displays. 3. In the 'Transfer Type' panel, select 'File to DBMS'. 1. 6 3. In the 'Source Project' field, click on the \_\_\_ button and browse for the name of the project file to copy to 1. 7 the repository. If the .EAP file has Replication enabled, this must be removed before performing the transfer. At the right of the 'Target Project' field, click on the 3. 1. button. 8 The 'Datalink Properties' dialog displays. 3. Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list. 1. 9 Click on the Next button. On the 'Use Data Source Name' field, click on the 3. drop-down arrow and select the ODBC Data Source 1. you configured to point to your new database. 10 Click on the OK button. The 'Project Transfer' dialog redisplays.

3. 1. 11	If required, select the 'Logfile' checkbox and type a path and filename for the data transfer log file.
3. 1. 12	Click on the Transfer button to begin the data transfer process.
3. 1. 13	When the process is complete, you have created a project on a PostgreSQL database and can now connect to it and open it from Enterprise Architect.

## 3.2 Load Initial Data - SQL Script

3. 2. 1	Open your SQL management console of choice (such as pgAdmin), connect to the new database.
3. 2. 2	Load the EABase_1220_PostgreSQL.sql file from the Sparx Systems website.
3. 2.	Run EABase_1220_PostgreSQL.sql to create the required database schema.

3

#### **Notes**

During the transfer, if an error message displays reporting '...nonstandard use of \\ in a string literal...', set the server variable in the postgresql.conf file to:
 escape\_string\_warning = off

## **Create a PostgreSQL Repository**

Creating a PostgreSQL database is fully documented in the product information provided with your PostgreSQL installer.

There are many ways to create a new PostgreSQL database, probably the most common is to use a SQL based Management Console like pgAdmin, which provides a convenient graphical user interface to enable the creation of databases, the execution of scripts, and backups and restores. However the exact method used is not important to this discussion, therefore you are free to use the most convenient or familiar method at your disposal.

Having created your PostgreSQL database, use the SQL script provided by Sparx Systems to create the required table definitions for Enterprise Architect. The EASchema\_1220\_PostgreSQL.sql script is freely available on the <a href="DBMS Based Repositories">DBMS Based Repositories</a> page on the Sparx Systems website.

#### **Notes**

• Ensure that the collation is set to the alphabet you use, such as Latin or Cyrillic

## Set up a PostgreSQL ODBC Driver

After you have created a PostgreSQL database, you will need to set up an ODBC DSN to the new database in order for Enterprise Architect to connect to it.

#### **Prerequisites**

#### Install:


- PostgreSQL DBMS and repository
- PostgreSQL ODBC driver software version 7.03.01.00 or above (note that versions 8.3.4, 8.4.1 and 9.03 of the PostgreSQL ODBC Driver are not supported)


#### Set up the ODBC driver

Your PostgreSQL driver is now available to connect to the repository from Enterprise Architect.

Ste	Action
p	
1	Under both 32-bit and 64-bit operating systems,
	Enterprise Architect requires 32-bit ODBC drivers to
	connect to a repository through ODBC. You can
	quickly load the correct 32-bit ODBC Data Source

	Administrator by selecting the 'Configure > User Tools > ODBC Data Sources' ribbon option.
	The ODBC Data Source Administrator window displays.
2	Click on the Add button.  The 'Create New Data Source' dialog displays, enabling you to add a new DSN.
3	Select 'PostgreSQL UNICODE' from the list.
4	Click on the Finish button. The 'Postgre SQL Connector/ODBC' dialog displays.
5	<ul> <li>Enter these configuration details:</li> <li>A data source name for the connection</li> <li>The actual name of the database</li> <li>The host address of the DBMS server</li> <li>User name</li> <li>A description (optional)</li> <li>The password</li> </ul>
6	To set the advanced options, click on the Datasource button and set the options on 'Page 1' as shown:





## Connect to a PostgreSQL Repository

To access your PostgreSQL repository, you must provide the connection details to Enterprise Architect.

#### **Prerequisites**

- The PostgreSQL repository and the project already exist
- You know the database user credentials that have SELECT, UPDATE, INSERT and DELETE access permissions
- The PostgreSQL ODBC driver has been set up

#### Access

Ribbon	: Open Project
Keyboard Shortcuts	Ctrl+O

### **Connect to the repository**

Ste p	Action
1	In the 'Open Project' dialog, select the 'Connect to Server' checkbox.
2	Click on the button.  The 'Data Link Properties' dialog displays.
3	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list.
4	Click on the Next>> button. The 'Connection' tab displays.
5	Click on the 'Use data source name' radio button and on the drop-down arrow in its field.  From the list, select the ODBC driver you have set up to connect to your PostgreSQL repository.
6	Click on the Test Connection button to confirm that the details are correct.
7	If the test does not succeed, revise your settings.  If the test succeeds, click on the OK button; the 'Connection Name & Type' dialog displays.
8	Give the connection a suitable name so that you can

	recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
9	If required, select the 'Encrypt Connection String' checkbox.  This encrypts and hides the connection details of the database from the users that the connection string is given to.
10	If required, select the 'Lazy Load' checkbox to not load the full project view when the model is loaded; instead, only the parts that are necessary to display the visible portion of the tree are loaded.  With this setting, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.
11	If required, select the 'Use WAN Optimization' checkbox.  Note: this option is only included for historical reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.  The WAN Optimizer was originally created to improve performance over a Wide Area Network by compressing all database requests from Enterprise Architect to reducing transfer times.  If you select this checkbox, complete the next two fields (see your administrator for the correct values);

	otherwise go to step 15.
12	In the 'Server' field, type the network name or address of the optimizer server.
13	In the 'Port' field, type the port on which the server is running on the remote machine.
14	In the 'DSN' field, type the data source name of the database as it appears on the remote machine.
15	Click on the OK button to complete the configuration and open the project.  This also adds the project name to the 'Recent' list on the Start Page; from now on, you can open the project again just by clicking on this name.

#### **Notes**

• This feature is available in the Corporate, Unified and Ultimate editions

# Create a Project in a SQL Server Database

To create a project on a repository in SQL Server 2005 and above, or SQL Server Express 2005 and above, work through these stages:

- Stage 1: Create an empty database repository and set up the data tables
- Stage 2: Set up initial model data

#### **Prerequisites**

- A machine with SQL Server installed and running
- MDAC 2.6 or higher on the client machine
- Permissions to create databases on SQL Server (see the *SQL Server Security Permissions* Help topic)
- ALTER permission on the t\_image table in Enterprise Architect, to be able to import model images

## 1. Create a SQL Server Repository

Ste	Action
p	

1.	Create a new empty database and configure it to your installation's defaults.
1. 2	Open your SQL management console of choice (such as Microsoft SQL Server Management Studio) and connect to the new database.
1. 3	Load the EASchema_1220_SQLServer.sql file from the Sparx Systems website.
1. 4	Run EASchema_1220_SQLServer.sql to create the required database schema.

## 2. Set up Initial Data

Enterprise Architect repositories requires a basic amount of reference data to function correctly.

Setting up this initial data can be achieved in 2 different ways:

- 1. Transferring the entire contents of an existing model into the new database, or
- 2. Load Initial data using a SQL Script

## 2.1 Load Initial Data - Transfer existing

#### model

If you choose to set up your new database with the contents of an existing model then Sparx Systems recommend that a Project Integrity check is performed on the existing model to ensure it is 'clean' and free from data-related errors before being copied into the new database.

The Enterprise Architect installation provides a model specifically for this purpose; the model is copied into the installation folder and is called EABase.eap. However, if you have customized the various drop-down lists in another model then you might prefer to use that. Regardless of what model you choose to use, the process is the same and is outlined here.

Ste	Action
p	
2. 1. 1	In Enterprise Architect, open the existing repository and select 'Configure > Model > Integrity > Project Integrity' in the ribbon.
2. 1. 2	Ensure that the Action is set to 'Report Only' and that all items in 'Checks to Run' are enabled, then click the Go button.
2. 1. 3	If Enterprise Architect detects that the existing model contains integrity issues then these will be listed, these should be corrected before continuing

	with the Project Transfer.
2. 1. 4	With Enterprise Architect open, ensure that it there is no Project loaded, by selecting 'Close Project' from the button.
2. 1. 5	Select the 'Configure > Model > Transfer > Project Transfer' ribbon option.  The 'Project Transfer' dialog displays.
2. 1. 6	In the 'Transfer Type' panel, select '.EAP to DBMS'.
2. 1. 7	In the 'Source Project' field, type the name of the project file to copy to the repository.  If the .EAP file has Replication enabled, this must be removed before performing the transfer.
2. 1. 8	At the right of the 'Target Project' field, click on the button.  The 'Datalink Properties' dialog displays.
2. 1. 9	Select 'Microsoft OLE DB Provider for SQL Server' or 'Microsoft OLE DB Driver for SQL Server' from the list. Click on the Next button.

On the 'Data Source Details' page of the 'Datalink 2. Properties' dialog, type in the server name, database 1. name and any security details required. 10 Click on the OK button. The 'Project Transfer' dialog redisplays. If required, select the 'Logfile' checkbox and type a 2. path and filename for the data transfer log file. 1. 11 2. Click on the Transfer button to begin the data transfer process. 1. 12 When the process is complete, you have created a 2. project on a SQL Server database and can now 1. 3 connect to it and open it from Enterprise Architect.

## 2.2 Load Initial Data - SQL Script

The Sparx Systems website provides a SQL Script that contains a series of INSERT statements that will load an empty database with all the data needed by Enterprise Architect.

Ste	Action
p	

2. 2. 1	Open your SQL management console of choice (such as Microsoft SQL Server Management Studio), connect to the new database.
2. 2. 2	Load the EABase_1220_SQLServer.sql file from the Sparx Systems website.
2. 2. 3	Run EABase_1220_SQLServer.sql to create the required database schema.

## **Create a SQL Server Repository**

Creating a SQL Server database is fully documented in the product information provided with your SQL Server installer.

There are many ways to create a new SQL Server database, probably the most common is to use a SQL based Management Console like Microsoft SQL Server Management Studio, which provides a convenient graphical user interface to enable the creation of databases, the execution of scripts, and backups and restores. However the exact method used is not important to this discussion, therefore you are free to use the most convenient or familiar method at your disposal.

Having created your SQL Server database, use the SQL script provided by Sparx Systems to create the required table definitions for Enterprise Architect. The EASchema\_1220\_SQLServer.sql script is freely available on the <a href="DBMS Based Repositories">DBMS Based Repositories</a> page on the Sparx Systems website.

### **SQL Server Management Studio example**

Ste	Action
p	

1	In SQL Server Management Studio, locate the server on which to create your new repository (ie. DBSERVER02\SQLEXPRESS) and login with administrator privileges;
2	Right-click and choose the 'New Database' option.
3	Enter a suitable name for the database. Set any file options as required.  Ensure that the database collation is set to the alphabet you use, such as Latin or Cyrillic, and case-insensitive.
4	Click on the database to select it, then select the 'New Query' menu option.
5	In the Query window, use the 'Open File' dialog to locate the EASchema_1220_SQLServer.sql script file.
6	Click on the Open button. In the drop-down menu, check that you have selected the correct database to run the script in.
7	Click on the Execute button; SQL Server executes the script, which creates the base tables for an Enterprise Architect project.

#### **Notes**

- You should have ALTER permission on the t\_image table in Enterprise Architect, to be able to import model images
- When creating a project in a SQL Server database you must have 'db\_ddladmin' permission in order to execute the SET IDENTITY\_INSERT (table) {ON | OFF} command

## **SQL Server Security Permissions**

The security model implemented by Microsoft's SQL Server is quite powerful and highly configurable, supporting many different possible solutions for securing the data contained in SQL Server databases and ensuring it is only accessible to users with the required permissions. For a more detailed description and explanation of SQL Server permissions, see the SQL Server documentation.

Enterprise Architect users who plan to add, edit and delete contents in a SQL Server repository must have permissions to execute SELECT, UPDATE, INSERT and DELETE statements on all Tables in the Enterprise Architect database. The easiest way to achieve this is to grant the database roles of 'db\_datareader' and 'db\_datawriter' to each user.

### **Additional Permissions for Diagram Images**

When an Enterprise Architect repository has not been defined with the optional schema update (EASchema\_1220\_SQLServer\_Update1.sql) database users will require additional permissions in order to be able to perform Project Transfers and XML imports that include Diagram Images.

Why is this the case? In order for Enterprise Architect to be able to store unique images in each repository the value used as the key in T\_IMAGE records needs to be set, however

the original schema definition of the T\_IMAGE table did not allow this and as a result Enterprise Architect needed to execute SET IDENTITY\_INSERT T\_IMAGE {ON | OFF} commands, which requires higher permissions. ie. the role of 'db\_ddladmin'.

To avoid the need of each user to have an elevated level of permissions, an optional schema update (EASchema\_1220\_SQLServer\_Update1.sql) was developed which unfortunately is not backward compatible with earlier versions of Enterprise Architect. Therefore the optional schema update (EASchema\_1220\_SQLServer\_Update1.sql) should only be applied if all users are using Enterprise Architect 14 or later. see https://www.sparxsystems.com/resources/repositories/index.html

## Does Enterprise Architect support Windows Authentication?

Enterprise Architect does support Windows Authentication. However, the type of authentication is determined by the configuration of the connection used, and not by Enterprise Architect.

Windows Authentication to SQL Server is commonly used by Enterprise Architect users, but this requires that all Windows users in Enterprise Architect be defined on the SQL Server server and be granted the security roles 'db\_datareader' and 'db\_datawriter' for the repository.

# **Connect to a SQL Server Repository**

After you have created a Microsoft SQL Server database, you can connect to it immediately without any further configuration directly from Enterprise Architect.

## **Prerequisites**

- The Microsoft SQL Server database/repository already exists and you know the details
- You have the details of a database user with the required permissions within the database, see <u>SQL Server Security</u> Permissions
- Microsoft SQL Server OLE DB driver

#### Access

Ribbon	: Open Project
Keyboard Shortcuts	Ctrl+O

# **Connect to the repository**

In the 'Open Project' dialog, select the 'Connect to
Server' checkbox.
Click on the button.  The 'Data Link Properties' dialog displays.
<ul> <li>Select 'Microsoft OLE DB Provider for SQL Server' or 'Microsoft OLE DB Driver for SQL Server' from the list.</li> <li>Note: <ul> <li>'Microsoft OLE DB Provider for SQL Server' is usually part of the Windows Operating System, otherwise it can be installed as part of MDAC 2.8.</li> <li>'Microsoft OLE DB Driver for SQL Server' is a newly released driver that adds support for TLS v1.2 and other more recent features of Microsoft SQL Server (like multi-subnet failover capabilities). This driver is available from the Microsoft website.</li> </ul> </li> </ul>
Click on the Next>> button. The 'Connection' tab displays.

5	Type in the server details, including Server Name, User Name and Password.
6	Click on the 'Select the database on the server' option and on the drop-down arrow.  From the list, select the project to connect to.
7	Click on the Test Connection button to confirm that the details are correct.
8	If the test does not succeed, revise your settings.  If the test succeeds, click on the OK button; the 'Connection Name & Type' dialog displays.
9	Give the connection a suitable name so that you can recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
10	If required, select the 'Encrypt Connection String' checkbox.  This encrypts and hides the connection details of the database from the users that the connection string is given to.
11	If required, select the 'Lazy Load' checkbox to not load the full project view when the model is loaded; instead, only the parts that are necessary to display the visible portion of the tree are loaded.

	With this setting, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.
12	If required, select the 'Use WAN Optimization' checkbox.  Note: this option is only included for historical reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.  The WAN Optimizer was originally created to improve performance over a Wide Area Network by compressing all database requests from Enterprise Architect to reducing transfer times.  If you select this checkbox, complete the next two fields (see your administrator for the correct values); otherwise go to step 15.
13	In the 'Server' field, type the network name or address of the optimizer server.
14	In the 'Port' field, type the port on which the server is running on the remote machine.
15	Click on the OK button to complete the configuration and open the project.  This also adds the project name to the 'Recent' list on the Start Page; from now on, you can open the

project again just by clicking on this name.

### **Notes**

• Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions

# Create a Project in a Sybase ASA/SQL Anywhere Database

To create a project in a repository on Sybase Adaptive Server Anywhere 8 or 9, or SQL Anywhere 10, 11 or 12, you work through these stages:

- Stage 1: Create an empty database repository
- Stage 2: Set up the ASA ODBC Driver
- Stage 3: Set up initial data

# **Prerequisites**

- A machine with Adaptive Server Anywhere installed and running
- Install SQL Anywhere Studio, this also installs the ASA ODBC driver

## 1. Create Database Repository

Ste p	Action
1. 1	Create a new empty database.

1. 2	Open your SQL management console of choice (such as Sybase Central) and connect to the new database.
1. 3	Load the EASchema_1220_ SybaseASA.sql file from the Sparx Systems website.
1. 4	Run the EASchema_1220_ SybaseASA.sql to create the required database schema.

# 2. Set up the ODBC DSN

Ste	Action
p	
2.	Create a suitable ODBC Data Source using the
1	Sybase Adaptive Server Anywhere ODBC driver to
	the new database.

# 3. Set up Initial Data

Enterprise Architect repositories requires a basic amount of

reference data to function correctly. For Sybase ASA based models this can be achieved by transferring the contents of an existing model into the new database.

Ste p	Action
3.	In Enterprise Architect, open the existing repository and select 'Configure > Model > Integrity > Project Integrity' in the ribbon.
3. 2	Ensure that the Action is set to 'Report Only' and that all items in 'Checks to Run' are enabled, then click the Go button.
3.	If Enterprise Architect detects that the existing model contains integrity issues then these will be listed, these should be corrected before continuing with the Project Transfer.
3. 4	With Enterprise Architect open, ensure that it there is no Project loaded, by selecting 'Close Project' from the button.
3. 5	Select the 'Configure > Model > Transfer > Project Transfer' ribbon option.  The 'Project Transfer' dialog displays.
3.	In the 'Transfer Type' panel, select '.EAP to DBMS'.

6	
3. 7	In the 'Source Project' field, type the name of the project file to copy to the repository.  If the .EAP file has Replication enabled, this must be removed before performing the transfer.
3.	At the right of the 'Target Project' field, click on the button.  The 'Datalink Properties' dialog displays.
3. 9	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list. Click on the Next button.
3.	In the 'Use Data source name' field, click on the drop-down arrow and select the ODBC Data Source you configured to point to your new database. Click on the OK button. The 'Project Transfer' dialog redisplays.
3. 11	If required, select the 'Logfile' checkbox and type a path and filename for the data transfer log file.
3. 12	Click on the Transfer button to begin the data transfer process.
3.	When the process is complete, you have created a

project on an ASA database and can now connect to it and open it from Enterprise Architect.

# Create an Adaptive Server Anywhere Repository

Creating an ASA database is fully documented in the product information provided with your ASA installer.

There are many ways to create a new Adaptive Server Anywhere database, probably the most common is to use a SQL based Management Console like Sybase Central, which provides a convenient graphical user interface to enable the creation of databases, the execution of scripts, and backups and restores. However the exact method used is not important to this discussion, therefore you are free to use the most convenient or familiar method at your disposal.

Having created your ASA database, use the SQL script provided by Sparx Systems to create the required table definitions for Enterprise Architect. The EASchema\_1220\_SybaseASA.sql script is freely available on the <a href="DBMS Based Repositories">DBMS Based Repositories</a> page on the Sparx Systems website.

### **Notes**

• Ensure that the collation is set to the alphabet you use, such as Latin or Cyrillic

# Set up an ASA ODBC Driver

After you have created a Sybase ASA database, you will need to set up an ODBC DSN to the new database in order for Enterprise Architect to connect to it.

## **Prerequisites**

#### Install:

- Adaptive Server Anywhere SQL Anywhere Studio 8 or higher, and create a repository
- ASA ODBC driver software (installed with the ASA DBMS)

# Set up the ODBC Driver

Ste	Action
p	
1	Under both 32-bit and 64-bit operating systems, Enterprise Architect requires 32-bit ODBC drivers to connect to a repository through ODBC. You can quickly load the correct 32-bit ODBC Data Source Administrator by selecting the 'Configure > User Tools > ODBC Data Sources' ribbon option.

	The ODBC Data Source Administrator window displays.
2	Click on the Add button.  The 'Create New Data Source' dialog displays, enabling you to add a new DSN.
3	Select 'Adaptive Server Anywhere' or 'SQL Anywhere' from the list.
4	Click on the Finish button. The 'ASA Connector/ODBC' dialog displays.
5	<ul> <li>Enter these configuration details:</li> <li>A data source name for the connection, on the 'ODBC' tab</li> <li>User name and password on the 'Login' tab (dba, sql are the defaults when ASA is installed)</li> <li>The server name and the path to the database, on the 'Database' tab</li> <li>The network protocol on the 'Network' tab (if the database is on a network location)</li> </ul>
6	Return to the 'ODBC' tab and click on the Test Connection button to confirm that the details are correct.
7	If the test succeeds, click on the OK button to

complete the configuration.

If the test does not succeed, review your settings.

# **Connect to an ASA Data Repository**

To access a project in your Adaptive Server Anywhere (ASA) data repository, you must connect to the data repository from Enterprise Architect.

## **Prerequisites**

- The ASA repository and the project already exist
- You have SELECT, UPDATE, INSERT and DELETE access permissions
- The ASA ODBC driver has been set up

#### Access

Ribbon	: Open Project
Keyboard Shortcuts	Ctrl+O

# **Connect to the repository**

Ste p	Action
1	In the 'Open Project' dialog, select the Connect to Server button.
2	Click on the button.  The 'Data Link Properties' dialog displays.
3	Select 'Microsoft OLE DB Provider for ODBC Drivers' from the list.
4	Click on the Next>> button. The 'Connection' tab displays.
5	Click on the 'Use data source name' radio button and on the drop-down arrow in its field.  From the list, select the ODBC driver you have set up to connect to your ASA repository.
6	Click on the Test Connection button to confirm that the details are correct.
7	If the test does not succeed, revise your settings.  If the test succeeds, click on the OK button; the 'Connection Name & Type' dialog displays.
8	Give the connection a suitable name so that you can

	recognize it in the 'Recent Projects' panel on the 'Open Project' dialog.
9	If required, select the 'Encrypt Connection String' checkbox.  This encrypts and hides the connection details of the database from the users that the connection string is given to.
10	If required, select the 'Lazy Load' checkbox to not load the full project view when the model is loaded; instead, only the parts that are necessary to display the visible portion of the tree are loaded.  With this setting, the model loads faster and users can begin work sooner, but at the expense of later small delays as Enterprise Architect loads specific portions of the model.
11	If required, select the 'Use WAN Optimization' checkbox.  Note: this option is only included for historical reasons, the WAN Optimizer product has been replaced by the vastly improved Pro Cloud Server.  The WAN Optimizer was originally created to improve performance over a Wide Area Network by compressing all database requests from Enterprise Architect to reducing transfer times.  If you select this checkbox, complete the next two fields (see your administrator for the correct values);

	otherwise go to step 15.
12	In the 'Server' field, type the network name or address of the optimizer server.
13	In the 'Port' field, type the port on which the server is running on the remote machine.
14	In the 'DSN' field, type the data source name of the database as it appears on the remote machine.
15	Click on the OK button to complete the configuration and open the project.  This also adds the project name to the 'Recent' list on the Start Page; from now on, you can open the project again just by clicking on this name.


## **Notes**

• Connecting to DBMS based Repositories is available in the Corporate, Unified and Ultimate editions

# The WAN Optimizer

You can significantly improve Enterprise Architect's performance in a Wide Area Network (WAN) by reducing the amount of data transmitted and the number of network calls made. To achieve this, you can use the Sparx Systems Wide Area Network (WAN) Optimizer, a lightweight server installed on a Local Area Network (LAN) connection to a Database Management System (DBMS) that hosts an Enterprise Architect repository. You can configure the server to listen for client connections on a particular port; it acts as a local proxy to execute queries and return the results in a compressed format to the client.

In this diagram, transmission between Enterprise Architect and a DBMS is depicted first without and then with the WAN Optimizer.



You can download the WAN Optimizer installer from the 'Downloads' page of the Registered Users section of the Sparx Systems website. The Wan Optimizer Service installer package provides two installable features for the target machine:

- WAN Optimizer Service the installer also helps register and start the service on the target machine, and add it to the Windows Startup folder
- WAN Optimizer Admin Client to enable an administrator to administer and configure the service from

a remote client

The Optimizer has its own *Sparx Systems WAN Optimizer User Guide*. See that Guide for more information on:

- WAN Optimizer Components
- Installing and Starting the WAN Optimizer Service
- Configuring the Service
- Troubleshooting

#### **Notes**

- The WAN optimizer was the first generation product
- The Sparx Systems Cloud Services was the second generation and replaced the WAN optimizer
- The Sparx Systems Pro Cloud Server is the third generation and has replaced the Sparx Systems Cloud Services
- All Cloud products provided similar basic functionality of the WAN Optimizer, but the later generations do so faster and more securely; they also have many more additional features

Whilst you can still use the WAN Optimizer as described here, we recommend that the Pro Cloud Server should now be used instead of both the WAN Optimizer and Cloud Services products.

# **Cloud Based Repositories**



In terms of Enterprise Architect and Sparx Systems, Cloud based repositories are repositories that are hosted by the Sparx Systems Pro Cloud Server. The Pro Cloud Server is a supporting product to Enterprise Architect and allows Enterprise Architect repositories to be hosted anywhere in the world and encapsulates the retrieval of all repository data and serves it to Enterprise Architect clients for consumption.

Sparx Systems have designed the Pro Cloud Server to be installed in your company's infrastructure thereby giving you full control over its configuration but more importantly the data contained in your repositories. We use the term 'Cloud' to indicate that Enterprise Architect users can simply connect to a repository with a single URL without any further configuration or setup.

#### **Notes**

- Cloud Repositories are supported in Enterprise Architect Corporate Edition and above.
- Enterprise Architect Professional Edition also supports Cloud Repositories, though only those which are hosted on a Firebird database.
- An unlicensed installation of the Pro Cloud Server provides basic Cloud Repository functionality, allowing you to host Cloud repositories and access them via Enterprise Architect. With a valid license, the Pro Cloud Server provides a range of additional features.

# **Introducing Cloud Repositories**

The Sparx Systems Pro Cloud Server solution provides seamless access to Enterprise Architect models in repositories held anywhere in the world, providing high performance for remote access, secure encrypted links and optimization for high latency WAN connections.

Cloud based repositories provide easy access to models, not only for people within your local team but also for remote team members, external customers and consultants with Internet access, anywhere around the world. Collaborative and distributive modeling and design are dramatically enhanced by using a Cloud based repository, which can provide the shared backbone for a wealth of development scenarios.

#### This section will:

- 1. Familiarize you with the concepts of the Cloud Repositories
- 2. Discuss considerations of when and where you should use a Pro Cloud Server
- 3. Walk you through the process of setting up a Pro Cloud Server
- 4. Walk you through the process of connecting for the first time
- 5. Highlight some of the additional functionality available through licensing the Pro Cloud Server
- 6. Outline working with Active Directory using IIS

# **Benefits of Cloud Repositories**

Enterprise Architect models are stored in databases, such as MySQL, SQL Server and Oracle. Traditional installations of Enterprise Architect require each user to install the appropriate drivers for each DBMS, and in some cases define an ODBC DSN with the database connection details.

When connecting to a Pro Cloud Server, the procedure for a user to connect to a model is dramatically simplified. For users connecting to models hosted in a Pro Cloud Server only need a single URL, no special drivers or further configuration is required.

Connecting to a Pro Cloud Server provides a number of key benefits:

- 1. Improved performance for models used for distributed development. The Pro Cloud Server provides benefits to connections that involve high latency and reduced data transfer speeds.
- 2. The process of setting up drivers and connections is performed once by an administrator during the server configuration. The only set-up required on a user machine is to install Enterprise Architect and to connect to a model on the Cloud server.
- 3. Database servers no longer have to be exposed through a firewall; the Pro Cloud Server can be run from inside the corporate firewall. All model connections are created using HTTP/S, allowing firewalls to completely isolate

your database server.

- 4. A Pro Cloud Server can be configured to encrypt all communication. Using standard TLS/SSL protocols, you can be confident that your data is not intercepted during transmission on insecure networks.
- 5. A Pro Cloud Server can be configured to provide HTTP-level authorization to any model taken directly from the model user list. Even when the model is exposed on a public network, you can be assured that only authorized users are able to access your model.
- 6. A Pro Cloud Server can be configured to provide read-only access to any model; for example, for clients required to review a model.

## **Pro Cloud Server Features**

Even without a License, the Pro Cloud Server can be used for hosting Cloud Repositories to be accessed by Enterprise Architect (providing all the benefits mentioned above), however using a valid Pro Cloud Server license provides a number of additional benefits.

- WebEA, a web based application that allows users to view and discuss elements in Enterprise Architect models through a web browser, while on portable devices or remote desktop systems
- OSLC Restful API, provides an interface for external applications

- Integration Plugins, allow data from external providers to be displayed within Enterprise Architect
- Prolaborate, a team Sharing and Collaboration Software package
- The Sparx Systems Floating License Server
- Visibility Levels for Oracle and SQL Server 2016 based models, so that it is possible to restrict parts of the model from individual users or group of users

Sparx Systems Pro Cloud licenses are available in three different editions:

- Token Edition, is a scalable edition of the Pro Cloud Server. "Tokens" are allocated to enable specific features of the Pro Cloud Server and also determine the number of concurrent web users. There is no restrictions on the number of Tokens, you only purchase the number that suit your organization's needs
- Team Server Edition, supports up to seven repositories, and unlimited web users
- Enterprise Server Edition, supports any number of repositories, and unlimited web users

### Webinar

Before you go on to set up the Pro Cloud Server, Sparx Systems recommend that you watch the 'Setting Up Pro

## Cloud Server for Enterprise Architect' webinar.

You can also watch a <u>second webinar</u>, which demonstrates setting up a MySQL repository on the Amazon Web Services (AWS) Cloud using Amazon Relational Database Services (RDS), and creating and configuring an Enterprise Architect project in the repository via the Cloud connection.

# **Pro Cloud Server Setup**

This is an overview of the typical process for setting up the Pro Cloud Server.

# Typical steps for setting up a Cloud Server

Ste p	Description
P	
1	Install the Pro Cloud Server.
2	Review the default settings in the 'SSProCloud.config' file, in most environments these will be sufficient. However if necessary change the SERVER_PORT to suit your environment and Restart the Pro Cloud Server service.
3	Open the Configuration Client, by default a shortcut to this should be created on the Desktop.
4	Configure the Port(s) to be used for accessing your Cloud based models. If changes were made restart the Pro Cloud Server service.
5	Define connections to your repositories/models.

6	Configure your Firewall.
7	Test access to Cloud based model(s) from Enterprise Architect.
8	Optionally, if you are planning to use any Pro features such as WebEA or Integration Plugins, etc then your Pro Cloud Server will need to be 'licensed'. Refer to the License Screen topic for details.
9	Optionally, if you are using the Token edition of the Pro Cloud Server then you might want to adjust the token allocations (for example, enabling specific integration plugins).

## **Pro Cloud Server Installation**

The basic installation process is quite straightforward. Typically you can simply download, and run the installer on your server, then follow the prompts.

#### **Download the Installer**

The Pro Cloud Server installer can be downloaded from the 'Registered User' section of the Sparx Systems website.

# **Installation Steps**

If you already have the 'Sparx Systems WAN optimizer' or 'Sparx Systems Cloud Services' installed on your server we recommend you manually remove them before commencing the Pro Cloud Server Installation.

To remove any potential permission issues, we recommend that the installation is performed by a user with Administrator level permissions, to install follow these steps:

- 1. Run the SparxProCloud.msi installer
- 2. On the Welcome page, click the Next button.
- 3. Read the End User Licence Agreement, and accept the

terms outlined in it, and click Next button.

- 4. The Readme Information page contains the minimum system requirements, so make sure that the host server meets the outlined requirements, and then click the Next button.
- 5. The Custom Setup page allows you to choose what components of the Pro Cloud Server are installed, for the simplest installation (I.e. using the defaults), go straight to step 7.
- 6. If you want to install specific components, for example, to have different components on separate machines, refer to the Pro Cloud Server Components table below, then return here to step 7.
- 7. The Ready to Install page, is the last step before the installation begins, when ready click the Install button.
- 8. The installation progression will be shown and once finished the wizard should state that the process has completed, click the Finish button.
- 9. Now refer to the Pro Cloud Server Configuration Help topic.

https://sparxsystems.com//help/model\_repository/cloud\_ser ver configuration.html

To assist you in performing and understanding the installation process, watch the Sparx Systems webinar *Setting Up Pro Cloud Server for Enterprise Architect*. Click on the link to access this webinar.

# **Pro Cloud Server Components**

The 'Custom Setup' page lists the various components that are available in the installer. Each component can be controlled separately by clicking the small disk image in front of the component name and selecting the option you require.

Component	Description	
Pro Cloud Server service	This component is the Windows service that will accept connections from Enterprise Architect and the configuration client. For Pro Cloud Server, this includes the Sparx Systems Floating License Server. The default option is to install this component. Generally, the only time you would choose not to install this component is when you have already installed it on one machine and are now installing other	
	components on a different machine.	
Management Clients	When the Management Client component is selected the Pro Cloud Server Configuration Client application will be installed, which supports the execution of management tasks, including:  • Setting which databases a Pro Cloud	

	<ul> <li>Server can connect to</li> <li>Configuring those database connections</li> <li>Configuring what HTTP/HTTPS ports the Pro Cloud Server will listen on</li> <li>Configuring various server options</li> <li>The default option is to install this component; Sparx Systems recommends that the Configuration Client should be installed whenever the Pro Cloud Server service is installed.</li> </ul>
WebConfig	This component installs the application files (PHP, CSS and JavaScript) for the Web Base Configuration Client ("WebConfig").  The default option is to install this component; you can unselect this component if you do not plan to use the Web Based Configuration Client.
WebEA	This component installs the WebEA application files (PHP, CSS and JavaScript) that enable a web user to view an Enterprise Architect model on a mobile, android or remote desktop machine without having to install Enterprise Architect on that device.  The default option is to install this

	component; you can unselect this component if you do not plan to use WebEA.
Integration Plugins	Integration Plugins or Server Based Plugin Interface (SBPI), this component installs the SBPI Server and all the SBPI Plugins that allow the Pro Cloud Server to read data from external products such as Dropbox, Jira and Team Foundation Server. There is a separate SBPI Plugin for each external product.  The default option is to install this component; you can unselect the component if you do not plan to link your Enterprise Architect models to external products.
Visibility Levels	Visibility Levels; this component installs a set of SQL scripts to be applied to your MS SQL Server 2016 + or Oracle based Enterprise Architect repositories.  The default option is install this component; you can unselect this component if you do not plan to use the Visibility Level functionality.
IIS Integration	An optional component providing integration with IIS.

The default option is to not install this component; however, if your server requires advanced authentication methods available through IIS then this component should be installed.

# **Installing New Versions**

If you are installing a newer version of the Pro Cloud Server product then the new installer will automatically uninstall the old version. Before doing so, typically it is better to manually stop the 'Sparx System Professional Cloud' Windows service because the installer might have problems performing this task and will require the machine to be rebooted after the installation is finished.

Note: The installer has been designed to not override any configuration settings of a previous installation.

#### **Steps**

- 1. Run the installer using the earlier installation steps.
- 2. The installer will have copied the newest version of WebEA to the location specified during installation; if this location is not being used by your web server, you need to manually copy (and override) all WebEA files (except the includes/webea\_config.ini file) from the installation folder to the web server folder. See *WebEA Note*.
- 3. As above, if you use the WebConfig client you should

copy the contents of the WebConfig folder (specified during installation) to the appropriate location on your Web Server, overriding the existing WebConfig files (except settings.php).

Upgrading from PCS3 to PCS4 Note: With the release of Pro Cloud Server 4 and default installation folder has been changed to C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\ and the configuration filename changed to SSProCloud.config. This means that if you are upgrading from version 2 or 3 of the Pro Cloud Server to version 4 or later and you want to keep your existing configuration the old SSCloudServices.config file in C:\Program Files (x86)\Cloud Services\Service\ will need to be manually copied into the new installation folder, renamed from SSCloudServices.config to SSProCloud.config and the Pro Cloud Server Windows Service restarted.

Additionally because of the change of installation location all Firebird based database managers will need to be manually removed, their files physically moved from the old path to the new one and then re-added with PCS4.

Old Firebird model location:

'C:\Program Files (x86)\Sparx Systems\Cloud Services\Service\Models\'

New Firebird model location:

'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\Models\'

WebEA Note: In regard to WebEA, consider the situation

that WebEA was installed to the default location and your website is being served by Apache in

C:\Xampp\htdocs\webea, this command would perform the required copy and not override your existing configuration file in the live site:

robocopy "C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebEA" "C:\xampp\htdocs\webea" /MIR /e /DCOPY:T /njh /ndl /nfl /xf webea\_config\*.ini

**Firewall Note**: The installer creates a Firewall rule for the Pro Cloud Server. This rule is removed and re-created during an upgrade. If you had previously modified this rule then you will need to apply these changes again after the Pro Cloud Server installation.

## **Pro Cloud Server Configuration**

This topic discusses the configuration of the Pro Cloud Server. There are several other configuration files associated with the Floating License Server, WebEA and Visibility Levels components of the server. The procedures for editing those files are described in the separate topics for those features.

The SERVER\_PORT and SERVER\_PASSWORD need to be set by directly editing the configuration file **SSProCloud.config**, which is found in your Service directory. To edit the configuration file, open it in a text editor (using the 'Run as administrator' option).

A number of additional general options can be defined in the config file as described here; however, these can typically be left with their default values.

After defining the Server Port/Password, you can open the Pro Cloud Server Configuration Client - Application and configure Ports and Model/Database connections.

Note: It is important to realize that the Pro Cloud Server only reads the configuration file once, when it starts up. If you manually change the options in the configuration file then the Pro Cloud Server must be restarted.

### **Configuration Client Connection Settings**

Normally the first settings you will see in the configuration

file are to control how the Configuration Client will connect to the server. The default values are:

SERVER\_PORT=803 SERVER\_PASSWORD=

Use of the Configuration Client is discussed in the *Pro Cloud Configuration Client* topic.

Setting	Description
SERVER_P ASSWORD	SERVER_PASSWORD is the password to protect the administration functions of the server.  Note: This can be changed within the Configuration Client, which means a full server restart will not be necessary.
SERVER_P ORT	SERVER_PORT is used when you connect to the Configuration Client or opt to use the IIS integration instead of the integrated web-server. For more detail see the <i>Cloud Server Using IIS</i> Help topic.  Note: When changing this, check firewall settings and other services using the port. Additionally, when the service is running on Wine you should not use privileged ports - those below 1024. Under Wine, most applications are only able to listen on ports above 1024.

### **General Settings**

The next list of settings includes the default global settings across the entire service:

DBMAN\_DEFAULTMAXSIMQUERIES=10
AUDIT\_TIME\_PERIOD=3600
TEMP\_DIRECTORY=%SERVICE\_PATH%\Temp
LOGGING\_LEVEL=SYSTEM
LOGGING\_DIRECTORY=%SERVICE\_PATH%\Logs
LOGGING\_FILECOUNT=3
LOGGING\_FILESIZE=1048576

Setting	Description
DBMAN_DE FAULTMAX SIMQUERIE S	The default for the maximum number of simultaneous queries that can be run at a time for any configured database. This can be changed directly within the Management Client (see <b>Default Max Simultaneous Queries</b> under <i>Global Server Options</i> in the <i>Pro Cloud Server Configuration Client</i> topic). There is no explicit limit for this default value.  Note: if this setting is changed within a of the Configuration Clients, a full server

	restart will not be required.
AUDIT_TIM E_PERIOD	The number of seconds between the recording activities by system logs on each database.
TEMP_DIRE CTORY	The location to write temporary files before they are sent to clients. Generally you should not change this, as there are security implication. For example the owning user of the Windows service will need full write permissions to this directory.
LOGGING_ LEVEL	Determines how verbose the server should be when writing log files. The valid values are: OFF, FATAL, WARNING, INFO and SYSTEM. The value can be changed directly within the Management Client. (See <b>Log Level</b> under <i>Global Server Options</i> in the Pro Cloud Configuration Client - Application topic).  Note: if this setting is changed within a of the Configuration Clients, a full server restart will not be required.
LOGGING_ DIRECTOR	Defines where the log files are to be stored. The default is set to:

Y	%SERVICE_PATH%\Logs Note: The %SERVICE_PATH% refers to the directory where the Pro Cloud Server is installed. ie by default 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server'
LOGGING_ FILECOUNT	Determines the maximum number of rolling log files that should be kept. When the file count is exceeded, the oldest file is automatically deleted.
LOGGING_ FILESIZE	Determines the maximum file size of each log file. Whenever the current log file has reached its maximum size a new log file is created as 'SparxCloudServicesLog-1.log' and all older ones have their number incremented.  For more details on using the logs see the <i>Cloud Server Troubleshooting</i> topic.

## Restarting the Sparx Systems Professional Cloud service

If you make any manual changes to the configuration file

you must restart the service for the changes to take effect (unless otherwise stated). A service restart is carried out in the Windows Services application.

Depending on the operating system, there are two methods for restarting the Pro Cloud Server service:

1) Using Windows Services. This is available in all versions of Windows (see 'Control Panel | Administrative Tools | Services').





Figure 8: Start and Stop options for Cloud Services in the Windows Services view

2) Using the Server Manager on Windows Server 2012.



### **Pro Cloud Configuration Clients**

With the release of version 3 of the Pro Cloud Server, Sparx Systems now offers two different Configuration Clients, the original Windows based application and the new web based application. Each client is capable of managing the main settings of the Sparx Systems Pro Cloud Server. We expect that most users will prefer to use the web based application, although it does require one extra step during setup, to

install the web pages into a supported web server (like Apache or IIS).

Windows Application benefits

- no third party products required, you can connect to the Pro Cloud Server immediately after install using the default settings

Web based Application benefits

- can be configured to use SSL (HTTPS)
- one interface for all component settings

For details on each of the Configuration Clients, see the following topics:

Pro Cloud Server Configuration Client - Application
Pro Cloud Server Configuration Client - Web

# Pro Cloud Server Configuration Client - Application

At any point after installation you can configure the Pro Cloud Server using the Configuration Client application; the installer will create a **Pro Cloud Config Client** shortcut on the desktop.


By default the Configuration Client executable is accessible from the 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Client' folder.

The Configuration Client can be used from any machine on your local network; however, communications between it and the Pro Cloud Server are not secure, so it should only be used from within a secure network.

The Configuration Client is used to configure various settings related to the Pro Cloud Server and the repositories it connects to. When the application first starts, a prompt to enter the address of the Pro Cloud Server (see the Pro Cloud Server Logon Screen topic for details) you wish to connect to is displayed. Once you have connected, the main screen displays.

#### The Main Screen

This screen shows a list of all defined database managers and the details of the connected Pro Cloud Server. It is also the entry point for all management functions; like configuring your License, what ports the Pro Cloud Server listens on and the maintenance of database connections.



Sparx Systems Pro Cloud Server support connections to these DBMS products:

- Firebird
- Microsoft SQL Server
- MySQL
- Oracle
- PostgreSQL

Item	Description
Database Managers	This tab lists the defined repositories that the Pro Cloud Server makes available to clients. Each database manager definition contains the details of one database connection and a number of other properties that control how it will


	function.
Ports	This tab allows you to view and configure Ports which the Pro Cloud Server will allow connections on for accessing Models.
Integration	This tab allows you to configure Cloud Models to use Integration Plugins. Integration Plugins require a valid Pro Cloud Server license, see the Integration Plugins section for details.
Server Properties	The properties on the right hand side specify the details of the connected Pro Cloud Server.
	Main Properties
	<ul> <li>Server name - the server name hosting the currently connected Pro Cloud Server</li> </ul>
	• Configuration port - the port the Cloud Client is using for communication with the Pro Cloud Server
	<ul> <li>Server version - the major, minor and build numbers of the connected Pro Cloud Server</li> </ul>
	• Edition - the edition of the Pro Cloud Server

	<ul> <li>Expiry - the expiry date for the current license</li> <li>Licensed to - The name of the company which the Pro Cloud Server is licensed to.</li> <li>Licensee - The email address associated with this license. I.e. The email address which was provided when the License Request was created.</li> <li>Pro Models - the number of models enabled for Pro Features and the number allow by the current license</li> <li>The Edition, Expiry and Pro Models apply to Pro Cloud server licenses. If no license has been added, or the license is invalid, or it has expired, then the Edition will display 'None' and the Expiry 'Never'</li> </ul>
Extended Properties	Click on this button to display the extended properties for the connected Pro Cloud Server. A number of these extended properties can also be modified.
Licensing	Click on this button to view and manage the connected Pro Cloud Server's licenses. This button allows you to enter the license for the Pro Cloud Server.
Refresh	Click on this button to reload the contents

	of the 'Database Managers' list.
Add	Click on this button to add a new database manager.
Edit	Click on this button to view and manage the settings for the currently selected database manager.
Remove	Click on this button to permanently delete the selected database manager from the Cloud Server.

## **Pro Cloud Server Logon Screen**

The Pro Cloud Server Logon screen is the first to be shown when launching the Configuration Client, and at a minimum requires the address and port of the Pro Cloud Server to connect to.



### **Pro Cloud Server Logon**

Option	Description
Server Address	The Server Address format is: <pre></pre>

Password	Enter the password you defined in Configuration Client Connection Settings, in the Pro Cloud Server Configuration topic. By default this password is blank; you can set it to a new value, as described in the Help topic Global Server Options.
OK	Click on this button to log in to the Cloud Configuration Client.

## **Database Managers**

The list of Database Managers on the Pro Cloud Server Configuration Client's main screen displays all defined repositories that are accessible by Enterprise Architect clients and the main properties for each. Database Managers can be maintained (added, modified and deleted) directly from the main screen.

The Database Managers list includes the following details for each defined repository:


#### **Columns**

Option	Description
Database Manager	This column includes both a colored icon representing the enabled state (green for enabled, red for disabled) of the database manager and its connection string.
Alias	A unique name that identifies the repository. On Enterprise Architect's 'Cloud Connection' screen this is the value entered into the 'Model Name' field. An alias can be assigned when a database manager is defined, if this field is left

	blank the Pro Cloud Server will determine its value.
Connections	The number of active user connections and the maximum number of connections possible.  Note: typically the number of active user connections is zero, since they are only considered 'active' while a request is being processed, as soon as the data is returned to the client the connection is set to inactive. The number of connections is only refreshed when either the Refresh button is pressed or a change is made to a
	database manager's definition.
R/O	A flag to indicate if the database manager has been configured as Read-Only
SSL	A flag to indicate if the database manager has been configured to only allow secure connections
Pro	A flag to indicates if 'Pro features' has been enabled for the repository, this is controlled by the 'Enable Pro Features (OSLC, WebEA and Integration)' option on the Configure Database Manager screen.

## **Add Database Manager**

The Add Database Manager screen displays when you click on the **Add.**. button on the 'Sparx Systems Pro Cloud Server Configuration Client' screen; it allows you to define a new database connection to any supported DBMS.



The process for defining a Database Manager is subtlety different for each DBMS, each is explained on the following pages.

- Add Database Manager Firebird
- Add Database Manager ODBC
- Add Database Manager SQL Server
- Add Database Manager Oracle

#### The 'Alias'

It is important to note that the Pro Cloud Server uniquely identifies Databases by a single value; this value is referred

to as the database 'Alias'.

When adding a new database manager, the Alias can be specified using the 'Alias' field on the 'Add Database Manager' dialog.

If no Alias is specified, then a default Alias is determined using the following rules:

- Firebird definitions, the 'Alias' is the filename minus the extension
- ODBC based definitions, the 'Alias' is the 'Data Source'
- Oracle OLE DB based definitions, the 'Alias' is the Oracle 'net service name'
- SQLServer OLE DB based definitions, the 'Alias' is the 'Initial Catalog'

Therefore, take care when defining database connections, to ensure that you do not create duplicate database aliases. However, if two or more database definitions do share the same alias then all Enterprise Architect clients will connect to the first database found with the requested alias.

### **Relative path Note**


This note is shown on the Add Database Manager screen:

'Note: The Data Source Names and network paths provided by the Data Link Properties and ODBC Data Sources dialogs are relative to this machine and may need to be modified to match those on the server.' The purpose of this note is to inform the user that ODBC definitions are saved on each machine and that if the Pro Cloud Server Configuration Client is used to access a Pro Cloud Server on another machine the ODBC DSN definition list is relative to the client machine and not the machine hosting Pro Cloud Server.

This means if the Pro Cloud Server Client application is running on a remote machine (that is, not the machine running the Pro Cloud Server) the definitions that are shown by clicking on the button and ODBC Data Sources button are relative to the current machine and not the Pro Cloud Server machine, so care should be taken.

### **Default State of Added Database Managers**

As a safety precaution, whenever a new Database Manager is defined it is automatically configured to be disabled. You can enable the database after it has been initially defined by selecting the 'Enabled' checkbox on the Configure Database Manager screen.




## **Add Database Manager - Firebird**

Firebird based repositories are the simplest DBMS to add to the Pro Cloud Server and can be either completely new or an existing repository.

#### **New Firebird Repository**

To add a completely new repository, just enter the physical file name of the new model and click OK. ie MyFireBird.feap.



The Pro Cloud Server will automatically create a new empty Enterprise Architect repository database and add it to the list of defined Database Managers on the main Pro Cloud Server Configuration Client screen.

#### **Existing Firebird Repository**

To add an existing Firebird database to your Pro Cloud

Server environment, the physical file must first be copied into the 'Models' folder in the Pro Cloud Server's installation folder (the default being 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\Models'), this ensures the Pro Cloud Server has the necessary security permissions to the file.

Once the existing file is placed in the 'Models' folder, simply enter the filename of the database in the 'Add Database Manager' screen and click OK. Your existing database will then be added to the list of defined Database Managers on the main Pro Cloud Server Configuration Client screen.

### **Background Information**

Firebird is a free, open source rational database that runs on a variety of platforms. Firebird is very sophisticated and offers great concurrency, scalability and performance. It can be used in an enterprise setting and has been used in production systems, under a variety of names, since 1981.

To discover more about the Firebird database, please visit this website:


http://www.firebirdsql.org/en/about-firebird/ You can view the webinar by clicking on this link:

https://sparxsystems.com/resources/webinar/model-repositor y/cloud/introduction/introduction-cloud-services.html

## **Add Database Manager - ODBC**

Pro Cloud Server connections to MySQL, Oracle and PostgreSQL based databases require the use of ODBC DSNs, which need to be defined in the Windows 'ODBC Data Source Administrator (32-bit)' screen. If you are running the Configuration Client on the same machine as the server you can:

- 1. Click on the button to open the 'Data Link Properties' dialog to build the connection string.
- 2. Select the provider 'Microsoft OLE DB Provider for ODBC Drivers' and click on the Next >> button.
- 3. Select the pre-defined System DSN from the 'Use data source name' field.
- 4. Fill in the user name and password and select the 'Allow saving password' checkbox.



#### Notes:

- All ODBC DSNs should be defined as SYSTEM DSNs, because the Pro Cloud Server runs as a Windows Service and User DSNs might not be available to the Pro Cloud Server
- The step for filling in the user name and password might not be required if the user name and password have been saved with the ODBC DSN
- The ODBC Data Sources button displays the Windows 'ODBC Data Source Administrator' dialog, which you can use to set up a new ODBC system data source to be listed on the 'Data Link Properties' dialog (if you are running the administration client on the same machine as the server);

it is particularly helpful because it shows the 32-bit ODBC data sources.

## Add Database Manager - SQL Server

Pro Cloud Server connections to SQL Server based databases requires the use of an OLE/DB driver, currently Sparx Systems Pro Cloud Server supports both the historical "Microsoft OLE DB Provider for SQL Server" (that has been included with MDAC for many years) and the newly released "Microsoft OLE DB Driver for SQL Server". With the latter supporting TLS v1.2 and other new features released with the later versions of SQL Server.

#### Authentication

The SQL Server OLE/DB drivers support two forms or database authentication, both of which are supported by Sparx Systems Pro Cloud Server:

- 1. Windows Authentication / Windows NT Integrated security (or SSPI) and
- 2. SQL Server Authentication / "specific user name and password"

Many Sparx Systems customers expect the 'Windows Authentication' option to use the authentication details of the end user logging into Enterprise Architect, however this is NOT the case. When this option is selected it is actually the credentials of the owning user of the Sparx Systems Professional Cloud Windows Service that are used to

authenticate against the database. Which by default is 'Local System'.

Credentials are needed to establish a database connection, however it is a relatively slow process, if the Pro Cloud Server was required to establish a connection to the database using the end user's details for every query, performance would be severely impacted. Instead the Pro Cloud Server creates a 'pool' of database connection when it starts. Database connections from the pool are allocated to action each requests for data as they arrive, and since they have already been established execution is almost instantaneous.

Therefore when defining database connections to SQL Server based repositories special consideration should be made to determine the best/most appropriate database credentials for your environment. Typically we recommend the use of SQL Server authentication with the use of a predefine SQL Server user, however for many customers the SQL Server authentication method goes against their company's security policy, so therefore they need to either change the owning user of the Sparx Systems Professional Cloud Windows Service to one that has the necessary permissions in SQL Server or grant the Local System account permissions to the SQL Server database.

#### **Roles / Permissions**

In order for end users of Enterprise

Architect/WebEA/Prolaborate etc to be able to read and update information within the repository, the database users requires the relevant permissions, the easiest way to achieve this is to grant the following roles to each database user:


```
db_datareaderdb_datawriter
```

## Add SQL Server database using SQL Server authentication

Prior to defining the Pro Cloud Server connection, define a SQL Server user with and roles to the database that will act as the Enterprise Architect repository.

You can define a connection to a SQL Server Database by specifying the connection string to the database. If you are running the Configuration Client on the same machine as the server you can:

- 1. Click on the button to open the 'Data Link Properties' dialog to build the connection string.
- 2. Select 'Microsoft OLE DB Provider for SQL Server' or 'Microsoft OLE DB Driver for SQL Server' and click on the Next >> button.
- 3. Select or type in the instance of SQL Server.
- 4. Select the 'Use a specific user name and password' checkbox and fill in the user name and password, then select the 'Allow saving password' checkbox.
- 5. Select the database that is the Enterprise Architect



repository in 'Select the database on the server'.

## Add SQL Server database using Windows authentication

Help

Cancel

You can define a connection to a SQL Server Database by specifying the connection string to the database. If you are running the Configuration Client on the same machine as the server you can:

- 1. Click on the button to open the 'Data Link Properties' dialog to build the connection string.
- 2. Select the provider 'Microsoft OLE DB Provider for SQL

Server' or 'Microsoft OLE DB Driver for SQL Server' and click on the Next >> button.

- 3. Select or type in the instance of SQL Server.
- 4. Select the 'Use Windows NT Integrated security' checkbox.
- 5. Select the database that is the Enterprise Architect repository in 'Select the database on the server'.



#### Note:


 Because the Sparx Systems Professional Cloud Windows service is run under a single account, all database access will be under that account, so it will not be possible to keep track of what records are updated in the database by individual end users, however internally Enterprise Architect can store audit history if required.

## **Add Database Manager - Oracle**

Pro Cloud Server connections to Oracle based databases requires the use of either ODBC or OLE/DB drivers, although Sparx Systems tends to recommend the use of OLE/DB since it provides superior performance compared to ODBC.

You can define a connection to an Oracle Database (via OLE/DB) by specifying the connection string to the database. If you are running the Management Client on the same machine as the server you can:

- 1. Click on the button to open the 'Data Link Properties' dialog to build the connection string.
- 2. Select the provider 'Oracle Provider for OLE DB' and click on the Next >> button.
- 3. Type in the name of the 'Data Source'; this is the Oracle net service name as defined in the TNSNAMES.ORA.
- 4. Fill in the user name and password and select the 'Allow saving password' checkbox.




#### Note:

• The Pro Cloud Server identifies databases by the 'Data Source' value and Oracle OLE DB defines the 'Data Source' as the net service name, so it is only possible to access one Oracle repository per net service name; the workaround to this limitation is to define multiple net service names in TNSNAMES.ORA that differ only by name

# **Configure Database Manager**

The Configure Database Manager screen is shown when you click on the **Edit...** button on the 'Sparx Systems Pro Cloud Server Configuration Client' screen. It allows you to modify the various options for the selected Database.



# **Options**

Option	Description
--------	-------------

Database Manager	Read-only field showing the description of the database as shown in the 'Database Manager' List. The format of the description quickly describes the database, as shown here:  {odbc provider}:{user}@{datasource}
Enabled	Select this checkbox to allow the Data Manager to respond to requests for the connection.
Alias	The database Alias. This is the value Enterprise Architect clients will need to enter in the 'Model Name' field of the 'Cloud Connection' screen. Whenever a database manager is created the system will define a value for Alias automatically but if necessary you can change this value to a more meaningful or appropriate name for your Enterprise Architect and WebEA or users.
Database Type	Read-only field showing the DBMS of the defined database, such as Firebird, MySQL, Postgres, SQLSvr or Oracle.
Connection String	Read-only field showing the full connection string used to connect to the

	database.
Copy Button	A convenience button for copying the connection string to the clipboard.
Max Simultaneous Queries	Type in the maximum number of queries that the Pro Cloud Server can process simultaneously for the selected Database Manager. You can use the up/down arrows to adjust this figure to balance resource usage with concurrent user performance.  There is no explicit limit for this value, but the higher the value the more resources are consumed on your server, without a matching increase in benefit in user performance. Connections are held so briefly that the reduction in user wait time due to more connections being opened is not usually noticeable. If you are reaching the number of queries/connections you have defined here, increase it by small increments.
Minimum EA Build	Optional. If you want to ensure that all users of the model are on an appropriate build of Enterprise Architect, type in the lowest build number required.

OSLC Access Code	Optional. Type in the access code that all OSLC clients, including WebEA, are required to send in an HTTP header.  Leave blank to indicate that the OSLC clients are not required to send an access code.
Require a secure and authenticated connection	Select this checkbox to ensure that all clients (Enterprise Architect, WebEA,Prolaborate etc) connecting to this Database Manager must use SSL authentication.
Read-only connection	Select this checkbox to prevent users from modifying the database.
Enable Pro Features (OSLC, WebEA and Integration)	This option is only available in Pro Cloud Server editions. A checked state indicates that the current model has 'Pro Features' enabled, which includes OSLC, WebEA and Integration to external systems.  If this option is disabled then the reason for disabling it will be shown in the text
	for disabling it will be shown in the text. For example:  No License - There is no license defined
	or the license has expired
	Model Limit Reached - Both the 'Token' and 'Team' editions of the Pro Cloud Server are limited to a certain number of

	models that can be Pro-enabled; this reason code implies the maximum number of models has already been Pro-enabled
Run Scheduled Tasks	When this option is checked the Pro Cloud Server will update Time Series charts in the current model as a schedule task.
Periodically Generate Diagram Images for WebEA & Prolaborate	This option is only available in Pro Cloud Server editions when a Database Manager has Pro Features enabled.  In order to generate diagram images and linked documents (which are required by WebEA and Prolaborate) a 'worker' can be configured to run periodically, the Pro Cloud Server is capable of automatically starting these workers whenever it starts.
	To configure a worker, check this option, then click the 'Configure' button.  On the 'Configure Worker' screen enter the configuration details for the following fields:  Connection String: this value is a EA connection string or path to an EAP shortcut file (located on the Pro Cloud

	Server machine), which the Worker application will use to access the current model.
	Update Period: this value defines how often the Worker process will check for modified diagrams, and generate where required. The default value is 30 seconds.
OK	Click on this button to save the settings and close the dialog.

# Obtain Database Manager Connection String

Each Cloud Connection / Database Manager definition includes a connection string which the Pro Cloud Server uses to access the Project / Database.

This connection string can be particularly helpful in diagnosing issues when connecting to the Cloud Model. You can obtain the connection string either via the Cloud Configuration Client Application or the Cloud Configuration Web interface (WebConfig).

# **Cloud Configuration Client**

To obtain the connection string via the Cloud Configuration Client Application:

Ste p	Description
1	Open the Cloud Configuration Client.
2	In the list of defined Database Managers, select the relevant Database Manager then click on the Edit button.
3	The Configure Database Manager screen is

	displayed. This includes the Connection String field.
4	Click on the Copy button which is located next to the Connection String field.


# WebConfig

To obtain the connection string via the Cloud Configuration Web Interface (WebConfig):

Ste	Description
p	
1	Login to the WebConfig home screen.
2	Locate the relevant model in the Model Connections list. Click on the Edit Connection button in the Action column.
3	The Edit Model Connection page is displayed. Click on the Advanced heading to expand its contents.
4	Click on the Copy button which is located next to the Connection String field.

# **Extended Server Properties**

The Extended Server Properties screen displays when you click on the 'Extended Properties' button on the Main screen. It helps you to configure the global options applied to the Pro Cloud Server. Each of these options can also be set in the configuration file; however, the service does not require a restart if the options are changed using this screen.



# **Options**

Option	Description
Audit Time	Read-only value showing the number of

Period	seconds between audit reports.
Default Max Simultaneous Queries	Provides a default value for the setting of 'Max Simultaneous Queries' when defining new database managers.
Logging File Count	Read-only value showing the number of log files that should be retained. All logging is written to files named 'SparxCloudServicesLog-X.log' where X represents the file number.  File 'SparxCloudServicesLog-1.log' is always the current file. When the maximum file size is reached, all existing files are renamed by incrementing the file number and a new 'SparxCloudServicesLog-1.log' created.
Logging File Size	Read-only value showing the maximum file size of each log file. When the file reaches this maximum, a new file is created.
Log Level	Click on the drop-down arrow and select the level of information to be written to the log file. The valid options are:  OFF - No logging is performed  FATAL - Only fatal errors are logged


	WARNING - Warning are logged INFO - Information messages that provide general message advising what actions are occurring SYSTEM - More detailed messages Log Levels are cumulative, for example the INFO level includes all messages of type FATAL, WARNING and INFO
Logging Directory	Read-only value showing the physical directory into which the log files are saved.
License Store	Displayed when using the Pro Cloud Server. Displays the path of the license store file, by default this is C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\sskeys.dat
Temp Directory	Read-only value showing the physical path of the temp directory, by default this is C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\Temp.
Set New Password	Select this checkbox to set/change the administrator password for the currently connected Pro Cloud Server. If a Password is set then all users attempting to use the Pro Cloud Server

Configuration Client will be required to
provide the specified password.


# **Pro Cloud Server Licensing**

The 'Pro Cloud Server License Manager' screen displays whenever you click on the Licensing button on the Main screen. It allows the user to quickly and easily see what Pro Cloud Server licenses have been defined, and the complete details of each license.

On a new installation, when the 'License' screen is first shown it should resemble this:



However, over time as your Pro Cloud Licenses expire you will be able to see a complete history of all licenses:



In the above example the current Token license is valid from February 3rd, 2019 to February 4th, 2020 and has 5 tokens. If there is any kind of problem with the license the 'Valid' column will show the reason, this message is also written to the current log file.

#### License Procedure

As of Pro Cloud Server version 4.0.30 the licensing procedure has been enhanced. Pro Cloud Server licenses are now linked to the host machine, which is an enforcement of what was stated in the license agreement. To add a License, the basic procedure to follow is:

- 1. Purchase the desired Pro Cloud Server license
- 2. Create a 'License Request' from the Pro Cloud Server machine
- 3. Send the 'License Request' file to the Sparx Systems Sales team
- 4. The Sparx Systems Sales Team will then return the 'License Certificate'
- 5. Add your 'License Certificate' to your Pro Cloud Server installation
- 6. Your Pro Cloud Server is now licensed!

Along with the change to Licensing procedures Pro Cloud Server 4.0.30 introduced the 'Token' Edition, which provides a more flexible upgrade path by making use of tokens that can be purchased separately at any time to enable only the extra functionality your environment requires.

For the premium editions (Team and Enterprise) the enabled functionality remains unchanged except for the Team edition now allows 7 Pro enabled models which has been increased by 2 compared to earlier versions.

### Class

As shown in the above screen shots, the Pro Cloud Server Licensing screen contains a list of Licenses and a selection of action buttons, which are described below:

Li	<ul> <li>The list of Licenses displays a historically record of all Licenses for the current Pro Cloud Server. Each License will display the following details/columns:</li> <li>License Type (one of Token, Team or Enterprise)</li> <li>Token Count, the number of Token associated with the License</li> <li>Company, the name of the company which the Pro Cloud Server is licensed to</li> <li>Email, the email address associated with this license. I.e. The email address which was provided when the License Request was created.</li> </ul>

- Start Date, the date the License is valid from
- Expiry Date, the date the License expires on
- Valid, a value of 'True' to indicate the current license is loaded, otherwise an error message describing why it is not valid

Cr ea te R

eq

ue

st.

The Create Request.. button is permanently visible on the Pro Cloud Server License Manager screen. Selecting this button will display the 'New License Request' screen, which allows the user the create a new Pro Cloud Server License request.

\_\_\_

A The Add.. button is permanently visible on the Prodd Cloud Server License Manager screen.

... Selecting it will prompt the user to select a Pro Cloud Server License Certificate file (\*.CRT) in the file system.

R e m

ov

e

The Remove button is permanently visible on the Pro Cloud Server License Manager screen, however it is only enabled when a License is selected in the list.

Selecting this button will remove the selected Pro Cloud Server License from list.


If the Remove action was performed by mistake the License Certificate file (.CRT) will still exist in the

	file system under, {installation path}\Licenses\deleted\ folder. Therefore to reinstate the deleted license, manually copy the {GUID}.CRT from the \deleted\ folder to {installation path}\Licenses\ and restate the Pro Cloud Server.
R en e w.	The Renew button is permanently visible on the Pro Cloud Server License Manager screen, however it is only enabled when a License is selected in the list.  Selecting this button will display the 'New License Request' screen, however some of the fields will be pre-populated with the details of the selected License.
M an ag e Al lo ca tio ns	The Manage Allocations button is only visible when the selected Pro Cloud Server License is a Token license.  Selecting this button will display the 'Manage License Token Allocations' screen, which allows the user the control the minimum and/or maximum number of Tokens associated to each Pro Feature.

# **Create Request**

The 'New License Request' screen is displayed when the Create Request.. button is selected on the 'Pro Cloud Server License Manager screen. The purpose of this screen is to create a license request for the connected Pro Cloud Server installation.

The 'New License Request' screen will initially be displayed as:



The creation of a License Request is required after purchasing a Pro Cloud Server license, the License Request help Sparx System identify and registry what hardware is going to host the Pro Cloud Server.

#### Class


The 'New License Request' screen consists of the following

# input details:

Company Name	Mandatory value. The name of the company that made the Pro Cloud Server purchase.
Email	Mandatory value. The email address associated to the Pro Cloud Server purchase.
Installation ID	Mandatory value. The unique GUID that was supplied in the confirmation email of your Pro Cloud Server purchase.  If you purchased your Pro Cloud Server license prior to Jun-2019, use your Pro Cloud Server version 3 License key.
Start Date	Optional value. Use this date to request that your Pro Cloud Server License should start on a future date. If no value supplied the Sparx System Sales Team will assume the current date.
Comments	Optional value. Any additional comments that might be helpful to the Sparx Systems Sales Team.

#### Class


In order to minimize any potential delays please provide the Sales Team with as much detail as possible about your Pro Cloud Server License purchase. For example:




Once entry of all Pro Cloud Server purchase information is complete, clicking the OK button will prompt to save the resulting License Request to the file system. This file should then be emailed to the Sparx Systems Sales team, sales@sparxsystems.com

## Add a new License

The Sparx System's Sales Team will reply with your License Certificate, when this occurs click the Add... button on the License screen and select the supplied License Certificate file (\*.lic or \*.crt). The details of the License Certificate will be loaded and shown on the License screen, similar to:



When the License screen is closed the main screen will now reflect the new License in the Server Properties section:



## Remove a License


At any time it is possible to remove an existing Pro Cloud Server License simply by selecting the license in the list on the 'Pro Cloud Server License Manager' screen and pressing the Remove button. The list of allocated licenses will be refreshed accordingly, there is no need to restart the Pro Cloud Server, the internal License and all related functionality enabled (or disabled) by the change/removal of a License will take effect immediately.

## Renew a License

On the 'Pro Cloud Server License Manager' screen, the Renew button will be enabled whenever a License is selected in the list of licenses, it is a convenience function which displays the same License Request screen that the Create Request button shows, however the difference is that the Renew option will pre-populate the valid details of the selected License, the remaining fields will still need to be filled in manually. The renewal process is the same as the initial process and will need to be repeated whenever the License expires.

# **Manage Allocations**

The 'Manage License Token Allocations' screen is displayed when the Manage Allocations... button on the 'Pro Cloud Server License Manager' screen is pressed. This screen allows the user to control how tokens are consumed to enable Pro Feature functionality.



The Manage Allocations screen is broken up into 3 sections, a Summary of token usage, Explicit Allocations, and allocations of tokens which are shared for Web Access.

#### **Token Summary**

The token summary lists the following:

Total - The total number of tokens based on the active license/s.

Explicit - The number of explicit token allocations. These refer to tokens which have been allocated to enable specific features on the server.

Shared - The number of shared tokens which are available. Shared tokens are consumed when users access features such as WebEA. When logging out the token is returned to the shared token pool.

Click on the Usage button to display a more detailed break down of the token allocations, including how many tokens are currently in use.

#### **Explicit Allocations**

This section allows you to enable Integration Plugins for your Pro Cloud Server. Enabling integration with a specific product (e.g. Jira) consumes one token.

#### **Shared for Web Access**

WebEA, Prolaborate and OSLC users consume a single token with every logon. For most environments these allocations can be left with their default values (0 reserved and no maximum). In this case all users are accessing a single shared pool of tokens, regardless of what type of access (WebEA, Prolaborate or OSLC) they require.

Alternatively, each user type can define a number of tokens that are reserved (ie. can only be used by that type of access) as well as a maximum number.


Note: a **Max Allowed** value of 0 implies that users are NOT allowed, ie if WebEA's Max Allowed value was set to 0, the Pro Cloud Server would deny all WebEA user requests to logon.

Note: a empty value for **Max Allowed** implies there is no limit on the number of users, although the total number of users is still limited to the number of available tokens.

# **Port Configuration**

When setting up the Pro Cloud Server you will need to define at least one Port which will be used for communication between the Pro Cloud Server and Enterprise Architect when accessing a Cloud model.

Ports can be configured via the Ports tab in the Cloud Configuration client.



#### The Ports Tab

The 'Ports' tab provides information and a number of options:

Item	Description
Port List	The main area of the Ports tab provides a

list of the existing Port definitions. These Port settings are also covered in more detail in the Add a Port Definition topic. **Columns** Port - The Port Number Protocol - Displays the transfer protocol, http or https that the Port has been configured to communicate on. OSLC Supported - Displays True if OSLC support is enabled for this port. OSLC Support is required for WebEA access. Default Model - If the port is configured to open a specific default model, it's name is displayed Authentication - Indicates what type of Authentication is required (if any). Resource Located in the lower left of the Ports Tab,

this button can be used to open the

Monitor


	Windows Resource Monitor. This allows you to check which Ports are already in use before adding a new Port Definition.  Please note: this will open the Windows Resource Monitor for the current machine, which is only relevant if the Configuration Client is running on the machine hosting the Cloud Server.
Add	Click on this button to add a new Port Definition.
Edit	Click on this button to edit the configuration of the selected Port. Editing a Port provides the same options as when adding a new one, however the Port number cannot be changed.
Remove	Click on this button to permanently delete the selected Port Configuration

## **Add a Port Definition**

As mentioned in the *Port Configuration* topic, when setting up the Cloud Server you will need to define at least one Port for communication between the Pro Cloud Server and Enterprise Architect.

#### To add a new Port Definition:

- 1) Open the <u>Pro Cloud Server Configuration Client -</u> <u>Application.</u>
- 2) Select the Ports tab.
- 3) Click on the Add button.
- 4) The Add TCP Port dialog will be display. Referring to the table below, enter the Port details, then Click OK.
- 5) Confirm that your <u>Firewall Settings</u> are correct.
- 6) Restart the Pro Clioud Server Windows Service so that the changes take effect.



## **Add TCP Port**

Field	Description
Server Port	Enter the Port number to be used for Cloud Connections.  Each defined Port must be unique and not used by any other service or application on the current machine. The standard HTTP Port (80) and HTTPS Port (443) are no different; if they are available, the Pro Cloud Server can be configured to use them. You can use the Windows Resource Monitor (which is accessibly via an icon on the Configuration Client 'Ports' tab) to check which Ports are already in use.

Firewall Note: When changing or adding a new Port, check that incoming requests are allowed by the firewall settings at both the local machine and network levels.

Wine Note: When the service is running on Wine you should not use privileged Ports - those below 1024; under Wine, most applications are only able to listen on ports above 1024.

#### **Protocol**

Select the protocol that the port will be configured as, options are:

HTTP - The default value

HTTPS - When this option is selected, you will be presented with four additional checkboxes which control the what versions of TLS (and SSL) are allowed on the given port.



Additional for HTTPS to be configured correctly a file named *server.pem*, must also exist in the same directory as the configuration file, and it must contain a valid private key / certificate. For more details on *server.pem* see the *SSL Certificates* section.

OSLC Supported	Enable this option to allow OSLC access to Models.  Note, WebEA makes use of OSLC. If you intend to access Models via WebEA then this option should be enabled.
Default Model	Optionally, enter the name of a default model which will be used by OSLC.  Typically OSLC URL's include the model name. If a default model has been specified then the model name can be omitted from the URL.
Authentication	Select the type of authentication that will be required for this Port:  Model - All model connections that use the current port will be forced to request HTTP authorization using the user security defined in the Enterprise Architect model being connected to. Passwords must be explicitly and individually assigned in that model using the Maintain Users procedure; the default administrator password and any passwords imported from Windows Active Directory do not work.  Note, if you are not using SSL to connect, the usernames and passwords will be sent

in plain text.

If the model does not have security enabled, the Cloud user is not prompted for a password.

Global - Selecting this option displays an additional Global Model field. In this field enter the name of a model which will be used to provide the security profile to all connections opened with the current port. This is helpful if you want to provide multiple models but only manage one list of users. Passwords must be explicitly and individually assigned in the reference model using the *Maintain Users* procedure; the default administrator password and any passwords imported from Windows Active Directory do not work.

Note, if you are not using SSL to connect, the usernames and passwords will be sent in plain text. Global authentication should only be used with the HTTPS protocol.

## **SSL Certificates**

In order for the Pro Cloud Server's internal Web Server to start a port using SSL, two individual files, **cacert.pem** and **server.pem** are required in the same folder as the Pro Cloud Server configuration file.

- cacert.pem contains a collection of trusted certificates (in .X509 format); that is, CA certificates
- **server.pem** contains a certificate and private key (in .X509 format) for your server

Sparx Systems do not supply a server.pem, because typically SSL certificates have to include the current server's details as well as individual details about your organization. Although this is an additional step, it is a particularly good idea to apply it if you are providing access to external users. Creating and signing a SSL certificate for your Cloud Server should be performed using an appropriate certificate authority (CA).

However, to help with initial setup and testing purposes, or for setups that are entirely within a closed network, you can generate your own self-signed certificate.

In general, self-signed certificates are not trusted by major browsers or operating systems and will generate errors or warnings visible to end users. See the <u>Self-Signed SSL</u> <u>Certificates</u> section on how to create a self-signed certificate.

To add trust to a self-signed certificate when it is not practical to generate globally trusted certificates, see Add

#### Trust with a Certificate Authority (CA).

Note: If the Pro Cloud Server is started without a valid server.pem file and a port is defined with Protocol=HTTPS then the internal web server will not be able to open the port. If this situation occurs, error messages to this effect will be written to the .LOG file.

### **Advanced Port Configuration**

Optionally, Ports can also be configured by directly editing the Cloud Server's configuration file (SSProCloud.config). This allows some additional settings which are not available in the Cloud Configuration Client.

The definition of a Port is denoted in the configuration file, with open and close parentheses, each on their own lines without any leading whitespace. Inside the parentheses contain a number of supporting options that control and limit how the port can be used. All options except SERVER PORT are optional.

```
SERVER_PORT=804
REQUIRE_SSL=0
OSLC_SUPPORT=1
DEFAULT_MODEL=
MODEL AUTHENTICATION=
```

```
GLOBAL_AUTHENTICATION=user model
EA_MINIMUM_BUILD=
EA_MAXIMUM_BUILD=
SSL_PROTOCOLS=SSLv3 | TLSv1 | TLSv1_1 |
TLSv1_2
)
```

## **Settings Explained**

Setting	Description
SERVER_P ORT	This option expects a numeric value (whole number) that defines a Port number; there is no default value.  For example, SERVER_PORT=804 states that the Pro Cloud Server service will listen to HTTP connections on port 804. Each defined port must be unique and not used by any other service or application on the current machine. The standard HTTP port (80) and HTTPS port (443) are no different, if they are available the Pro Cloud Server can be configured to use them.  Firewall Note: When changing or adding a new port, check that incoming requests

	are allowed by the firewall settings at both the local machine and network levels.  Wine Note: When the service is running on Wine you should not use privileged ports - those below 1024. Under Wine, most applications are only able to listen on ports above 1024.
REQUIRE_S SL	This option expects either a value of 0 or 1; the default is 0.  A value of 1 will enforce the use of SSL on the current port; that is, all connections must be performed using HTTPS, which is useful when connections need to be exposed on public networks.  In order for the Pro Cloud Server to be able to successfully configure ports as REQUIRE_SSL=1, a file called server.pem must exist in the same directory as the configuration file, and contain a valid private key / certificate. For more details on server.pem see the SSL Certificates section.
SSL_PROTO COLS	This option is a pipe delimited list of TLS/SSL protocol versions accepted by the port. If omitted the default of

	TLSv1_2 value is assumed. Valid values are "SSLv3", "TLSv1", "TLSv1_1", "TLSv1_2". For example if a port was to accept versions TLS 1.2 and 1.1 and entry should be:  SSL_PROTOCOLS=TLSv1_1   TLSv1_2
OSLC_SUPP ORT	This option expects either a value of 0 or 1, the default is 1.  A value of 1 defines that connections that use the current port will be able to perform queries using the 'Open Services for Lifecycle Collaboration' standard.  This is discussed further in the OSLC Requirements Management topic.
DEFAULT_ MODEL	This option expects the alias of a defined database manager, or blank, the default is blank.  By defining a value for this option allows a single model to be exposed on a port, making it possible to use a different port for each model. Model names are discussed further in the <i>Connecting Enterprise Architect to a Cloud Server</i> topic.
MODEL_AU	This option expects either a value of 0 or

#### THENTICA TION

1, the default is 0.

By defining this option as 1, all model connections that use the current port will be forced to request HTTP authorization using the user security defined in the Enterprise Architect model being connected to. Passwords must be explicitly and individually assigned in that model using the *Maintain Users* procedure; the default administrator password and any passwords imported from Windows Active Directory do not work. Note that if you are not using SSL to connect, the usernames and passwords will be sent in plain text.

If the model does not have security enabled, the Cloud user is not prompted for a password.

This option is mutually exclusive with **GLOBAL\_AUTHENTICATION**.

#### GLOBAL\_A UTHENTIC ATION

This option expects the alias of a defined database manager, or blank, the default is blank.

By defining this option a single Enterprise Architect model with security enabled can be used to provide the security profile to all connections opened with the current port. This is helpful if

	you want to provide multiple models but only manage one list of users. Passwords must be explicitly and individually assigned in the reference model using the <i>Maintain Users</i> procedure; the default administrator password and any passwords imported from Windows Active Directory do not work.  This option is mutually exclusive with MODEL_AUTHENTICATION.
EA_MINIM UM_BUILD	This option expects a numeric value that represents the minimum Enterprise Architect version that can connect to models using this port. The default is undefined which implies all versions are allowed.
EA_MAXIM UM_BUILD	This option expects a numeric value that represents the maximum Enterprise Architect version that can connect to models using this port. The default is undefined which implies all versions are allowed.

## **Advanced SSL**

In general, self-signed certificates are not trusted by major browsers or operating systems and will generate errors or warnings visible to end users. See the <u>Self-Signed SSL</u> <u>Certificates</u> section on how to create a self-signed certificate.

To add trust to a self-signed certificate when it is not practical to generate globally trusted certificates, see <u>Add</u> <u>Trust with a Certificate Authority (CA)</u>.

## **Self-Signed SSL Certificates**

#### Create a certificate

There are many ways to create SSL certificates; however, we have found the OpenSSL toolkit to be the easiest and most comprehensive. As the name suggests, OpenSSL is an open source toolkit for SSL/TLS; see the official website for details.

You will need to download and install the OpenSSL product that suits your environment. For the purpose of this document OpenSSL was installed into C:\OpenSSL-Win64. If your OpenSSL is installed into a different directory then these steps will have to be adjusted to suit.

- Create a new command/batch file in C:\OpenSSL-Win64\bin\
- Open this file and paste these details into it set SRVNAME=localhost openssl genrsa -out %SRVNAME%.key 2048 openssl req -new -x509 -key %SRVNAME%.key -out %SRVNAME%.cert -days 3650 -subj /CN=%SRVNAME% copy /b %SRVNAME%.cert+%SRVNAME%.key server.pem
- Change the value 'localhost' in the first line to suit your server's name and save the file

- Run the batch file
- Move the generated 'server.pem' file to the Pro Cloud Server's 'Service' folder (that is, C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\)

In the statements, the 'openssl genrsa' command will use OpenSSL to generate a new SSL private key, and save it to 'localhost.key'.

The 'openssl req' command will generate a .X509 self-signed certificate using the key generated, specifying 'localhost' as the common name (CN), setting the expiry to be 10 years from the current date and saving the certificate as 'localhost.cert'.

The final command simply copies the contents of the certificate and key files into the new file 'server.pem'.

# Add Trust with a Certificate Authority (CA)

In general, it is preferable to use a certificate that has been signed by a globally trusted root Certificate Authority (CA). There are many CAs that are trusted by all major browser and operating systems that can be used to sign certificates for use with a https server.

If the system architecture makes using a globally trusted CA impractical then it is still possible to have client browsers and operating systems set up to trust a self-signed certificate and avoid security errors or showing warnings to end users.

One way is to simply add the certificate to the trust store of the client browser or operating system, however this would need to be done for each certificate generated. A better approach is to create your own root Certificate Authority and use that to sign each server certificate.

To do this, a self-signed SSL certificate needs to be signed with your own Certificate Authority (CA) certificate and key. And the clients (browsers, operating systems) need to be told to trust the CA certificate. The instructions for adding a CA to a client vary by operating system or browser used.

## **Create a Certificate Authority**

There are many ways to create CA certificates, however, the OpenSSL toolkit is one of the easiest and most comprehensive. As the name suggests, OpenSSL is an open source toolkit for SSL/TLS; see the official website for details. You will need to download and install the OpenSSL product that suits your environment.

To create a CA there are two steps:

- 1. Generate new key and certificate request.
- 2. Self-sign the request to generate a CA certificate.

## 1. Generate new key and certificate request

This can be done in multiple steps, or generated from an existing key file, but for simplicity a new key and new request can be generated in one command. The example below shows how to create a request for a company named 'My Company'. Change this to something more appropriate for your organisation:

openssl req -new -sha256 -nodes -newkey rsa:4096 -subj '/O=My Company/CN=My Company Internal CA'
 -keyout MyCompanyCA.key -out MyCompanyCA.csr

## 2. Self-sign the request to generate a CA certificate

This step self-signs the CA certificate request, and makes the CA valid for 1 year (-days 365). Change 'MyCompany' to match the key and csr request generated in the previous step:

 openssl x509 -req -sha256 -in MyCompanyCA.csr -signkey MyCompanyCA.key -days 365 -out MyCompanyCA.crt

## Create a server certificate and use the CA to sign it

Now that the MyCompanyCA.crt is generated, it can be used to sign your own certificates for a cloud server or WebEA.

First, similarly to <u>Self-Signed SSL Certificates</u>, create a new certificate request. The following example creates a new key and certificate request for a server named 'cloud.mycompany.com':

 openssl req -new -nodes -newkey rsa:4096 -subj '/CN=cloud.mycompany.com' -keyout cloud.mycompany.com.key -out cloud.mycompany.com.csr

Sign the new certificate request with the CA:

 openssl x509 -req -CA MyCompanyCA.crt -CAkey MyCompanyCA.key -CAcreateserial -sha256 -days 365 -in cloud.mycompany.com.csr -out cloud.mycompany.com.crt

The final step for use with a Pro Cloud Server is to concatenate the key and certificate into a 'server.pem' file:

- Windows: copy /b cloud.mycompany.com.crt+cloud.mycompany.com.key server.pem
- Linux: cat cloud.mycompany.com.crt cloud.mycompany.com.key > server.pem

#### Allow clients to trust the root CA

The client operating system or browser now needs to have the CA certificate added to its list of trusted CAs. The instructions vary by operating system and browser but instructions for a few major clients are listed below. For all these steps the 'certificate' referred to is the 'MyCompanyCA.crt' generated in Step 2 above:

Client	Instructions
(Operating	
System,	
Browser)	
Microsoft	Right click the CA certificate file and

Windows	select 'Install Certificate'. Follow the prompts to add the certificate to the trust store either for the current user only or all users of the computer.
Linux - Ubuntu	Copy CA cetificate to /usr/local/share/ca-certificates eg:     sudo cp ~/MyCompanyCA.crt /usr/local/share/ca-certificates/  Update certificates with the following command:     sudo update-ca-certificates The output should show something similar to 'Adding debian:~/MyCompanyCA.pem'.  If using Wine then close all Wine programs and restart Wine:     wineserver -k  See Ubuntu Help for more information.
Firefox	Firefox does not use the operating systems trust store so the CA needs to be added manually.

	If the certificate has a '.pem' extension, then the simplest way is to drag-and-drop the CA certificate file onto Firefox and a prompt will ask to trust the certificate.  Otherwise, manually add certificates and manage added certificates through Firefox's Privacy & Security preferences.  More information can be found on the Firefox wiki
Chrome/Chro mium	Chrome & Chromium do not use the operating system trust store so the CA needs to be added manually.  Open Settings > Advanced > Manage Certificates > Authorities, and select Import.
Internet Explorer	Internet Explorer uses the Windows trust store so adding the certificate to Windows (see above) is sufficient to add trust to the browser as well.
WebEA	WebEA uses PHP/curl to communicate with a Pro Cloud model. If the connection between PHP and the Pro Cloud uses HTTPS, then the CA can be added to PHP's configuration to allow it to trust the certificate.

## **Pro Cloud Server Configuration Client - Web**

As an alternative to the Pro Cloud Server Configuration Application, the Pro Cloud Server also includes a Web Based Configuration Client "WebConfig".

### **WebConfig Server Requirements**

To setup the WebConfig Client you require the following:

- A Web Server (Apache or IIS) capable of hosting PHP v7.0 (or later)
- A Web Server with these standard PHP extensions installed and enabled: core, curl, date, gettext, hash, json, libxml, mbstring, pcre, session, standard and tokenizer
- A Web Server with PHP sessions enabled
- Communication between the web server and the server hosting the Pro Cloud Server
- A base folder (on the web server) to store the WebConfig website pages

Note, these requirements are the same as for hosting WebEA. The WebConfig, could be deployed on the same Web Server as WebEA.

## **Configuration Steps**

Ste p	Description
1	If you have not already, install the Pro Cloud Server by following the steps outlined in the Pro Cloud Server Installation topic, making sure that the WebConfig component is installed.
	After installation you should find the WebConfig website files in the Installation directory (e.g. C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebConfig). These files make up the "WebConfig" website/client, and need to be hosted on a web server. In the simplest configuration the web server would be installed on the same machine as the Pro Cloud Server.
2	Download/install and configure your web server for PHP, according to your requirements.  Tip: XAMPP is the most common Apache/PHP web server that includes all the required components; it is available for Windows/Linux and OS X at https://www.apachefriends.org/download.html.

Note: The WebConfig only requires the minimum XAMPP installation, Apache and PHP; it does not require MySQL, FileZilla Mercury, Tomcat or any of the other optional components, so if you have no need for these components Sparx Systems would recommend to not install them.

Define and configure a website for the WebConfig in your web server.

As there are many different web servers and configurations, configuring the web site, deciding what port the web server will listen to, and making sure the website is secure from external attacks, are all outside the scope of this documentation.

Tip: Using the default XAMPP configuration, the port for the default website is 80 and the base folder is at 'C:\xampp\htdocs'. XAMPP will already have added files to this folder; The WebConfig does not require these files, so if you have no need for them, move them to a backup location.

Copy the WebConfig folder from the Pro Cloud Installation (e.g. C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebConfig) to an appropriate location on the web server (e.g. C:\xampp\htdocs).

Within the WebConfig folder which was copied to your web server, locate the file settings.php and open it with a text editor. This file defines the following settings:

\$sProtocol = 'http';

The Protocol used to access the Pro Cloud Server

\$sServerName = 'localhost';

The Name/IP of the machine running the Pro Cloud Server

\$sPort = '804';

The Port which should be used to access the Pro Cloud Server

*\$sEnforceCerts = 'true';* 

Applies to https connections only. When 'true' self-signed SSL certificates will be denied. When 'false' self-signed SSL certificates can be used.

These settings determine how the WebConfig will access the Pro Cloud Server. By default, the Pro Cloud Server is configured to allow HTTP communication on Port 804, therefore if the Pro Cloud Server and web server are on the same

machine then these settings can typically be left as is.

Alternatively, update these values to reflect the name/ip of the Cloud Server and the appropriate Protocol and Port based on the definitions in the SSProCloud.config file.

On a remote machine, open an internet browser and enter the URL of http://{yourwebserver}/WebConfig/index.php, where the value '{yourwebserver}' is either the name or IP number of the machine hosting the WebConfig website.

This should display the WebConfig. If a password has already been set for the Pro Cloud Server then the "PCS Configuration - Login" prompt will be displayed. If no password has been set, then the Pro Cloud Server Configuration Home screen will be displayed.

## WebConfig - Login

Having setup the WebConfig client/website you can login by entering the relevant URL.

#### For example:


http://{yourwebserver}/WebConfig/

or

http://{yourwebserver}/WebConfig/index.php

By default, the Cloud Server Configuration has a blank password applied to it. In this case the WebConfig URL will bypass the Login prompt and navigate directly to the WebConfig Home page.


If a Password has been assigned then the PCS Configuration - Login prompt will be displayed. Enter the password and click on the Login button to login.



If necessary, after logging in you can set / reset the password for the Cloud Server via the <a href="WebConfig - Server Settings">WebConfig - Server Settings</a> | Change Password option.

## WebConfig - Home Screen

The Cloud Configuration Home page is broken up into 3 Sections - Server Summary, Tasks and Model Connections.



#### **Server Summary**

The Server Summary lists information regarding the current server version, license and port configurations.

Item	Description
Version	The version number of the Pro Cloud Server which the WebConfig is

	accessing.
Pro Models	The number of models which currently have Pro Features enabled.
License	The edition of the Pro Cloud Server (based on the license). If no License has been added then an 'Add' link will be displayed here (which will take you to the 'Pro Cloud Server Licenses' screen').
Expiry	The expiry date of the Pro Cloud Server License.
Licensed to	The name of the company which the Pro Cloud Server is licensed to.
Licensee	The email address associated with this license. I.e. The email address which was provided when the License Request was created.
Model Ports	Lists Ports which are currently defined for use by Model Connections.

## **Tasks**

The tasks section provides links to perform various tasks. The options which are available can vary depending on the type of license.

Item	Description
Server Settings	Provides options to configure the Pro Cloud Server (log level, password, and Cloud Server License), and displays additional server information (log settings, and paths to relevant configuration files and directories).
Configure Ports	View and configure Ports which the Pro Cloud SErver will use for accessing Models.
Configure Integration	Configure the Integration Server and Integration Providers, and bind Integration Providers with Pro Models Connections.  Note, this is only available when using Team Server or Enterprise edition. When
	using the Token edition, this option can be enabled by adjusting the Token Allocations
Manage EA	Manage floating license for EA (and EA

Licenses	Add-Ins).  Note, this option is only available when using Team Server or Enterprise edition of the Pro Cloud Server (it is not available when using the Token edition).
View Logs	Navigates to the View Logs page. This page lists the Cloud Server log files. On the View Logs page, click on the View Log icon in the Actions column to view the contents of the log file.

#### **Model Connections**

Lists Model Connections which are defined for the Cloud Server. This List includes the following information.


Item	Description
Model Status	Left of the Name / Alias is a status icon. Red indicates that the connection has not been enabled (via the "Enable Access" option), meaning this connection cannot currently be used. Green indicates that the Model Connection is enabled.

Name / Alias	This field displays the name of the model connection. When connecting to a cloud model via EA, this Name / Alias should be entered in the Model Name field.
Pro	This field indicates whether Pro Features are enabled for this model connection. Pro features include the ability to access the Model Connection via WebEA, and the ability to use Integration Plugins (for Confluence, Jira, etc). A green tick indicates that Pro features are enabled, while a blank field indicates they are not. An alert icon indicates that the "Pro Features" option was enabled, however Pro Features are not currently enabled/accessible for the Model Connection. For example, this could occur if Pro Features were enabled, however the Pro Cloud License has expired. When the alert icon is displayed, check the icon's tooltip for more information.
Database Type	Displays the database type of the model (Firebird, SQL Server, etc).
Read Only	Indicates whether this connection provides Read-Only access to the model.

Require HTTPS	Indicates that the Model Connection can only be accessed via the HTTPS protocol (via a Port which is also configured to use the HTTPS protocol).
Actions	Provides icons to perform the following actions.  Edit - Edit the Model Connection Settings.  Delete - Delete the Model Connection.
Add a Connection	The final item in the list is a link to Add a Connection.

## WebConfig - Server Settings

The Server Settings page provides various options and information regarding the Pro Cloud Server Configuration.



## **Server Settings**

Item	Description
Default Max Queries	Model Connections can specify the maximum number of requests which can be serviced concurrently. This setting

	determines the default 'Max Simultaneous Queries' when defining a new Model Connection".  Default: 10
Logging Level	Click on the drop-down arrow and select the level of information to be written to the log file. The valid options are:
	OFF - No logging is performed
	FATAL - Only fatal errors are logged
	WARNING - Warnings are logged
	INFO - Information messages that provide general message advising what actions are occurring
	SYSTEM - More detailed messages
	Log Levels are cumulative, for example the INFO level includes all messages of type FATAL, WARNING and INFO
Manage PCS Licenses	Navigates to the 'Pro Cloud Server Licenses' screen, which allows you to

	add/remove Pro Cloud Licenses.
Change Password	Allows you to change the password for accessing the Cloud Configuration (or set a password if one has not already been set).  Changing/Setting a password will also log you out of the Cloud Configuration, returning you to the login screen.
More Info	The More Info section contains a number of read only fields providing information regarding the Cloud Server Configuration.
	Log File Count  The number of log files that should be retained. All logging is written to files named 'SparxCloudServicesLog-X.log' where X represents the file number.  File 'SparxCloudServicesLog-1.log' is always the current file. When the maximum file size is reached, all existing files are renamed by incrementing the file number and a new 'SparxCloudServicesLog-1.log' created.
	Log File Size (bytes)

The maximum file size of each log file. When the file reaches this maximum, a new file is created.

#### **Log Audit Time Period (sec)**

The number of seconds between audit reports.

#### **Log Directory**

The directory into which the log files are saved.

#### **Floating License Keystore**

The full path of the Floating License Keystore file.

#### **Floating License Group Config**

The full path of the Floating License Keystore group configuration file.

#### **Cloud Installation Directory**

The Directory where the Cloud Server is installed to.


#### **Temp Directory**

The Cloud Server Temp directory.

## WebConfig - Pro Cloud Server Licenses

The Pro Cloud Server Licenses screen can be accessed from the WebConfig - Home Screen, either by using the Configure License icon found in the Server Summary Section, or by selecting Server Settings, then Manage PCS Licenses.

This screen allows you to quickly and easily see what Pro Cloud Server licenses have been defined, and the complete details of each license.



In the above example the current Token license is valid from February 3rd, 2019 to February 4th, 2020 and has 5 tokens.

If there is any kind of problem with the license the 'Valid' column will show an alert icon, check the tooltip of the icon for more information. Details regarding the issue will also be written to the current log file.

#### License Procedure

As of Pro Cloud Server version 4.0.30 the licensing procedure has been enhanced. Pro Cloud Server licenses are now linked to the host machine, which is an enforcement of what was stated in the license agreement.

Along with the change to Licensing procedures Pro Cloud Server 4.0.30 introduced the 'Token' Edition, which provides a more flexible upgrade path by making use of tokens that can be purchased separately at any time to enable only the extra functionality your environment requires.

For the premium editions (Team and Enterprise) the enabled functionality remains unchanged except for the Team edition now allows 7 Pro enabled models which has been increased by 2 compared to earlier versions.

To add a License, the basic procedure to follow is:

Ste p	Description
1	Purchase the desired Pro Cloud Server license (e.g. via the Sparx Systems Website).
2	Create a 'New License Request'.
3	Send the 'License Request' file to the Sparx Systems Sales team with the details of your purchase.

4	The Sparx Systems Sales Team will then return the 'License Certificate'.
5	Add your 'License Certificate' to your Pro Cloud Server installation.
6	Your Pro Cloud Server is now licensed!

#### **Pro Cloud Server Licenses**

The Pro Cloud Server Licenses screen displays a table with information and actions for each Pro Cloud Server license which has been added.

License Type	The License Type (either Token, Team or Enterprise). In the case of a Token edition license, this field also displays the number of Tokens.
Valid	Displays a tick to indicate that the license is valid and enabled. If the license is not valid an alert icon is displayed. See the tooltip of the icon for details on why the license is considered invalid.

Start Date	The date the License is valid from.
Expiry Date	The date the License expires on.
Actions	Provides buttons to either Renew or Delete the License.

#### **Tasks**

Below the Pro Cloud Server Licenses table is a Tasks section. This provides the following options.

New License Request	Create a new license request.
Add License	Add a license to the Pro Cloud Server.
Allocate Tokens	Allocate Tokens to enable specific Pro Cloud Server features.  Note, this option appears only when using the Token edition of the Pro Cloud Server.


## WebConfig - New License Request

Pro Cloud Server licenses are linked to a specific machine. After purchasing the Pro Cloud Server you will be provided with an Insallation ID. You will then need to create a License Request file and send this to the Sparx Systems sales team. The Sales team will respond with your License Certificate file

Note, when creating the License Request it is important that the Pro Cloud Server which you are accessing is running on the machine which you intend to use. The License Certificate which you are provided with will be valid for this machine only.

To create a new license request, open the WebConfig - Pro Cloud Server Licenses screen, then click on the New License Request button. The New License Request screen is displayed.

Fill in the details of your company and the Pro Cloud Server purchase (refer to the table below for more information), for example:



Click on the Create License Request button, then email the saved file to the Sparx Systems Sales team, sales@sparxsystems.com.

#### **New License Request Form**

The 'New License Request' form provides the following fields:

Company Name	Mandatory value. The name of the company that made the Pro Cloud Server purchase.
Email	Mandatory value. The email address associated to the Pro Cloud Server purchase.


Installation ID	Mandatory value. The unique 'Installation ID' which was supplied in the confirmation email of your Pro Cloud Server purchase.  If you purchased your Pro Cloud Server license prior to Jun-2019, use your Pro Cloud Server version 3 License key.
Start Date	Optional value. Use this date to request that your Pro Cloud Server License should start on a future date. If no value supplied the Sparx System Sales Team will assume the current date.
Comments	Optional value. Any additional comments that might be helpful to the Sparx Systems Sales Team.

## WebConfig - Add a License


After sending a License Request to the Sparx System's Sales Team, they will reply with your License Certificate file. You can then add your license to the Pro Cloud Server.

On the WebConfig - Pro Cloud Server Licenses screen, click on the Add License button. The Add Pro Cloud Server License screen is then displayed.

Click on the Browse button, select the supplied License Certificate file (\*.lic or \*.crt), then click OK.



The details of the License Certificate will be loaded and the license should appear in the list on the Pro Cloud Server Licenses screen, similar to:



When returning to the WebConfig Home page, the Server Summary details should now display the appropriate information for your licens<sub>e</sub>.

## WebConfig - Remove a License

On the <u>WebConfig - Pro Cloud Server Licenses</u> screen, the Actions column for each existing license contains Renew License and Delete License buttons.

Click on the Delete License button to delete/remove that license. The list of allocated licenses will be refreshed accordingly, there is no need to restart the Pro Cloud Server, the internal License and all related functionality enabled (or disabled) by the change/removal of a License will take effect immediately.

## WebConfig - Renew a License

On the <u>WebConfig - Pro Cloud Server Licenses</u> screen, the Actions column for each existing license contains Renew License and Delete License buttons.


The Renew License button is a convenience function which displays the same License Request form that the Create Request button shows, however the difference is that the Renew option will pre-populate the valid details of the selected License, the remaining fields will still need to be filled in manually. The renewal process is the same as the initial process and will need to be repeated whenever the License expires.

## WebConfig - Token Allocations

#### **Manage Allocations**

The Manage Allocation button will only be visible when the current license is the Token edition and allows the user to control how tokens are consumed to enable Pro Feature functionality.

Click on the Allocate Tokens button to access the Manage Allocations screen.



The Manage Allocations screen is broken up into 4 sections, a Summary of tokens, Explicit Allocations, Web Access

Allocations, and Token Usage.

#### **Summary**

The token summary lists the following:

Total - The total number of tokens based on the active license/s.

Explicit - The number of explicit token allocations. These refer to tokens which have been allocated to enable specific features on the server.

Shared - The number of shared tokens which are available. Shared tokens are consumed when users access features such as WebEA. When logging out the token is returned to the shared token pool.

#### **Explicit Allocations**

This section allows you to enable Integration Plugins for your Pro Cloud Server. Enabling integration with a specific product (e.g. Jira) consumes one token.

#### **Shared for Web Access**

WebEA, Prolaborate and OSLC users consume a single token with every logon. For most environments these allocations can be left with their default values (0 reserved and no maximum). In this case all users are accessing a single shared pool of tokens, regardless of what type of access (WebEA, Prolaborate or OSLC) they require.

Alternatively, each user type can define a number of tokens that are reserved (I.e. can only be used by that type of access) as well as a maximum number.

Note: a **Max Allowed** value of 0 implies that users are NOT allowed, ie if WebEA's Max Allowed value was set to 0, the Pro Cloud Server would deny all WebEA user requests to logon.

Note: a empty value for **Max Allowed** implies there is no limit on the number of users, although the total number of users is still limited to the number of available tokens.

#### **Token Usage**


Click the heading to expand this section. The Token Usage section displays a more detailed break down of the token allocations, including how many tokens are currently in use.

## **WebConfig - Configure Ports**

The Ports page allows you to configure Ports which can be used for communication with the Pro Cloud Server. A Port must be configured in order to allow access to Cloud Models (via Enterprise Architect or WebEA).

By default, Port 804 is defined for http access and Port 805 for https.

The WebConfig client itself also communicates on one of these defined Ports (as specified in the WebConfig 'settings.php' file). The WebConfig's default configuration uses Port 804 (via http).



### **Configure Ports**

The Configure Ports list displays the following information and links.


Item	Description

Port	The Port Number.
Protocol	The Protocol which can be used on this Port.
OSLC Support	Indicates whether OSLC / WebEA support is enabled.
Default Model	If the port is configured to open a specific default model, it's name is displayed.
Authenticatio n	Indicates what type of Authentication is required (if any).
Actions	Provides options to either Edit or Remove the Port definition.
	Editing a Port provides the same options as adding a new Port, except the port number cannot be modified.
	Note, the WebConfig itself uses one of the defined Ports for communication with the Cloud Server (as defined in the WebConfig 'settings.php' file). It is not possible to delete this Port while it is in
	use. If necessary you can modify the 'settings.php' file so that the WebConfig uses a different Port. You can then delete

	the Port which the WebConfig was previously using.
Add a Port	The final item in the Port list is a link to Add a Port.

## WebConfig - Add or Edit a Port

The Add Port page allows you to define a Port to be used by the Pro Cloud Server. The Edit Port page provides the same options, except the Port number cannot be modified.



## **Add Port / Edit Port**

The Add/Edit Port pages provide the following options.

Item	Description
Server Port	Defines the Port number that the Pro Cloud Server will listen for HTTP/HTTPS connections. Each defined Port must be unique and not used by any other service or application on the current machine. The standard HTTP Port (80) and HTTPS Port (443)

are no different; if they are available, the Pro Cloud Server can be configured to use them. You can use the Windows Resource Monitor (which is accessibly via an icon on the Configuration Client 'Ports' tab) to check which Ports are already in use.

Firewall Note: When changing or adding a new Port, check that incoming requests are allowed by the firewall settings at both the local machine and network levels.

Wine Note: When the service is running on Wine you should not use privileged Ports - those below 1024; under Wine, most applications are only able to listen on ports above 1024.

#### Protocol

Select the transfer protocol that the Port communicates on.

When selecting HTTPS you can also specify which versions of SSL/TLS are allowed by selecting the relevant checkboxes.

Additionally, for HTTPS to be configured correctly a file named *server.pem*, must also exist in the same directory as the configuration file, and it must contain a valid private key / certificate. For more

	information, see the SSL Certificates section of the Add a Port Definition topic.
WebEA / OSLC Supported	If checked, this flag enables OSLC requests on the current Port. Note: this option is required for WebEA access.
Default Model	Optional field for OSLC access.  Typically OSLC URL's include the model name. If a default model has been specified then the model name can be omitted from the URL.
Authenticatio n	Select the type of authentication that will be required for this Port:
	Model - All model connections that use the current port will be forced to request HTTP authorization using the user security defined in the Enterprise Architect model being connected to. Passwords must be explicitly and individually assigned in that model using the Maintain Users procedure; the default administrator password and any passwords imported from Windows Active Directory do not work.  Note, if you are not using SSL to connect, the usernames and passwords will be sent

in plain text.

If the model does not have security enabled, the Cloud user is not prompted for a password.

Global - Selecting this option enables the Global Authentication Model field. In this field enter the name of a model which will be used to provide the security profile to all connections opened with the current port. This is helpful if you want to provide multiple models but only manage one list of users. Passwords must be explicitly and individually assigned in the reference model using the Maintain Users procedure; the default administrator password and any passwords imported from Windows Active Directory do not work.


Note, if you are not using SSL to connect, the usernames and passwords will be sent in plain text. Global authentication should only be used with the HTTPS protocol.

Global Authenticatio n Model Required when the Authentication option is set to Global (see above).

## **WebConfig - Integration Plugins**

The Integration Settings page allows you to configure integration plugins to be used with Pro Cloud Models. These plugins enable data from external providers to be displayed within Enterprise Architect. This component is only available in the licensed editions of Sparx System Pro Cloud Server, ie Token, Team and Enterprise editions.

The Integration Plugins component is also known as the Server Based Plugin Interface (SBPI).



#### **Integration Settings**

The Integration Settings section refers to the configuration

of the Pro Cloud's 'Integration Server'. The Integration Server communicates with one or more Integration Plugins, which provides the integration with a specific product, such as Jira, Confluence, etc.

Typically if the Integration Server is run on the same machine as the Pro Cloud Server, and Port 8080 is not in use, then the default settings can be used.

Item	Description
Enable Integration	This checkbox enables (or disables) Integration Plugins for the current Pro Cloud Server installation.
Get Defaults	Loads the default values for the Integration Server settings into any empty fields.
Executable Path	This value defines the complete path for the Integration Server's executable, and if defined, implies that the Pro Cloud Server should automatically start this application when it's own service starts up (assuming the Integration Server Enabled flag is checked).  If the Pro Cloud Server is installed into the default location then this value should

	be C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI\SBPI.exe.
SBPI Server URL	The SBPI Server URL consists of three components.
	Protocol When the 'Use Proxy' option is unchecked, this value defines both the Protocol the Integration Server will listen on and the Protocol Enterprise Architect client will use to communicate to the Integration Server.
	When the 'Use Proxy' option is checked, this value defines the Protocol that the Integration server will listen with.
	Name/IP This value defines the machine name or IP of the server hosting the Integration Server.
	When the 'Use Proxy' option is unchecked, this value defines both the machine name hosting the Integration Server and the machine name Enterprise

Architect client will send their Integration related requests to. It is important to remember that this value is supplied to the Enterprise Architect clients so the Name/IP must be resolvable by them and not the current machine.

When the 'Use Proxy' option is checked, this value defines the Server Name/IP of the machine hosting the Integration Server, the Proxy is responsible for converting the client Name/IP requested by Enterprise Architect to this value.

#### **Port**

When the 'Use Proxy' option is unchecked, this value defines both the Port that the Integration Server will listen on and the Port Enterprise Architect clients will send requests to.

When the 'Use Proxy' option is checked, this value defines the Port that the Integration server will listen on.

#### Ignore SSL Errors

This value defines if SSL related errors that occur while communicating to the Integration Server component should be

ignored. The most common SSL errors are related to self signed certificates, by default a client does not treat self signed certificates as being secure, therefore in order to connect to a server that uses self signed certificates this option should be checked.
This value defines if the Integration Server is operating behind a proxy and if Enterprise Architect clients are required to connect to one URL, but the Integration Server is physically listening for requests on a completely different URL. In most environments this option should be set to the default value of unchecked.
The Client URL is required when the Use Proxy option is enabled. This consists of three components.  Protocol  Defines the Protocol that Enterprise Architect clients will use to communicate to the Integration Server.  Name/IP  Defines the machine name or IP of the

server clients should send Integration requests to. It is important to remember that this value is supplied to the Enterprise Architect clients so the Name/IP must be resolvable by them and not the current machine.

#### Port

Defines the Port that Enterprise Architect clients will send requests for the Integration Server to, this implies that when the Integration Server starts, it will configure itself to start listening on the specified port.

## **Integration Providers**

A single Pro Cloud Server can support any number of external Data Providers, and in turn each of the external Data Providers can be available to as many models as are supported by the installation's license. Please note only Pro-enabled Model Connections can access external data providers. A Pro-enabled Model Connection is one that has the 'Enable Pro Features (OSLC, WebEA and Integration)' option checked.

## The Integration Providers section lists the following information.


Item	Description
Name	A friendly name that describes the provider, this value will show within Enterprise Architect.
Provider	The type of external provider.
Prefix	A short unique value for the provider. This value is added to each external link within Enterprise Architect.
Port	The port the Integration Plugin is configured to listen to.
Bindings	Bindings refer to the model connections which will have access to this integration plugin. These can be configured via the Actions column.
Actions	Provides options to either Edit the Integration Provider's settings, Configure Model Bindings, or Delete the Integration Provider.
Add a	The final item is a link to Add a new

Provider	Provider.	
----------	-----------	--

# WebConfig - Add or Edit an Integration Data Provider

The 'Add Data Provider' and 'Edit Data Provider' screens allow you to configure an Integration Data Provider. The options provided are the same in both cases, except when editing the Provider and Prefix cannot be modified.

Wherever possible the 'Add/Edit Data Provider' screen will fill each field with a default value in order to make it easier for you; if the default values are not correct, simply overwrite them. To this end, whenever the 'Provider' value is changed, a number of other fields will be set to the default values for the new Provider, such as the Data Provider's Prefix, the Integration Plugins' Executable Path and config filename.



The Integration settings are broken up into a number of groupings.

#### **Data Provider**

This group of settings contains the basic information to identify the Data Provider.

Item	Description
Name	This value represents the friendly name for the current Data Provider, it will be shown to users of Enterprise Architect.

Provider	This value specifies the Provider type of the current Data Provider. As mentioned, whenever this value is changed a number of other fields can be automatically updated to make data entry easier for the user.
Prefix	This value represents a short unique name to identify the current Data Provider.  This value will be saved against every Enterprise Architect element that is linked to an external element.

## **Integration Plugin**

This group of settings relate to the physical location of the Integration Plugin relative to the Integration Server, the combination of Protocol, Server Name and Port must be resolvable by the machine hosting the Integration Server, so that requests can be forwarded to it. In the simplest case the Integration Plugin will reside in the same folder as the Integration Server, ie C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI

Item	Description
Protocol	This value represents the protocol that the

	Integration Server should use to communicate to the Integration Plugin, in the simplest configuration this will be HTTP.
Server Name / IP	This value represents the Server Name or IP that the Integration Server should use to communicate to the Integration Plugin, in the simplest configuration this will be localhost (or 127.0.0.1).
Port	This value represents the port that the Integration Server should use to communicate to the Integration Plugin. Each Integration Plugin requires a unique Port number.
Executable Path	This value represents the physical path to the Integration Plugin executable file. If a value is specified the Integration Server will attempt to start this executable during it own startup routine.
Config filename	This value represents the physical filename of the configuration file for the current Integration Plugin, which must reside in the same folder as the Integration Plugin's executable.

#### **Provider Server**

This group of settings relate to the details of the external data provider, ie Dropbox, Jira, etc. The Integration Plugin will use the defined details to connect to the remote system and retrieve data from it so that it can be sent back to Enterprise Architect. The combination of Protocol, Server Name and Port must be resolvable by the server hosting the Integration Plugin, which in the simplest case is the Pro Cloud Server.

Item	Description
Protocol	This value represents the protocol that the Integration Plugin should use to communicate to the external Data Provider.
Server Name/IP	This value represents the Server Name/IP that the Integration Plugin should use to communicate to the external Data Provider.
Port	This value represents the port that the Integration Plugin should use to communicate to the external Data Provider.

Base URL	Some external Data Providers allow for the concept of multiple repositories at a single location, for such Data Providers this field acts as a filter.
	For example it is possible to use another Enterprise Architect model as an external data source, in the case of Enterprise Architect the Protocol, Server & Port determine the Pro Cloud Server, the Base URL is the DB Alias of the repository.
Username	This value represents the user name that should be used (in combination with the password) to access the data within the external system. If a value is defined in this field all Enterprise Architect users of the current Data Provider will use the same set of credentials to read the external system. Otherwise if the user name field is left empty, Enterprise Architect will prompt each user independently for their credentials.
Password	This value represents the matching password for the specified user name.
Create Items	This checkbox controls if Enterprise

	Architect users are able to create new items within the external system.
Modify Items	This checkbox controls if Enterprise Architect users are able to modify the details of external items within the external system.
Post Discussions	This checkbox controls if Enterprise Architect users are able to create discussions against elements within the external system.
Ignore SSL Errors	This checkbox controls if the Integration Plugin should ignore SSL related errors that occur as a result of communicating to the external system.

## Logging

This group of settings relate to the how the Integration Plugin will create entries in it's log file(s). Since the Integration Plugins run without user intervention, it is important for them to be able to write to any messages or potential problems to a log file. However special consideration must be made to ensure that performance isn't

impacted by writing to such files, which is possible if the log file continually grows without limits. It is also unreasonable to expect that manual intervention should be required to ensure that the size and number of log files don't impact performance. For these reasons each Integration Plugin has it's own set of log files and configuration options to manage its log files.

The current log file will always include a '1' on the end of its filename. A new log file will be created whenever the Integration Plugin is started or the physical size of the current log file reaches the Max File Size. When this occurs all existing files will be 'rolled over', meaning their file numbers will be incremented and a new '{filename}1.log' created. If the roll over process causes more files to exist than the 'File Count' setting allows, these additional files will be deleted.

Item	Description
File Count	Default value: 3 This value represents the 'rolling' number of log files that should be retained for the current Integration Plugin.
Max File Size	Default value: 1048576 This value represents the maximum number of bytes a log file can be before a new one is created.

Level	Default value: WARNING This value represents what maximum level of messages that should be written to the log file. The levels are: OFF, FATAL, WARNING, INFO and SYSTEM. A defined log level is inclusive of all lower levels, therefore if a Plugin is set to a log level of INFO then all FATAL, WARNING and INFO messages will be written to its log file.
Directory	(READ-ONLY) This field displays the physically location of where the log files for the current Data Provider will be saved.

## **Proxy**


This group of settings relate to how the Integration Plugin should communication to the External Data Provider when they are separated by a Proxy Server.

Item	Description
Server Name/IP	The server name (or IP) and port number of the Proxy Server. ie

	proxyserver.com:3131
Bypass	This field provides a mechanism for certain addresses to bypass the proxy; it accepts multiple values separated by semi-colons (;). For example, 192.168.*;*.localdomain.com;www.myd omain.com
User Name	If the Proxy Serer requires credentials, then enter the user name into this field.
Password	If the Proxy Serer requires credentials, then enter the password into this field.

# **WebConfig - Edit Model Bindings**

After defining an integration provider you must apply some model bindings. The integration will only be available to these 'bound' models. Also note, integrations can only be bound to models which have the 'Enable Pro Features (OSLC, WebEA and Integration)' option enabled.



The Edit Bindings page provides the following information and options.

## **Provider**

Item	Description
Provider Name	(Read Only) The Name of the Provider which you are editing the bindings of.
Provider Type	(Read Only) The Provider type (Enterprise Architect, Jira, etc).

## **Model Bindings**


The Model Bindings section lists all model connections which currently have pro features enabled. Next to each model connection name is a checkbox. Check this box to bind the integration provider with that model connection (i.e. making the integration available when using that model).

Note, one Provider can be bound to many model connections.

# WebConfig - Manage EA Floating Licenses

The Manage EA Floating Licenses page allows you to manage Enterprise Architect (and Add-in) floating licenses.

Important: All communications to the Pro Cloud's Floating License Server are performed via HTTPS, therefore to use the Pro Cloud Server's Floating License Server functionality at least one Port has to be configured to use the HTTPS protocol and a valid certificate/private key file is defined in the Pro Cloud Server's Services folder. See the Advanced SSL topic for more details.



This page provides the following information and options.

## **License Server Settings**

The License Server Settings section allows you to adjust settings for the handling of Floating Licenses.

After adjusting these settings click the Apply button to save/apply these options.

Item	Description
Total Key	(Read Only) Displays the total number of

Count	keys in the keystore.
Key leases expire after	Enter a numerical value, then select either Days or Weeks from the dropdown list. This determines when a checked out key is automatically returned to the keystore.
Auto Checkin	When enabled, if a user closes Enterprise Architect then their key will be immediately returned to the keystore.  When disabled, closing Enterprise Architect will not be automatically returned, instead the key remains checked out to the user for amount of time defined by the 'Key leases expire after'.  Typically the Auto Checkin option would be enabled it users need to work offline for periods of time, otherwise the option should be enabled to make the make most efficient use of shared keys.

# **Key Summary**

This table provides a summary of the keys in the keystore for each product type.

Item	Description
Product	Name of the Product.
Available	The number of checked in keys.
Expired Lease (Available)	The number of keys which are checked out but available because their lease has expired.
Checked Out	The number of keys which are currently checked out
Total Available	The total number of keys which are currently available (i.e. the sum of the Available and Expired Lease values).

## **Keys**

The Keys table lists information on all keys in the keystore. It provides options to force the check-in of a key, delete a key, and add keys.

Checked out keys are displayed at the top of the list, and keys are grouped by product type.

Item	Description
Key	The Product Key.
Product	The Product which the key is for.
Assigned to	The user who currently has the key checked out. When empty this indicates that the key is checked in.
Lease Expires	The date when the key will be automatically returned to the keystore (based on the 'Key leases expire after' setting).
Actions	Provides the following options:
	Check In Key Only available it the key is currently checked out. This option can be used to manually release/check-in the key.  Delete
	Deletes the key from the keystore.
	Add Keys
	The final item in the Key list is an option

to Add Keys.

Click this option to display the "Add Floating Licenses" page. The "Add Floating Licenses" page contains a single field for adding keys to the keystore.

To add keys, enter one or more key into the "Enter Floating License/s" field, then click OK.

When adding multiple keys in the field at once, each key should be on a separate line.

## **Group Configuration**

The Cloud Server allows you to define groups which only have access to a set number of keys for a specific product. This is done by directly editing the ssflsgroup.config file on the Cloud Server.

See the Floating License Server <u>Install and Config</u> topic for details.

### Notes

• The WebConfig Floating License Management feature is

available when using either the Team Server or Enterprise edition of the Pro Cloud Server.


# WebConfig - Adding a Model Connection

New model connections can be added via the Add a Connection link on the WebConfig Home screen.

Adding a new model connection consists of 2 steps, selecting the connection type, then entering the details which are required to add the model connection.

## **Select Connection Type**

After using the Add a Connection option the 'Select Connection Type' page is displayed. Select the relevant type, depending on what type of database you are accessing.



The WebConfig supports the creation of Firebird, Oracle (OLE DB) or SQL Server (OLE DB) Model Connections. In the case of Firebird you will then have the option to either created a new Firebird model directly from the WebConfig,

or access an existing Firebird model.

For other model types (DBMS repositories), the model should have been created and tested (accessing the model via EA's 'Connect to Server' option) prior to adding the Cloud Connection.

#### Note:

- The DBMS types (Oracle, Sql Server, etc) are only listed on this page if the relevant drivers are found on the server.
- The Pro Cloud Server also supports connections to MySQL and PostreSQL databases, however these connections cannot be created using the WebConfig (they require definition of a ODBC system data source which is not possible via the web client). To create a connection to a MySQL or PostreSQL, use the Pro Cloud Server Configuration Application.

## **Add Model Connection**

After selecting the model type, the Add Model Connection page is displayed. The options provided vary depending on the model type which was selected.

Item	Description
Firebird	Firebird Models are stored on the server within the Pro Cloud Server's Models

sub-folder (e.g. C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\Models).

When selecting Firebird you will be provided with two options.


#### **New Firebird Model**

Select this option to create a new Firebird model. Enter a name for the Firebird Model in the File Name field. No path or file extension are required.

The new, empty Firebird model will be created on the server (in the Models sub-folder) and the Model Connection will be associated with this file.

## **Existing Firebird Model**

Select this option to create a Model Connection which links to an existing Firebird model (which already exists in the Models sub-folder).



# Oracle (OLE DB)

#### **Connection Name / Alias**

Specify a short unique name for the connection. This is required when accessing the model via EA or WebEA.

#### **Net Service Name**

Enter the Oracle Net Service Name as defined in the TNSNAMES.ORA.

#### User

Enter the user name

#### **Password**

Enter the password for the user specified above

Add Model Connection	
Connection Name / Alias	OracleModel1
Database Type	oracle-oledb
Driver	OraOLEDB.Oracle.1
Net Service Name	ora11g
User	eauser
Password	•••••

# SQL Server (OLE DB)

## **Connection Name / Alias**

Specify a short unique name for the connection. This is required when accessing the model via EA or WebEA.

#### Server / Instance

Enter the Server Name or Server Instance. E.g. 'SQL-SERVER' or 'SQL-SERVER\SQL2012'

#### User


Enter the user name

#### **Password**

Enter the password for the user specified above


#### **Database**

Enter the name of the database that is the Enterprise Architect repository



# WebConfig - Edit Model Connection

The Edit Model Connection screen is shown when you click on the Edit button for an existing Model Connection on the WebConfig home page. This page allows you to modify various options for the selected Model Connection.



## **Edit Model Connection**

Item	Description
Alias	The database Alias. This is the value all

	Enterprise Architect clients will need to select in the 'Model Name' field of the 'Cloud Connection' screen. If necessary, you can edit this Alias to enable users to reference it from Enterprise Architect and WebEA.
	Note, this value must be unique. You are not able to use the same alias for multiple model connections.
Database Type	(Read only) Displays the DBMS type of the database, such as Firebird, MySQL, Postgres, SQLSvr or Oracle.
Enable Access	By default, new model connections are disabled. Select this checkbox to allow access to this model connection.
Enable Pro Features (OSLC, WebEA and Integration)	This option is only available in Pro Cloud Server editions. Select this checkbox to enable 'Pro Features', such as OSLC, WebEA and Integration to external systems.
Connection String	(Read only) Displays the connection string used to connect to the database.  The Copy button can be used to copy this connection string to the Clipboard.

Max Simultaneous Queries	Type in the maximum number of connections that can be open. You can use the up/down arrows to adjust this figure to balance resource usage with concurrent user performance.  There is no explicit limit for this value, but the higher the value the more resources are consumed on your server, without a matching increase in benefit in user performance. Connections are held so briefly that the reduction in user wait time due to more connections being opened is not usually noticeable. If you
	are reaching the number of connections you have defined here, increase it by small increments (units) rather than large ones (tens).
OSLC Access Code	Optional. Type in the access code that all OSLC clients, including WebEA, are required to send in an HTTP header.  Leave blank to indicate that the OSLC clients are not required to send an access code.
Require HTTPS and	If checked, this model connection can only be access via the https, using a port


Authenticatio n	which is configured to use https with Authentication enabled (I.e. set to either 'Model' or 'Global')
Read-only connection	Select this checkbox to prevent users from modifying the database referenced by this connection.
Run Scheduled Tasks	When this option is checked the Pro Cloud Server will update Time Series charts in the current model as a schedule task.
Enable Worker	Select this checkbox to enable the Pro Cloud 'Worker' application. The Worker process runs on the server and periodically generates images for diagrams in the model. These images are required for WebEA and Prolaborate.
Connection Details	Enter the Enterprise Architect Connection String, or path to an EAP shortcut file (located on the Pro Cloud Server machine), which the Worker application will use to access the model.
	For example; EAConnectString:model1 ;Connect=Cloud=protocol:http,address:lo

	calhost,port:804,user:fred,pwd:pwdxxx;D ata Source=model1;
	or,
	C:\EA\shortcuts\model1.eap
Update Period (seconds)	Default: 30 Specify how often the Worker process will check for modified diagrams and update their stored images.

# **Firewall Settings**

When setting up a Pro Cloud Server, you must check that the Firewall on the server is set to allow the incoming ports for the database connections that you have created.

For example, in the default SSProCloud.config configuration file the Pro Cloud Server listens on ports 804 and 805, however if you have a firewall you must set these ports as enabled for inbound traffic.



The Pro Cloud Server installation will automatically create an inbound Windows firewall rule, similar to the one shown in the above image however the default rule should be reviewed and updated to suit your environment.

For information on creating the Inbound Rule to identify the ports you have specified in the config file (the 'Sparx Systems Professional Cloud' rule in the illustration), see the Microsoft Windows online topic <a href="Create an Inbound Port Rule">Create an Inbound Port Rule</a>.

Note: A common cause of failure is that other services or programs are already using the allocated ports. This is especially likely when using the default http (80) and https (443) ports. Check that no other services are using the allocated ports.

# **Using Multiple Configurations**

## **Using Multiple Configurations**

The Sparx Systems Pro Cloud Server can be run multiple times with different configurations by passing these additional arguments.

Argument	Description
config / -c	The argument following this will be interpreted as the path to the configuration file to read on startup. This allows a secondary instance of the Cloud server to run on a different set of ports, use an altered logging level or different directories.  When multiple configurations are being used, you need to ensure that each instance reads a configuration file that specifies different paths. Otherwise only the first instance will start successfully. By default this references SSProCloud.config in the directory containing the service executable.
path / -p	The argument following this will be interpreted as the absolute path to search

	for other resources. Changing this parameter changes where the configuration file is read from, along with all paths in the configuration file that specify %SERVICE_PATH%. Setting this to a directory other than the default is an easy way to separate multiple running instances of the Cloud service.
registry / -r	The argument following this will be interpreted as a registry path within HKEY_LOCAL_MACHINE where the models the Cloud server provides are specified. Changing this parameter allows using different Cloud servers to provide access to different models.  By default this is Software\Sparx Systems\SQLBridge.
standalone	This argument allows starting the SSProCloud.exe as a standalone executable instead of requiring it to be launched as a Windows service.  This can be important if Windows firewall is blocking the service, as it will prompt to create a firewall exception.  Additionally, Wine by default closes services automatically when the last user

process closes, but using the 'standalone' argument to run the server as an application will ensure that the service isn't terminated when no more user applications are running. Use the command line:

wine SSProCloud.exe standalone
Or, if you are launching from a terminal
and want to close it:

wine SSProCloud.exe standalone & disown or

nohup wine SSProCloud.exe standalone

(The 'disown' parameter and 'nohup' command both close the terminal but ignore the 'hangup' message that would otherwise disconnect Pro Cloud Server again.)

# **Pro Cloud Server using IIS (Optional)**

For most users, the built-in web server provided with the Pro Cloud Server provides all the functionality they require. It is also the easiest method to set up and use.

However, the Pro Cloud Server also provides the option of integrating with Internet Information Services (IIS). This is recommended *only* for users for whom the built-in authentication methods are insufficient, and who want to use Windows Active Directory or certificate-based authentication (see the *Import User IDs from Active Directory* Help topic). Note that the use of IIS does not eliminate the login process, and users must still enter their user IDs and passwords.

To configure IIS to host the Pro Cloud Server, you must first set the SparxCloudLink.sseap file to refer to the Pro Cloud Server, and then in Windows open the Internet Information Services (IIS) Manager and configure it to send requests to the appropriate module. Depending on your preferences you can choose either an HTTP Module or an ISAPI module.

Prior to setting up HTTP or ISAPI, these settings must be made in IIS:

- Application Pool settings
- Feature Settings

For a secure HTTPS setup (optional):

- Set up a Certificate
- Set up HTTPS

## **Configuration Settings**

Before setting up your HTTP module or ISAPI module, you must first check that the SSProCloud.config file for the service is configured as required, and note the port used so that you can specify it when you go on to set the SparxCloudLink.sseap file to refer to the Pro Cloud Server.

The directory path containing the ISAPI dll also contains the SparxCloudLink.sseap configuration file.

The path should resemble this example:

"C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\ISAPI"

Edit this file in a text editor, running as an Administrator.

The default contents are:

```
[cloud]
server=localhost
port=803
```

#### server:

The address to look up the machine running the Pro Cloud Server. In most circumstances it is best to run the HTTP module and the Pro Cloud Server on the same machine. In this case, the default value of localhost can be used. If the Pro Cloud Server is running on a different machine, use the IP address or server name where the service is running.

#### port:

The port the Pro Cloud Server is listening on for admin requests. By default this takes the value of 803, but this should be cross-referenced against your service configuration in the SSProCloud.config file.


### **Optional settings**

These points are optional. For testing purposes you might prefer to leave these changes until any issues with IIS are resolved.

- 1. In the SSProCloud.config file, remove all the references to ports other than the administration port (default 803). In other words, remove the bracketed entries (...) from the config file.
- 2. Save the SSProCloud.config file.
- 3. Restart the Service.


## **Application Pool Settings**

HTTP or ISAPI will require an Application pool that is 32-bit and not managed code. This illustration shows the settings for 32-bit applications in the IIS Application Pools Advanced Settings view.



#### **Feature Permissions**

This illustration shows the access path and the 'Default Web Site | Handler' mappings to permit Script Execution.



## **Setting up a Certificate**

In order to run the HTTPS service you must set up a security certificate in IIS.

### In the IIS Manager:

- 1. Under 'Connections', select the root connection (machine name).
- 2. Double-click on the 'Server Certificates' icon.
- 3. Click on 'Create Self Signed Certificate'.

4. Specify a simple, user-friendly name for the certificate.




## **Setting up HTTPS**

To set the bindings through which HTTPS will operate, you must include a port and a certificate in the site bindings.

## In the IIS Manager:

- Under 'Connections', select the 'Default Web Site' option
- Under 'Actions' click on the 'Bindings' option
- In the Site Bindings window click on 'Add'




This will open the Add Site Binding window.

Set these parameters:

• Type: HTTPS

• Port: 443

• SSL Certificate: select the certificate created in *Setting up* a *Certificate* 



## **HTTP Module**


To set up the HTTP module in the Internet Information Services (IIS) Manager:

- 1. In the 'Connections' panel, select the machine properties (top of the tree).
- 2. Double-click on the 'Modules' icon in the middle panel.



This returns the 'Modules' list and the 'Actions' view.

3. In the 'Actions' list, click on the 'Configure Native Modules...' option.



This opens the 'Configure Native Modules' view.

4. Click on the Register button to open the 'Register Native Module' dialog.



Type in the name and the path of the SSCSIISHttpLink.dll file.


5. Click on the OK button. The 'SSCloudServices' checkbox will now be selected.




- 6. Click on the OK button to close the 'Configure Native Modules' dialog.
- 7. In the 'Connections' panel (see Step 1), click on your web

site.


8. Double-click on the 'Handler Mappings' in the middle pane.




This opens the Handler Mappings view:



- 9. In the 'Actions' list, click on the 'Add Module Mapping' option to open the 'Add Module Mapping' dialog.
- 10. As illustrated, set the 'Request path' and 'Name'.
- 11. In the 'Module' field, click on the drop-down arrow and select the module added in step 4.



12. Click on the Request Restrictions button. On the 'Request Restrictions' dialog, select the 'Access' tab. Select the 'Execute' radio button to enable Execute permission.



- 13. Select the 'Mappings' tab and deselect the 'Invoke Handler only if request is mapped to' checkbox.
- 14. Click on the OK button.
- 15. Close the 'Add Module Mapping' dialog by clicking on the OK button again.


To complete this HTTP module set up, see the *Configuration Settings* section at the start of this topic. You

should then be able to connect to a model using Enterprise Architect via your IIS server using the HTTP module.

#### **ISAPI** Module

To configure an ISAPI module instead of the HTTP module:


1. In the 'Connections' panel, select the machine properties:



2. Double-click on the 'Handler Mappings' icon:




- 3. In the 'Actions' list, click on the 'Add Module Mapping' option.
- 4. In the 'Add Module Mapping' dialog, set 'Request path' to 'sparxCloudLink.sseap', 'Module' to 'IsapiModule', and 'Executable' to 'SSCSIISIsapiLink.dll', as shown.




5. Click on the OK button to close the dialog. You should now be able to connect to a model using Enterprise Architect via your IIS server using ISAPI.

# Connecting Enterprise Architect to a Cloud Model

Once your Pro Cloud Server has been set up with at least one port listening for communication and at least one model you can connect to, you can connect to the model in Enterprise Architect. When you first open Enterprise Architect, the 'Manage Projects' dialog displays. The Connect to Cloud button on the top right provides access to Cloud connections.




In later work sessions you can access this dialog and button by selecting the 'New > Manage projects' option on the Start Page. However, there is also a Cloud Connection link on the 'Start Page' itself.



## **Cloud Connection Dialog**

The 'Cloud Connection' dialog prompts you for the details of the model.



Option	Action
Name	Type the name to use to refer to this model. It does not have to match any values on the server, and will appear in your recent models list.
Protocol	Click on the drop-down arrow and select a secure (https) or insecure (http) connection, as supported by the server you are connecting to. When you select the protocol, the port will be automatically set to match the default for that protocol.
Server	Type in the machine name

	(sparxcloud.com) or IP address (192.168.0.20) of your server.
Port	Define the port number the service is listening on. This should match the settings in the configuration file on the server.  Note: For a server, the default settings will use port 804 for http and port 805 for https.
Model Name	Type in the name of the model available on the server.  Note: Generally a system administrator will provide you with a list of available models. However, for those with ability to use the Sparx Systems Pro Cloud Server Configuration Client the model name to access the given database can be found in the read-only 'Alias' field on the Configure Database Manager screen.

#### **Pro Cloud Server Features**

As mentioned in the Introducing Cloud Repositories topic, even without a License the Pro Cloud Server can be used for hosting Cloud Repositories to be accessed by Enterprise Architect. When using a licensed Pro Cloud Server a number of additional features are available (as outlined below).

#### WebEA

One of the most requested features from the Enterprise Architect user base recently has been the ability to access Enterprise Architect models on mobile devices or from desktops without the need to install the Enterprise Architect application.

Sparx Systems has developed WebEA using PHP, JavaScript and CSS to provide a solution that can be deployed easily, that runs on the widest variety of systems, and that doesn't require any special hardware or additional licensing.

WebEA has a large array of configuration options that give the Enterprise Architect customer the power to control exactly how each model can be accessed and what types of actions can be performed.

## WebConfig

The Pro Cloud Server 'WebConfig' is a web based configuration client, which can be used as an alternative to the Windows based 'Configuration Client'.

The WebConfig allows you to add/configure Cloud connections, set up integration plugins, manage floating licenses, and view Pro Cloud Server logs; all from a Web Browser.

#### **OSLC RESTful API**

The OSLC RESTful API (OSLC Architecture Management v2.0) provides direct access to a wide range information from your Enterprise Architect Cloud Repositories.

#### **Integration Plugins**

Or Server Based Plugin Interface (SBPI), is a framework developed to extend the Pro Cloud Server via Plugins. The Integration Plugins allows you to link Enterprise Architect elements to elements/objects in external products.

## **Floating License Server**

The Sparx Systems Floating License Server functionality has been available for many years as the Key Store, providing users of Enterprise Architect with the ability to manage their floating licenses. Up until the creation of Pro Cloud Server, the Key Store was only offered as an independent Windows service. Now that it has been integrated into the Pro Cloud Server, users only need to install, configure and maintain one service for all their Enterprise Architect needs.

#### **Visibility Levels**

The 'Visibility Levels' feature within Enterprise Architect gives model managers the ability to restrict access to certain sections of a model. Only models hosted by a Pro Cloud Server are able to make use of this feature. Visibility Levels are implemented by taking advantage of the Row Level Security feature included in Oracle and Microsoft SQL Server.

#### WebEA

Sparx System's WebEA is an application designed to display the data from Enterprise Architect models in a web browser, which means users can review and comment on a model in real time, on a range of mobile devices or a remote work station, without needing to install Enterprise Architect.

WebEA is a component of the Sparx Systems Pro Cloud Server, which is a separately-installed and licensed product, to complement Enterprise Architect. WebEA makes use of the PHP, HTML, CSS3 and javascript technologies and requires a web server (such as Apache or IIS) to host it. The topics of this chapter explain how to install and configure WebEA in detail, but if you are interested in getting started quickly see one of the *WebEA Quick Start Guides* for the necessary steps.

#### Requirements

- Users of WebEA require a HTML5 / CSS3 compatible web browser
- The WebEA interface requires JavaScript to be enabled in the web browser
- A client's device will require network connectivity to the web server hosting WebEA
- Users of WebEA will require this information in order to connect to and log into a WebEA model:

- The complete URL; that is, machine name/IP number and optionally the port number and/or the path to the WebEA files, depending on how the web server has been configured
  - The name of the model to access
- (Optional) an access code necessary to open a model, if one has been configured
- (Optional) the user ID and password required to open a model, if user security has been applied

## **WebEA Quick Start Guide**

The purpose of the WebEA Quick Start Guide is to provide the complete process for quickly installing and configuring WebEA in a new environment using the most common options.

The process is based on these assumptions:

- A clean Windows 7 (or later) based machine has been selected to host both the Pro Cloud Server and Web Server; that is, no other Web Servers or applications are configured to listen on port 80
- The latest version of XAMPP will be used to install Apache as the Web Server
- WebEA will access one brand new Firebird model (because it is the simplest, as it does not require any third party ODBC drivers)
- The Enterprise Architect user base is using Enterprise Architect 13.5 or later

#### 1. Download the Pro Cloud Server

Ste p	Description
1. 1	The Pro Cloud Server installer can be downloaded from the registered user section of the Sparx Systems

website. https://www.sparxsystems.com/registered/reg_ea_down.html
Note you will need valid credentials to access this area of the website.

#### 2. Install the Web Server

Ste	Description
p	
2.	XAMPP is available at https://www.apachefriends.org/download.html. Download the latest version for Windows, to the machine's desktop.
2. 2	The XAMPP installer should be run with Administration privileges; on the desktop, right-click on the XAMPP installer icon and select 'Run as Administrator'.
2. 3	Proceed through the installation process, accepting the defaults until the Select Components screen displays.  Deselect these checkboxes: MySQL, FileZilla, Mercury, Tomcat, Perl, phpMyAdmin, Webalizer

	and Fake Sendmail. WebEA only requires the minimum XAMPP installation of Apache and PHP. Click on the Next button.
2. 4	The installation folder should be set to C:\xampp. Click on the Next button until the installation starts. When the installation finishes, select the option to open the Control Panel, then complete the installation.

## 3. Configure the Web Server

With the default XAMPP configuration, the default website will use port 80. Its base folder is C:\xampp\htdocs.

Ste p	Description
3.	Using the XAMPP control panel, start Apache. No errors should be reported at this stage.

#### 4. Install Pro Cloud Server

Ste
-----

p	Description
4. 1	The Pro Cloud Server installer is a standard MSI; double-click on it to start the installation.  Note: Depending on a number of factors, you might be prompted for the credentials of a user with elevated permissions; these must be entered before the installation will continue.
4. 2	The 'Sparx Systems Pro Cloud Server Setup' dialog displays. Click on the Next button.
4. 3	Read the license agreement and select the checkbox for indicating that you accept the terms. Click on the Next button.
4.	Read the information about the Pro Cloud Server. Click on the Next button.
4. 5	The 'Custom Setup' page displays. Click on the Next button to accept the defaults.
4. 6	Click on the Install button to run the installation.

## 5. Configure the Pro Cloud Server

The Pro Cloud Server will have installed all of its files to the 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\' folder and added a Shortcut to the desktop.

Ste p	Description
5. 1	Run the 'Pro Cloud Config Client' shortcut which was added to your desktop.
5. 2	Enter the Server address of "localhost:803" and click on the <b>OK</b> button.
5. 3	Click on the <b>Licensing</b> button, then <b>Create Request,</b> fill in your company and purchase details, save the License Request and email it to the Sparx Systems Sales team (sales@sparxsystems.com).  When the Sparx Systems Sales team return your License Certificate, click the <b>Add</b> button and select the supplied certificate file, the Pro Cloud Server should now have a valid License loaded.
5. 4	Select the Ports tab  Select Port "804" from the list and click on the <b>Edit</b> button.

## Tick the checkbox OSLC Supported, then click OK. 5. Select the Database Managers tab, then click on the 5 Add button. Type the name 'fb-procloud.feap' in the connection string field, then click on the **OK** button. Select the new entry in the list and click on the **Edit** button. On the Configure Database Manager screen, select the Enabled and Enable Pro Features (OSLC, WebEA and Integration) checkboxes. Click on the **OK** button. For a more in depth explanation of how to add database managers, see the Help topic Add Database Manager. Open the standard Windows Services console 5. (command "services.msc"), locate and select the 6 service "Sparx Systems Professional Cloud", then restart it.

#### 6. Copy WebEA files to Website

Ste	Description
p	
6. 1	Copy the folder C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebEA\ to C:\xampp\htdocs.

## 7. Configure WebEA to access the model

To give a better demonstration of the WebEA options, we will define three different WebEA model connections. All will connect to the same physical Firebird database.

Each model connection will have its own set of options that control how users will be able to interact with the data.

Ste p	Description
7. 1	Open the file 'C:\xampp\htdocs\WebEA\includes\webea_config.ini 'with a text editor.

- In the "[model list]" section, remove the 'model4' 7. and 'model5' lines. Edit the remaining model names 2 to: model1 = "Pro Cloud Model (no updates)" model2 = "Pro Cloud Model with discussions" model3 = "Pro Cloud Model with access code" In the "[model1 : settings]" section change the 7. SSCS DB ALIAS option to "fb-procloud". The 3 remaining default options should remain unchanged. In the "[model2 : settings]" section change the 7. SSCS DB ALIAS option to "fb-procloud". The 4 remaining default options should remain unchanged. Delete the "[model3 : settings]" and "[model5 : 7. 5 settings]" sections, rename the "[model4 : settings] section header to [model3 : settings]", then set these options as shown: sscs db alias = "fb-procloud" sscs port = "804" sscs model user = "" sscs model pwd = "" auth code = "password01"
  - 7. Save the changes to the file webea\_config.ini in
  - 6 C:\xampp\htdocs\WebEA\includes.

# 8. Configure your firewall(s) to allow client access

Ste p	Description
8.	Firewall rules will have to be adjusted to allow traffic between the [Client] and [Web Server], on ports 80 and 443.
8. 2	Firewall rules will have to be adjusted to allow traffic between the [Web Server] and [Pro Cloud Server], on ports 804 and 805.

## 9. Use Enterprise Architect to add content

The initial Firebird model we created earlier will be empty. The easiest way to add content to the model is with Enterprise Architect.

Ste	Description
p	
9.	On a client machine with access to the web server,

1	open Enterprise Architect v13.5 or later.
9. 2	From the main menu select 'Open Project' or, from the ribbon, select the 'Solone > Open Project' option.
9. 3	Click on the Connect to Cloud button.
9. 4	On the 'Cloud Connection' screen set these parameters:  Name: fb-procloud  Protocol: http://  Server: {your servername}  Port: 804  Model Name: fb-procloud  Click on the OK button.
9. 5	<ul> <li>Open the 'Configure &gt; Model &gt; Options &gt; Cloud' options and tick these checkboxes:</li> <li>Auto create Diagram Image and Image Map (each time a Diagram is saved)</li> <li>Auto create HTML Page (each time a Linked Document is saved)</li> <li>These options ensure diagrams and Linked Documents are saved in a format that allows them to be viewed in WebEA.</li> </ul>

- 9. Create a sample set of Model Views, Packages,
- diagrams and elements, so that they can be viewed in WebEA later.

#### 10. Test WebEA access

Ste	Description
p	
10 .1	On a client machine, open a web browser and enter the URL http://{yourwebserver}/WebEA/login.php, where the value '{yourwebserver}' is either the name or IP number of the machine hosting the WebEA website. The WebEA login screen displays, listing the three model connections we defined earlier:  • Pro Cloud Model (no updates)  • Pro Cloud Model with discussions  • Pro Cloud Model with access code
10 .2	Select the first model connection - Pro Cloud Model (no updates) - and click on the Next button. This connects you to the model and displays the model views that are defined.  From here you should be able to navigate through the model by selecting Packages, diagrams and elements. When you select an element, its complete

details are displayed. Because of the way this model connection is defined, the bottom of the properties section will NOT contain the 'Discussions' section.

- Click on the 'hamburger' icon in the top right corner of the display, and select the 'Logout' option. Then select the second model connection Pro Cloud Model with discussions and click on the Next button. You should see the same model views as before; now navigate to an element and confirm that the 'Discussions' section is visible.
- Once again, click on the 'hamburger' icon in the top 10 right corner, and select the 'Logout' option. .4 Select the third model connection, 'Pro Cloud Model with access code' and click on the Next button. This time you should be presented with a prompt for the Access Code; enter 'password01' (as we defined in step 7.5) and click on the Login button. You should see the same model views as before. Navigate to an element; this time there should be a blue 'hamburger' menu in the element details area that allows the creation of element features such as tests and resource allocations. There should also be a pencil icon next to the element notes area that, when clicked on, will allow the modification of element notes.

## **Complete**

This quick start procedure is now complete. It has shown you how to install and configure a basic installation of WebEA. The Sparx System's online Help documentation has more detailed instructions and explains all possible options that can be configured. See the section *Model Repository* | *Cloud Based Repositories* | *Pro Cloud Server* in the Enterprise Architect online Help.

## WebEA Quick Start Guide - IIS

The purpose of the WebEA Quick Start Guide - IIS is to provide the complete process for quickly installing and configuring WebEA in a new IIS environment using the most common options.

The process is based on these assumptions:

- A clean Windows Server 2012 (or later) based machine has been selected to host both the Pro Cloud Server and Web Server; that is, no other Web Servers or applications are configured to listen on port 80
- IIS will be used as the Web Server
- WebEA will access one brand new Firebird model (because it is the simplest, as it does not require any third party ODBC drivers)
- The Enterprise Architect user base is using Enterprise Architect 13.5 or later

#### 1. Download the Pro Cloud Server

Ste	Description
p	
1. 1	The Pro Cloud Server installer can be downloaded from the registered user section of the Sparx Systems website.

https://www.sparxsystems.com/registered/reg\_ea\_down.html

Note you will need valid credentials to access this area of the website.

#### 2. Install the Web Server

Ste p	Description
2.	Enable IIS on Windows Server by running the Server Manager and selecting 'Add roles and features'
2. 2	Proceed through the installation process, accepting the defaults until the Server Roles screen displays.  Select the 'Web Server (IIS)' checkbox.  Continue through the installation, accepting defaults.
2. 3 - In st all P	Install PHP for IIS with 'Microsoft Web Platform Installer', available from: <a href="https://www.microsoft.com/web/downloads/platform.aspx">https://www.microsoft.com/web/downloads/platform.aspx</a> Run Microsoft Web Platform Install and select 'Products > Frameworks'.

Н	Select the version of PHP required (for example,
P	'PHP 7.2.2 (x64)').
	Click on the Add button and Install button.
	(This will download the required files and install
	them for use with IIS.)

## 3. Configure the Web Server

With the default IIS configuration, the default website will use port 80. Its base folder is %SystemDrive%\inetpub\wwwroot which is normally C:\inetpub\wwwroot.

Ste	Description
p	
3.	No additional configuration is required. Test the connection by browsing to server address from another computer. "Internet Information Services" landing page should display.

#### 4. Install Pro Cloud Server

Ste	Description
-----	-------------

p	
4.	The Pro Cloud Server installer is a standard MSI; double-click on it to start the installation.  Note: Depending on a number of factors, you might be prompted for the credentials of a user with elevated permissions; these must be entered before the installation will continue.
4. 2	The 'Sparx Systems Pro Cloud Server Setup' dialog displays. Click on the Next button.
4. 3	Read the license agreement and select the checkbox for indicating that you accept the terms. Click on the Next button.
4. 4	Read the information about the Pro Cloud Server. Click on the Next button.
4. 5	The 'Custom Setup' page displays. Click on the Next button to accept the defaults.
4. 6	Click on the Install button to run the installation.

# 5. Configure the Pro Cloud Server

The Pro Cloud Server will have installed all of its files to the 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\' folder and added a Shortcut to the desktop.

Ste p	Description
5. 1	Run the 'Pro Cloud Config Client' shortcut which was added to your desktop.
5. 2	Enter the Server address of "localhost:803" and click on the <b>OK</b> button.
5. 3	Click on the <b>Licensing</b> button, then <b>Create Request,</b> fill in your company and purchase details, save the License Request and email it to the Sparx Systems Sales team (sales@sparxsystems.com).  When the Sparx Systems Sales team return your License Certificate, click the <b>Add</b> button and select the supplied certificate file, the Pro Cloud Server should now have a valid License loaded.
5. 4	Select the Ports tab  Select Port "804" from the list and click on the <b>Edit</b> button.

## Tick the checkbox OSLC Supported, then click OK. 5. Select the Database Managers tab, then click on the 5 Add button. Type the name 'fb-procloud.feap' in the connection string field, then click on the **OK** button. Select the new entry in the list and click on the **Edit** button. On the Configure Database Manager screen, select the Enabled and Enable Pro Features (OSLC, WebEA and Integration) checkboxes. Click on the **OK** button. For a more in depth explanation of how to add database managers, see the Help topic Add Database Manager. Open the standard Windows Services console 5. (command "services.msc"), locate and select the 6 service "Sparx Systems Professional Cloud", then restart it.

#### 6. Copy WebEA files to Website

Ste p	Description
6. 1	Delete the default IIS files from C:\inetpub\wwwroot
6. 2	Copy the folder C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebEA\ to C:\inetpub\wwwroot.

## 7. Configure WebEA to access the model

To give a better demonstration of the WebEA options, we will define three different WebEA model connections. All will connect to the same physical Firebird database.

Each model connection will have its own set of options that control how users will be able to interact with the data.

Ste	Description
p	
7.	Open the file

1	'C:\inetpub\wwwroot\WebEA\includes\webea_config.ini' with a text editor.
7. 2	In the "[model_list]" section, remove the 'model4' and 'model5' lines. Edit the remaining model names to:  model1 = "Pro Cloud Model (no updates)"  model2 = "Pro Cloud Model with discussions"  model3 = "Pro Cloud Model with access code"
7.	In the "[model1 : settings]" section change the SSCS_DB_ALIAS option to "fb-procloud". The remaining default options should remain unchanged.
7. 4	In the "[model2 : settings]" section change the SSCS_DB_ALIAS option to "fb-procloud". The remaining default options should remain unchanged.
7. 5	Delete the "[model3 : settings]" and "[model5 : settings]" sections, rename the "[model4 : settings] section header to [model3 : settings]", then set these options as shown:  sscs_db_alias = "fb-procloud"  sscs_port = "804"  sscs_model_user = ""  sscs_model_pwd = ""  auth_code = "password01"

- 7. Save the changes to the file webea\_config.ini in
- 6 C:\inetpub\wwwroot\WebEA\includes.

# 8. Configure your firewall(s) to allow client access

Ste p	Description
8.	Firewall rules will have to be adjusted to allow traffic between the [Client] and [Web Server], on ports 80 and 443.
8. 2	Firewall rules will have to be adjusted to allow traffic between the [Web Server] and [Pro Cloud Server], on ports 804 and 805.

## 9. Use Enterprise Architect to add content

The initial Firebird model we created earlier will be empty. The easiest way to add content to the model is with Enterprise Architect.

Ste p	Description
9. 1	On a client machine with access to the web server, open Enterprise Architect v13.5 or later.
9. 2	From the main menu select 'Open Project' or, from the ribbon, select the 'ST > Open Project' option.
9. 3	Click on the Connect to Cloud button.
9. 4	On the 'Cloud Connection' screen set these parameters:  Name: fb-procloud  Protocol: http://  Server: {your servername}  Port: 804  Model Name: fb-procloud  Click on the OK button.
9. 5	<ul> <li>Open the 'Configure &gt; Model &gt; Options &gt; Cloud' options and tick these checkboxes:</li> <li>Auto create Diagram Image and Image Map (each time a Diagram is saved)</li> <li>Auto create HTML Page (each time a Linked</li> </ul>

	Document is saved) These options ensure diagrams and Linked Documents are saved in a format that allows them to be viewed in WebEA.
9. 6	Create a sample set of Model Views, Packages, diagrams and elements, so that they can be viewed in WebEA later.

#### 10. Test WebEA access

Ste	Description
p	
10 .1	On a client machine, open an internet browser and enter the URL http://{yourwebserver}/WebEA/login.php, where the value '{yourwebserver}' is either the name or IP number of the machine hosting the WebEA website. The WebEA login screen displays, listing the three model connections we defined earlier:  • Pro Cloud Model (no updates) • Pro Cloud Model with discussions • Pro Cloud Model with access code

- 10 | Select the first model connection Pro Cloud Model
- .2 (no updates) and click on the Next button. This connects you to the model and displays the model views that are defined.

From here you should be able to navigate through the model by selecting Packages, diagrams and elements. When you select an element, its complete details are displayed. Because of the way this model connection is defined, the bottom of the properties section will NOT contain the 'Discussions' section.

- Click on the 'hamburger' icon in the top right corner of the display, and select the 'Logout' option. Then select the second model connection Pro Cloud Model with discussions and click on the Next button. You should see the same model views as before; now navigate to an element and confirm that the 'Discussions' section is visible.
- Once again, click on the 'hamburger' icon in the top right corner, and select the 'Logout' option.

  Select the third model connection, 'Pro Cloud Model with access code' and click on the Next button. This time you should be presented with a prompt for the Access Code; enter 'password01' (as we defined in step 7.5) and click on the Login button. You should see the same model views as before. Navigate to an element; this time there should be a blue 'hamburger' menu in the element details area that allows the

creation of element features such as tests and resource allocations. There should also be a pencil icon next to the element notes area that, when clicked on, will allow the modification of element notes.

## **Complete**

This quick start procedure is now complete. It has shown you how to install and configure a basic installation of WebEA on IIS. The Sparx System's online Help documentation has more detailed instructions and explains all possible options that can be configured. See the section 'Model Repository | Cloud Based Repositories | Pro Cloud Server' in the Enterprise Architect online Help.

## **WebEA Installation and Configuration**

The Sparx Systems Pro Cloud Server product is installed using a standard Microsoft Windows Installer package that includes a number of optional components. WebEA is one of these components and is installed by default. It is possible to change the install location of WebEA; however, if the defaults are used WebEA will be installed into the C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebEA\ folder (assuming a 64 bit machine is being used).

See the *Pro Cloud Server Installation* and *Pro Cloud Server Configuration* Help topics for a full description of how to install and configure the Sparx Systems Cloud Service.

**Important**: If you are installing the Pro Cloud Server on a machine that already has the Sparx Systems Cloud Services or Sparx Systems WAN Optimizer installed then these should be uninstalled first.

## **WebEA Server Requirements**

In order to run WebEA in your environment you must have:

- A Web Server (Apache or IIS) capable of hosting PHP v7.0 (or later)
- A Web Server with these standard PHP extensions installed and enabled: core, curl, date, gettext, hash, json, libxml, mbstring, pcre, session, standard and tokenizer

- A Web Server with PHP sessions enabled
- Communication between the web server and the server hosting the Pro Cloud Server
- A base folder (on the web server) to store the WebEA website pages

## **Configuration Steps**

The installation of the WebEA application should have already been completed by following the steps outlined in the *Pro Cloud Server Installation* topic, making sure that the WebEA component was installed.

In additional to installing the Pro Cloud server, WebEA also needs a web server to host it. In the simplest configuration the web server would be installed on the same machine as the Pro Cloud Server.

Configuring WebEA applies these steps:

Ste	Action
p	
1	Decide what models are going to be available to WebEA users.
	At the same time it is worth considering these points, which will determine the configuration options of each model.
	• Is user security currently configured on the model?

- Should WebEA users be prompted for their model user and password?
- Should WebEA users be able to view element discussions?
- Should WebEA users be able to add element discussions?
- Should WebEA users be able to join and participate in reviews?
- Should WebEA users be able to insert new objects, and if so, what types?
- Should WebEA users be able to add new element features, and if so, what types?
- Should WebEA users be able to edit element notes?
- Should WebEA users be able to edit element tests?
- Should WebEA users be able to edit element resource allocations?
- What is the default list of watchlist items for the model?
- Using the Cloud Configuration Client and define a Port to be used for access to your Cloud Models. Ensure that the "OSLC Supported" option has been set to true.

After adding or modifying Port configurations, ensure the Windows service 'Sparx Systems Professional Cloud' is restarted.

- Ensure a database manager is defined for each model decided on in step 1, in the Pro Cloud Server's database manager list. The process to do this is as outlined in Sparx Systems Pro Cloud Server Configuration Client, in *Add Database Manager*.
- For each of the models decided on in step 1, select the model on the 'Sparx Systems Pro Cloud Server Configuration Client', click on the Configure button and select the 'Enable Pro Features (OSLC, WebEA and Integration)' checkbox.
- Ensure that your Pro Cloud Server has a valid License loaded by completing the following steps: Click on the **Licensing** button, then **Create Request**, fill in your company and purchase details, save the License Request and email it to the Sparx Systems Sales team (sales@sparxsystems.com).

When the Sparx Systems Sales team return your License Certificate, click the **Add** button and select the supplied certificate file, the Pro Cloud Server should now have a valid License loaded.

Check that you can access the model(s) in Enterprise Architect using the 'Connect to Cloud' option.

After opening each model in Enterprise Architect, enable the 'Data Cache' options and click on the Create button to generate the initial set of viewable

diagrams and Linked Documents. See the Model Configuration topic for details. Download/install and configure your web server for 7 PHP, according to your requirements. Tip: XAMPP is the most common Apache/PHP web server that includes all the required components; it is available for Windows/Linux and OS X at https://www.apachefriends.org/download.html. WebEA has been tested on all of the currently available versions of PHP, but if your environment has no special requirements then Sparx Systems would recommend v7.1.1 for Windows. All further Quick Start points will assume this configuration. Note: WebEA only requires the minimum XAMPP installation, Apache and PHP; it does not require MySQL, FileZilla Mercury, Tomcat or any of the other optional components, so if you have no need for these components Sparx Systems would recommend to not install them. 8 Define and configure a website for WebEA in your web server. As there are many different web servers and configurations, configuring the web site for WebEA, deciding what port the web server will listen to, and making sure the website is secure from external attacks, are all outside the scope of this documentation.

**Tip:** Using the default XAMPP configuration, the port for the default website is 80 and the base folder is at 'C:\xampp\htdocs'. XAMPP will already have added files to this folder; WebEA does not require these files, so if you have no need for them, move them to a backup location.

Opy the contents of the entire WebEA installation folder ('C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebEA\') to the base folder of the website.

**Tip:** Copy WebEA folder from 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\WebEA\' to 'C:\xampp\htdocs'.

**Special Note regarding reinstalls:** before updating the WebEA files, take a backup of the files you have modified, ie \includes\webea\_config.ini and \includes\webea strings.ini.

Due to the sensitive nature of some of the information contained in the WebEA configuration file, we recommend that the '\includes\' folder within the WebEA folder is severely restricted so that only PHP can access the files within. For example, in Apache this is achieved with this entry in the Apache configure file:

<Directory "{website\_path}/includes">
 AllowOverride none
 options none

Require all denied

</Directory>

Once your web server is configured and the WebEA application files copied into the base folder, restart/start the web server.

**Tip:** Using the XAMPP control panel, Stop/Start Apache.

Edit the '\includes\webea\_config.ini' file and define each model decided on in step 1.

See the *How to configure WebEA models* Help topic for more details on what each option means in WebEA's config file.

Tip: Edit

'C:\xampp\htdocs\includes\webea\_config.ini' file, and update all parameters with the prefix 'SSCS\_' to that of a defined repository in your Cloud Service.

**Special Note regarding reinstalls:** if you a have a previous backup of the \includes\webea\_config.ini file and wish to use the same configuration, you can simply restore the backup file.

On a remote machine, open an internet browser and enter the URL of http://{yourwebserver}/login.php, where the value '{yourwebserver}' is either the name or IP number of the machine hosting the WebEA website. This should display the WebEA login screen that lists the models which are defined in the

webea\_config.ini file.
Other considerations:

If you require different lists of models (or different options) for different user bases, then it is possible to define multiple websites, each with their own dedicated port and base folder, using Apache's virtual hosts. This could mean user group A could access its set of models with the URL http://{yourwebserver}:180/ while user group B would use the URL http://{yourwebserver}:200/
Firewall rules will have to be adjusted to allow traffic between the [Client] and [Web Server]
Firewall rules will have to be adjusted to allow traffic between the [Web Server] and [Pro Cloud

#### **HTTPS** and SSL

Server]

If the models have SSL enabled and are using self-signed certificates, then see <u>Advanced SSL</u> for advanced configuration of WebEA.

## **Model Configuration**

Action	Description
Configure Enterprise Architect model options	By default, diagrams and Linked Documents are not saved in a format that is viewable by web browsers. In order for users of WebEA to view these components, Enterprise Architect must be configured to generate (and store) viewable versions of them whenever changes are made. The options to generate viewable diagrams and Linked Documents are defined at the model level.  With the model open in Enterprise Architect, select the 'Configure > Model > Options' ribbon option. On the 'Manage Project Options' dialog, refer to the 'Data Cache' options on the 'Cloud' page.  Data Cache  Auto create Diagram Image and Image Map (each time a Diagram is saved) Auto create Diagram Image and Image Map (each time a Diagram is saved) Auto create Diagram Image and Image Map (each time a Diagram is saved) Auto create Diagram Image and Image Map (each time a Diagram is saved)  Auto create Diagram Image and Image Map (each time a Diagram is saved)  Auto create Diagram Image and Image Map (each time a Diagram is saved) Create
	The first option (if enabled), in addition to saving a diagram normally will also generate and save a static image of the diagram.  The second option (if enabled), in addition to saving a Linked Document

normally will also generate and save the document in HTML format. If these options are not enabled, diagrams and Linked Documents will not be viewable from within WebEA. When initially configuring a model to auto create viewable diagrams and Linked Documents, it is advisable to click on the Create button to generate the initial set of viewable diagrams and Linked Documents. While this is not mandatory, viewable versions of all existing diagrams and Linked Documents will not exist until they are saved. Note: This approach is relevant when all Enterprise Architect users are using a build later than 1350. If, however, some of your user base is using older versions of Enterprise Architect then updates to diagrams and Linked Documents will not be reflected immediately when saved. See the *How to configure automatic* viewable components Help topic for the recommended approach to overcome this situation. Configure It is possible for WebEA users to connect model users to user security enabled models in one of two ways:

	<ul> <li>Using their model User Login and Password; that is, the same credentials they use when connecting to the model with Enterprise Architect, or</li> <li>If the model has been configured in WebEA to not require login credentials then all users will be logged in under the one user account (using the sscs_model_user and sscs_model_pwd defined in the 'webea_config.ini' file)</li> </ul>
Single Sign-On (SSO)	<ul> <li>WebEA supports the following Single Sign-On Systems:</li> <li>Windows authentication with Active Directory</li> <li>OpenID</li> <li>Provided the Enterprise Architect Model has been configured for Single Sign-On, users will have the option to use Single Sign-On when accessing the Model via WebEA.</li> </ul>

## Acknowledgements

WebEA incorporates certain components developed by third parties. Sparx Systems acknowledges the contribution made

to the WebEA product by these components.

- jQuery v1.12.3 jQuery Foundation
- NicEdit ©2007-2008, Brian Kirchoff, under license from MIT
- Date Picker for jQuery v5.1.1, Keith Wood, under license from MIT

# How to configure automatic viewable components

While Sparx Systems recommend that users should always use the latest release of Enterprise Architect, we do acknowledge that in some situations this is hard to achieve. Therefore, in order for WebEA (and the Pro Cloud Server) to function correctly when users are using builds of Enterprise Architect earlier than 1350, the Pro Cloud Server includes a custom version of Enterprise Architect (referred to as the EA Worker) that will automate the generation of WebEA viewable diagrams and Linked Documents.

Each instance of an EA Worker is capable of connecting to a single model, and typically runs on the same server as the Pro Cloud Server.

#### **How to run EA Worker**

The 'EA Worker' application does not have a GUI of any kind, therefore it is started with two command line options:

- 1. cloudupdate: the frequency (measured in seconds) of how often the application should check for new or modified diagrams and Linked Documents.
- 2. A connection string to the model, defined as a .EAP file. An example command line is:

C:\> EA.exe /cloudupdate:30

"C:\EA\shortcuts\model1.eap"

Typically the easiest and most efficient method to run the EA Worker is with a Windows batch/command file.

#### Model shortcuts for EA Worker

Within Enterprise Architect it is possible to save model connections (no matter what type of DBMS is in use) as a .EAP file. These model shortcuts are not .EAP file databases, but plain text files that contain a connection string to a model.

An example .EAP shortcut to a model without security:

EAConnectString:model1 ---

;Connect=Cloud=protocol:http,address:localhost,port:804;D ata Source=model1;

However, when the model has security enabled the connection string requires a USER and PASSWORD parameters:

EAConnectString:model1 ---

;Connect=Cloud=protocol:http,address:localhost,port:804,us er:fred,pwd:pwdxxx;Data Source=model1;

## **EA Worker Configuration Steps**

Ste Description

p	
1	Create a .EAP shortcut to the model.  The creation of a .EAP shortcut file can be achieved by either:
	1) Manually creating a plain text file, renaming its extension to .EAP and entering the complete connection string as shown (making sure to replace all values enclosed in {}):
	EAConnectString: {modelname}; Connect=Cloud=protocol:http,address: {servername},port: {port},user: {username},pwd: {password}; Data Source={modelname};
	or
	2) In Enterprise Architect, open a Cloud connection to the model in question and then choose 'Save As Shortcut' from the or drop-down menu.
2	Create a batch/command file.
	Create a plain text file, give it a meaningful name, and change its extension to .CMD. Then edit the file and enter this text, making sure to replace {seconds} with the number of seconds and {filepath} with the location of the fully qualified .EAP created in the previous step:  "C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Worker\EA.exe" /cloudupdate:{seconds} "{filepath}"

3 Run the batch/command file.

Double-click on the file created in the previous step. Sparx System recommends that this batch/command file is added to Startup so that it is automatically run when the server starts.

## Lifecycle of EA Worker

The EA Worker application is designed to connect to the specified model automatically when it starts; if there is a problem with the connection the application ends. If the connection string is valid and the EA Worker connects to the model it will run continually until the server is restarted or until the process is manually terminated.

## How to configure WebEA models


All WebEA configuration is controlled by a single file 'webea\_config.ini', which must reside in the WebEA '\includes\' folder.

This configuration file defines the model connections which are available on WebEA's login page. For each WebEA model connection you define how WebEA will access the model (server, port, etc), and optionally apply settings to adjust WebEA's functionality (e.g. show/hide specific features).

## **Configuration Options**

There are two different options available for WebEA model configuration.

	Description
1	(Recommended) Use the web based configuration page (config.php).



Or, directly modify the 'webea\_config.ini' file using a text editor.

```
_ 🗆 🗙
                                            webea_config.ini - Notepad
File Edit Format View Help
[model list]
model1 = "Model One (no updates)"
model2 = "Model One with discussions"
model3 = "Model Two with user login"
model4 = "Model Three with all options"
model5 = "Sparx Systems Sample Model"
[model1 : settings]
sscs_protocol = "http"
sscs_server = "localhost"
sscs_port = "804"
sscs_db_alias = "model1"
auth_code = ""
login_prompt = "false"
default_diagram = ""
show_discuss = "false"
participate_in_reviews = "false"
[model2 : settings]
sscs_protocol = "http"
sscs_server = "localhost"
sscs_port = "804"
sscs_db_alias = "model1"
auth_code = ""
login_prompt = "false"
default_diagram = "
default_main_layout = "icon"
```

## **Security Considerations**

Due to the sensitive nature of some of the information contained in the WebEA configuration file, we recommend that the '\includes\' folder within the WebEA folder is severely restricted.

For example, in Apache this could be achieved using .htaccess and .htpasswd files in the '\includes\' folder.

# Configure WebEA models - via Web Browser

After copying the WebEA files from the Pro Cloud Installation to your website, WebEA can be configured via a web browser.

Using a web browser, enter the URL for WebEA's login page.

At the end of the URL, after "login.php" append "?config".


#### For example:

http://{yourwebserver}/login.php?config or,

http://{yourwebserver}/webea/login.php?config

Where the value '{yourwebserver}' is either the name or IP number of the machine hosting the WebEA website.

This should display the WebEA Configuration Page. This page includes a list of the WebEA connections which are currently defined in the webea\_config.ini file.



## **WebEA Configuration**

The WebEA Configuration Model list provides the following information and options.

Description
The display name for the WebEA Model connection. This appears in the WebEA login page, and in the WebEA header after opening the model.
The Actions column contains a number of buttons for modifying the model connection.  Edit

Allows you to edit/configure the options for this WebEA model connection.

#### Rename

Allows you to change the WebEA display name.

### Copy

Create a duplicate of this WebEA model connection. The duplicate will be added to the list of models with the name: {original name} - Copy

#### **Delete**

Delete this WebEA model connection.

#### Move

The Move column contains options for moving the model connection.

#### Move Up

Move the model connection up one position in the list.

#### **Move Down**

Move the model connection down one position in the list.

	Move to  Move the model connection to a specific location in the list.
Add a Model	The final list item provides the option to add a new model connection.  When selecting this option you will be prompted to enter the connection name / WebEA display name.  After entering the name the page to edit the Model Connection's settings is displayed.

## Saving the WebEA configuration

Changes which are made via the WebEA Configuration page (including changes when editing a specific model connection) are not saved automatically.

To save changes, click on the **Save** button at the bottom of the WebEA Configuration page.

Note, the Save button is only enabled when there are unsaved change.

## Creating a backup of the webea\_config.ini

### file

The **Create Backup** button at the bottom of the WebEA Configuration page will create a backup of the current webea\_config.ini file.

Backups are created with the name:

webea\_config\_bak\_{date}\_{time}.ini

Note, a Backup cannot be created while there are unsaved changes (if necessary select Save, then Create Backup).

# Edit WebEA Model Connection settings

After selecting the option to Edit a Model connection, the configuration options for that connection are displayed.

In the simplest case, the connection can be defined by only updating the Protocol, Server, Port and Model Name / Alias fields. A number of additional options are provided for configuring authentication, available functions, display options, etc.

## **Connection Options**

Item	Description
Protocol	Defines the protocol to be used to connect to the Sparx Systems Pro Cloud Server.
Server	Defines the fully qualified machine name or IP address of the server hosting the Pro Cloud Server.
Port	Defines the TCP port used to connect to the Sparx Systems Cloud Service. This

	port number must match one of the ports the Pro Cloud Server Windows Service is listening to or, in the case of an IIS setup, the IIS port servicing this repository.
Model Name / Alias	Defines the name / alias of the model connection. This corresponds to the Database Manager's Alias in the Pro Cloud Server Configuration Client or the 'Model Name' on the Enterprise Architect's Cloud Connection screen. The value is case sensitive.
Deny Self Signed Certificate	Defines whether self signed SSL certificates can be used.  If you are using HTTPS and a self signed certificate then this should be set to No.  Note, this option is only applicable when the Protocol is set to HTTPS.

# **Authentication Options**

Item	Description
Authentication Code	Defines the authorization code all WebEA users must enter before they can

access the model. If this value is blank, WebEA users are not prompted to enter a code.

This option is only used for basic username/password authentication and is not used for Windows Authentication or OpenID.

It's possible to set this option and also set a Model User (see below). In this case the user will be required to enter the access code only and will not be prompted for a username or password.

#### Model User

Defines the model user login (as defined in Enterprise Architect User Security) that will be used in combination with the Model User option (see below) to login to a security enabled model.

#### Note:

- When set, all other authentication schemes are bypassed, including Windows Authentication, OpenID and basic username/password login prompt.
- Sparx Systems would recommend the use of this option only on a model that

	has been configured as read only, since all updates made by WebEA users in this configuration will be identified as the same user.
User Password	Defines the password (as defined in Enterprise Architect User Security) that will be used in combination with the sscs_model_user option to login to a security enabled model.
	<ul> <li>When set, all other authentication schemes are bypassed, including Windows Authentication, OpenID and basic username/password login prompt.</li> <li>Sparx Systems would recommend the use of this option only on a model that has been configured as read only, since all updates made by WebEA users in this configuration will be identified as the same user.</li> </ul>
Allow blank passwords	Defines whether or not WebEA will attempt to send blank passwords to the Cloud Services for validation.

# **General Options**

Item	Description
Default Package Layout	Defines the default layout when viewing the contents of a package (or an element with children) in WebEA's main view. WebEA can display child items in one of three layouts. Either Icon view (the default), List view, or Notes view (resembling the Enterprise Architect Specification Manager view).
Object Order	Defines the order of objects in the Browser and Object List views. There are 3 different ordering behaviors
	Alphabetical Objects are sorted Alphabetically (by name).
	Free Sort  Objects are sorted based on their "Set Position" (manual sorting which is applied in EA), then Alphabetically. This reflects EA's sorting when the "Allow

Free Sorting" option is enabled. **Object Type** Objects are sorted by type, then Set Position, then Alphabetically. This reflects EA's sorting when the "Allow Free Sorting" option is disabled. Note, regardless of the Object Order setting, WebEA displays Diagrams, then Packages, then Elements. The Object Order applies to the items within each of these groupings. Default Defines the GUID of the diagram that should be automatically loaded when Diagram users log onto the model. If this option is not defined or an empty value is specified, WebEA assumes that no diagram should be loaded and displays the model root instead. The GUID of any diagram can be obtained from WebEA using the "Obtain direct link to the current page" icon in the navigation bar. Note: The entire GUID (including {}) must be used.

## Mini Properties Navigates

When set to 'Yes' selecting certain 'navigable' elements will cause WebEA to navigate to the target of these elements. Examples of such 'navigable' elements are Hyperlinks and Navigation Cells. For all other elements, selecting them will display the properties of the element in the Properties View. This option has no effect when the Properties View is not shown.

# Diagram Elements Navigate

As of WebEA version 3.01.23.1690 (included in Pro Cloud Server 3.0.23) the default selection of some objects on diagrams has changed to match Enterprise Architect behavior. This applies to i) Composite Elements and ii) Package elements that contain a diagram.

Composite Elements

A composite element on a diagram will navigate directly its composite diagram.

Package Elements

A Package element on a diagram will navigate to the first child diagram

	contained within the selected Package. If the selected Package does not contain any diagrams then the package's properties are displayed.  When Diagram Elements Navigate is set to 'No', selecting either a composite element or package element on a diagram will display the selected elements properties.
Recent Search Days	Defines the number of days the predefined 'Recent' searches should consider. For example if this value was set to '7' then whenever a user invokes the search for 'Recent elements', all elements modified in the previous 7 days will be returned.
Show Browser	<ul> <li>Defines the default visibility of the Browser.</li> <li>Note:</li> <li>If a user selects the 'Mobile' option when logging in to WebEA, this overrides the 'Show Browser' option and the Browser will be hidden</li> <li>This behavior could be overridden depending on the screen resolution; for example, on a low resolution screen</li> </ul>

	such as a mobile phone, the Browser will be hidden regardless of the 'Show Browser' option
Show Properties View	Defines the default visibility of the Properties View.  Note:  If a user selects the 'Mobile' or 'Tablet' option when logging in to WebEA, this overrides the 'Show Properties View' option and the 'Properties View' will be hidden  This behavior could be overridden depending on the screen resolution; for example, on a low resolution screen such as a mobile phone, the 'Properties View' will be hidden regardless of the 'Show Properties View' option
Show Discussions	Defines whether or not discussions on Packages and elements should be displayed within the WebEA interface.
Add Discussions	Defines whether or not new discussions on Packages and elements can be added to the model.  Note: This option is disabled when Show Discussions is set to 'No'

Participacte in Reviews	When set to 'Yes', users are able to Join discussion reviews. In order to make full use of this option Show Discussions and Add Discussions would also have to be set to 'Yes'.
Use Avatars	When set to 'Yes', all discussion messages are displayed with the creating user's avatar. When set to 'No', a set of generic images representing discussions and replies is used instead.

## **Object Update Options**

Item	Description
Can add Objects	Defines whether or not new objects (elements, diagrams, or packages) can be added to the model.
	Note: this option will be internally set and restricted to 'No' for Pro Cloud Server Express installations.
Edit Object Notes	Defines whether an object's notes can be edited.

Can add <type></type>	The remaining options in this section define whether or not elements of the given object type can be added to the model.
	Note, if the 'Can add Objects' is set to 'No', then this overrides the individual Can add <type> options.</type>

# **Object Feature Update Options**

Item	Description
Can add Object Features	Defines whether or not element features (Changes, Tests, etc) can be added to the model.
Can edit Tests	Defines whether or not the details of element tests can be edited in the model.
Can edit Resources	Defines whether or not the details of element resource allocations can be edited in the model.
Can add	The remaining options in this section

<feature type&gt;</feature 	define whether or not specific feature types (Changes, Tests, etc) can be added
	to elements in the model.
	Note, if Can add Object Features is set to
	'No', then this overrides the individual
	Can add <feature type=""> options.</feature>

### **Property Section Options**

The Property Section Options define whether specific properties are available/visible when viewing the properties of an element in WebEA.

By default, all property sections are set to be visible ('Yes').

Note, when viewing the Properties of an element in WebEA's Main View, the 'feature buttons' to display specific properties are only displayed if the element has features/properties of that type.

For example, if an element has no tagged values, then the Tagged Values feature button will not be displayed (regardless of Property Section Options).

# **Default Watchlist Options**

Item	Description
Days to Watch	Defines the default activity period of the model watchlist. The value is a number of days; for example, look for activity in the last 10 days.
Cookie Retention	Defines the period over which a WebEA user's set of Watch list options are stored. The value is the number of days that the cookies will be retained for.
Recent Discussions	Define whether or not the watch list should display a count of elements that have had discussions during the activity period.
Recent Reviews	Define whether or not the watch list should display a count of review elements that have been added or modified during the activity period.
Recent Diagrams	Define whether or not the watch list should display a count of added/modified diagrams during the activity period.
Recent Elements	Define whether or not the watch list should display a count of added/modified elements during the activity period.

Active resource tasks	Define whether or not the watch list should display a count of elements with active resource allocations during the activity period.
Ending resource tasks	Define whether or not the watch list should display a count of elements with resource allocations ending during the activity period.
Overdue resource tasks	Define whether or not the watch list should display a count of elements with resource allocations that fall overdue during the activity period.
Recently passed tests	Define whether or not the watch list should display a count of elements with tests that passed during the activity period.
Recently failed tests	Define whether or not the watch list should display a count of elements with tests that failed during the activity period.
Recently deferred tests	Define whether or not the watch list should display a count of elements with tests that were deferred during the activity period.

	1
Recent tests not checked	Define whether or not the watch list should display a count of elements with tests that were not checked during the activity period.
Tests not run	Define whether or not the watch list should display a count of elements with tests that were not run during the activity period.
Verified changes	Define whether or not the watch list should display a count of elements with verified changes during the activity period.
Recently requested changes	Define whether or not the watch list should display a count of elements with requested changes during the activity period.
Recently completed changes	Define whether or not the watch list should display a count of elements with changes completed during the activity period.
New changes	Define whether or not the watch list should display a count of elements with new changes added during the activity

	period.
Incomplete changes	Define whether or not the watch list should display a count of elements with incomplete changes during the activity period.
High Priority events	Define whether or not the watch list should display a count of elements with events set to high during the activity period.
Verified defects	Define whether or not the watch list should display a count of elements with verified defects during the activity period.
Recently reported defects	Define whether or not the watch list should display a count of elements with defects reported or 'requested' during the activity period.
Recently resolved defects	Define whether or not the watch list should display a count of elements with defects completed during the activity period.
New defects	Define whether or not the watch list should display a count of elements with defects added during the activity period.

Incomplete defects	Define whether or not the watch list should display a count of elements with incomplete defects during the activity period.
Verified issues	Define whether or not the watch list should display a count of elements with verified issues during the activity period.
Recently reported issues	Define whether or not the watch list should display a count of elements with issues reported or 'requested' during the activity period.
Recently resolved issues	Define whether or not the watch list should display a count of elements with issues completed during the activity period.
New issues	Define whether or not the watch list should display a count of elements with issues added during the activity period.
Incomplete issues	Define whether or not the watch list should display a count of elements with incomplete issues during the activity period.

Verified tasks	Define whether or not the watch list should display a count of elements with verified tasks during the activity period.
Recently reported tasks	Define whether or not the watch list should display a count of elements with requested tasks during the activity period.
Recently resolved tasks	Define whether or not the watch list should display a count of elements with tasks completed during the activity period.
New tasks	Define whether or not the watch list should display a count of elements with tasks added during the activity period.
Incomplete tasks	Define whether or not the watch list should display a count of elements with incomplete tasks during the activity period.
Recently reported events	Define whether or not the watch list should display a count of elements with requested events during the activity period.
Incomplete events	Define whether or not the watch list should display a count of elements with

	incomplete events.
Verified decisions	Define whether or not the watch list should display a count of elements with verified decisions during the activity period.
Recently reported decisions	Define whether or not the watch list should display a count of elements with requested decisions during the activity period.
Recently resolved decisions	Define whether or not the watch list should display a count of elements with decisions resolved during the activity period.
New decisions	Define whether or not the watch list should display a count of elements with decisions added during the activity period.
Incomplete decisions	Define whether or not the watch list should display a count of elements with incomplete decisions during the activity period.

# Configure WebEA models - via Text Editor

WebEA models can be configured by directly editing WebEA's webea\_config.ini file which resides in the \includes\ sub-folder of WebEA.

E.g. C:\xampp\htdocs\webea\includes\webea\_config.ini

Options are grouped under section headers, which are enclosed by square brackets. Each option must be defined on a separate line and follow the syntax:

{option name} = "{option value}"

### Note that:

- Option values are enclosed by double quotes
- The configuration file supports comments; the semi-colon character starts a comment
- The default 'webea\_config.ini' file included in the installation package contains samples of how models can be configured

# Why are there so many options?

In order to offer the greatest level of flexibility in how WebEA models can be accessed and used, Sparx Systems provides a large number of configuration options, which can be daunting when the complete list is viewed for the first time. However, to minimize your effort in understanding and managing the options, most are also grouped by prefix (sscs, login, add, edit and wl), which helps you to quickly understand what a particular option is used for.

### The Model List

The first section in the configuration file is '[model\_list]'; this section defines the model names that will be displayed to WebEA users on the 'Login' page. There is no limit to the number of models that can be defined; however, when there are more than ten models the login screen will automatically show a vertical scroll bar.

The model names have no direct link to the physical server or database name of the models they are describing, so you are free to use any meaningful name.

### For example:

```
[model_list]

model1 = "Model One (no updates)"

model2 = "Model One with discussions"

model3 = "Model Two with user login"

model4 = "Model Three with all options"

model5 = "Sparx Systems Sample Model"
```

Note: it is important that the 'modelx' definitions are consecutive; any out-of-sequence model numbers will be ignored and no further models will be added to the WebEA

Login page.

# **Model options**

For each numbered model found in the '[model\_list]' section a matching '[modelx : settings]' section is expected, further down the configuration file. All options within this section relate to that model only; that is, options can not be shared between models.

### For example:

```
[model1 : settings]

sscs_protocol = "http"

sscs_server = "localhost"

sscs_port = "80"

sscs_db_alias = "model1"

auth_code = ""

login_prompt = "false"

default_diagram = ""

show_discuss = "false"
```

## Model connection settings

Probably the most important settings for any model are the connection-related ones, prefixed with sscs (which stands

for 'Sparx Systems Cloud Server'). This group of settings defines how WebEA will connect and communicate with the Pro Cloud Server for data retrieval.

All communication between WebEA and the Pro Cloud Server is performed via the PHP cURL library, therefore some of the connection settings relate directly to the cURL options.

Option	Description
sscs_protocol	Defines the protocol to be used to connect to the Sparx Systems Pro Cloud Server.  Options: http or https  Default: http  Example: sscs_protocol = "http"  Note: When using the https protocol the configuration should also include sscs_use_ssl = "true". If you are using a self-signed certificate then sscs_enforce_certs = "false" should also be included.
sscs_port	Defines the TCP port used to connect to the Sparx Systems Pro Cloud Server. This port number must match one of the ports the Sparx Systems Pro Cloud Server is listening to or, in the case of an IIS setup, the IIS port servicing this repository.

	<b>Default:</b> 80
	Example: $sscs_port = "80_4"$
sscs_server	Defines the fully qualified machine name or IP address of the server hosting the Pro Cloud Server.  Default: localhost  Example: sscs_server = "sparxpublic.com" or sscs_server = "197.168.0.10"
sscs_use_ssl	As of WebEA version 3.01.23.1690 (included in Pro Cloud Server 3.0.23) this option is no longer used, instead WebEA determines this value dynamically based on the protocol in use, HTTP - sscs_use_ssl=false and HTTPS - sscs_use_ssl=true.  WebEA versions prior to 3.0.23.1690 uses this value to defines if all communications between WebEA and Pro Cloud Server should use SSL (secure socket layer). When this value is true, the protocol should be set to "https".  Options: true or false  Default: false Example: sscs_use_ssl = "false"

sscs_db_alias	Defines the database alias name of the model repository hosted on the Pro Cloud Server. This corresponds to the 'Database Alias' identified in the Pro Cloud Server Configuration Client or the 'Model Name' on the Enterprise Architect's Cloud Connection screen. The value is case sensitive.  Default: ea  Example: sscs_db_alias =  "RepositoryName"
sscs_enforce _certs	When SSL is set to true this option defines whether or not cURL will enforce that the certificate installed in Pro Cloud Server is correctly signed by a Certificate Authority.  Note: If you are using a self-signed certificate for Pro Cloud Server, this option must be set to false.  Options: true or false  Default: true  Example: sscs_enforce_certs = "false"
sscs_model_ user	Defines the model user login (as defined in Enterprise Architect User Security) that will be used in combination with the sscs_model_pwd option to login to a

security enabled model.

#### Note:

- Starting in Pro Cloud Server version 3.0.23 When set, all other authentication schemes are bypassed, including Windows Authentication, OpenID and basic username/password login.
- Sparx Systems would recommend the use of this option only on a model that has been configured as read only, since all updates made by WebEA users in this configuration will be identified as the same user.

### **Default:**

**Example:** sscs\_model\_user = "webuser"

# sscs\_model\_pwd

Defines the password (as defined in Enterprise Architect User Security) that will be used in combination with the **sscs\_model\_user** option to login to a security enabled model.

### Note:

• Starting in Pro Cloud Server version 3.0.23 - When set, all other authentication schemes are bypassed, including Windows Authentication,

OpenID and basic username/password login.
• Sparx Systems would recommend the use of this option only on a model that has been configured as read only, since all updates made by WebEA users in this configuration will be identified as the same user.
<b>Default:</b>
Example: sscs_model_pwd = "pwdxxx"

# Model general settings

These options define how WebEA users can access and display objects within the model.

Option	Description
auth_code	Defines the authorization code all WebEA users must enter before they can access the model. If this value is blank, WebEA users are not prompted to enter a code.  This option is only used for basic username/password authentication and is not used for Windows Authentication or

### OpenID.

It's possible to set this option and also set sscs\_model\_user. In this case the user will be required to enter the access code only and will not be prompted for a username or password.

**Options:** text

**Default:** blank

**Example:** auth\_code = "JWG47<sub>8"</sub>

### login\_prompt

This option is no longer used as of WebEA version 3.0.23.1690 (included in Pro Cloud Server 3.0.23). Basic authentication username and password fields will show for models that allow basic authentication (that is, are not restricted to SSO logins).

The basic authentication (username/password) will show for security enabled models that have not set *sscs\_model\_user*.

Windows Authentication, if enabled for the model, will be attempted automatically when selecting the model. OpenID authentication, if enabled in the model, will show above any basic authentication prompt.

	For older versions of WebEA the option is used to define whether or not all WebEA users must enter a model user/password before they can access the model.  Note: When this option is set to false and the model has security enabled, the sscs_model_user and sscs_model_pwd options must also be used to specify the logon credentials.  Options: true or false  Default: false  Example: login_prompt = "false"
login_allow_ blank_pwd	When the 'login_prompt' option is set to true, this option defines whether or not WebEA will attempt to send blank passwords to the Pro Cloud Server for validation.  Options: true or false  Default: false  Example: login_allow_blank_pwd = "false"
miniprops_na vigates	When the 'miniprops_navigates' option is set to true selecting certain 'navigable' elements will cause WebEA to navigate

to the target of these elements. Examples of such 'navigable' elements are Hyperlinks and Navigation Cells. For all other elements, selecting them will display the properties of the element in the Properties View. This option has no effect when the Properties View is not shown.

**Options:** true or false

**Default:** true

**Example:** miniprops navigates =

"false"

### navigate\_to\_ diagram

As of WebEA version 3.01.23.1690 (included in Pro Cloud Server 3.0.23) the default selection of some objects on diagrams has changed to match Enterprise Architect behavior. This applies to i) Composite Elements and ii) Package elements that contain a diagram.

### **Composite Elements**

A composite element on a diagram will navigate directly its composite diagram.

### **Package Elements**

A Package element on a diagram will navigate to the first child diagram contained within the selected Package. If the selected Package does not contain any

	diagrams then the package's properties are displayed.
	When navigate_to_diagram is set to false, selecting either a composite element or package element on a diagram will display the selected elements properties.
	<b>Options:</b> true or false
	Default: true
	Example: composite_navigates = "false"
show_discuss	Defines whether or not discussions on Packages and elements should be displayed within the WebEA interface.  Options: true or false  Default: false  Example: show_discuss = "true"
participate_in _reviews	When set to true, 'participate_in_reviews' allows users of WebEA to Join reviews that will automatically assign all discussions to the joined review. In order to make full use of this option show_discuss and add_discuss would also have to be set to true.  Options: true or false  Default: false

	Example: participate_in_reviews = "false"
use_avatars	When the 'use_avatars' option is set to true, all discussion messages are displayed with the creating user's avatar. When set to false a set of generic images representing discussions and replies is used instead.
	Options: true or false  Default: true
	<b>Example:</b> use avatars = "false"
	Example: usc_avatars — rarse
recent_search _days	Defines the number of days the predefined 'Recent' searches should consider. For example if this value was set to '7' then whenever a user invokes the search for 'Recent elements', all elements modified in the previous 7 days will be returned.
	<b>Options:</b> any positive integer value
	<b>Default:</b> 3
	<b>Example:</b> recent_search_days = "10"
prop_sec_ <se ction&gt;_visibl e</se 	Defines whether or not a property section (or "feature") is accessible.  If a feature is not visible then the button to display that feature will not be

available in the Main View, and the Feature will not be listed in the 'Select Feature' menu in the Properties View.

<section> can be one of:

- location
- instances
- relationships
- taggedvalues
- testing
- resourcealloc
- attributes
- operations
- files
- runstates
- features
- changes
- documents
- defects
- issues
- tasks
- events
- decisions
- efforts
- risks
- metrics

**Options:** true or false

Default: true

**Example:** prop sec testing visible =

"true"

prop\_sec\_<se
ction>\_expan
ded

This option is no longer used as of WebEA version 3.0.23.1690 (included in Pro Cloud Server 3.0.23). Property sections are no longer displayed as expandable/collapsible panels.

Defines whether or not a property section is expanded by default when the model is opened.

The property view includes numerous sections that can be optionally expanded or collapsed; these options set the default values for the model.

<section> can be one of:

- info
- location
- instances
- relationships
- taggedvalues
- testing
- resourcealloc
- attributes
- operations

- runstates
- changes
- defects
- issues
- tasks
- events
- decisions
- efforts
- risks
- metrics

**Options:** true or false

**Default:** false for all sections except

'info' and 'location', which are true

**Example:** prop\_sec\_testing\_expanded

= "true"

default\_diagr am Defines the GUID of the diagram that should be automatically loaded when users log onto the model. If this option is not defined or an empty value is specified, WebEA assumes that no diagram should be loaded and displays the model root instead. The GUID of any diagram can be obtained from WebEA by loading the diagram properties.

Note: The entire GUID (including {})

	must be used. <b>Example:</b> default_diagram =  "{C89E174A-19B0-47c7-B4A8-8A9807 1CD838}"
default_main _layout	Defines the default layout of container items for the current model. WebEA can display child items of a container in one of three layouts. Either Icon view (the default), Notes view (resembling the Enterprise Architect Specification Manager view) or List view.  Options: icon, notes or list  Default: list  Example: default_main_layout = "icon"
object_order	Defines the order of objects in the Browser and Object List views. There are 3 different ordering behaviors, represented by values 1,2, 3.  "1" = Alphabetical.  Objects are sorted Alphabetically (by name).  "2" = Free Sort.  Objects are sorted based on their "Set Position" (manual sorting which is

applied in EA), then Alphabetically. This reflects EA's sorting when the "Allow Free Sorting" option is enabled.

"3" = Object Type.

Objects are sorted by type, then Set Position, then Alphabetically. This reflects EA's sorting when the "Allow Free Sorting" option is disabled.

**Options:** 1, 2 or 3

**Default:** 3

**Example:** object\_order = "2"

Note, regardless of the object\_order setting WebEA displays Diagrams, then Packages, then Elements. The object\_order applies to the items within each of these groupings.

favorites\_as\_ home When set to true, the WebEA 'Home' will display the User's 'Favorites' Packages in the Browser/Package View. This is loaded when first accessing the model, and also when using WebEA's Home button.

The Browser's Up button is also hidden, helping to keep navigation within the

Favorites package/s.

**Options:** true or false

**Default:** true

**Example:** show\_browser = "false"

### Note:

- When set to true, this overrides the default\_diagram setting.
- Favorites are defined using Enterprise Architect. Refer to the link in the See Also column for details.
- If a user has no Favorites defined then the Model Root or Default Diagram (if one is defined) will be loaded instead.

show\_browse

Defines the default visibility of the Browser.

**Options:** true or false

**Default:** true

**Example:** show browser = "false"

Note:

- If a user selects the 'Mobile' option when logging in to WebEA then this overrides the show\_browser option and the Browser will be hidden
- This behavior can be overridden,

	depending on the screen resolution; for example, on a low resolution screen such as a mobile phone, the Browser will be hidden regardless of the show_browser option
show_propert iesview	Defines the default visibility of the 'Properties View'.  Options: true or false  Default: true
	<ul> <li>Example: show_propertiesview = "false"</li> <li>Note: <ul> <li>If a user selects the 'Mobile' or 'Tablet' option when logging in to WebEA, this overrides the 'show_propertiesview' option and the 'Properties View' will be hidden</li> <li>This behavior could be overridden depending on the screen resolution; for example, on a low resolution screen such as a mobile phone, the 'Properties View' will be hidden regardless of the show_propertiesview option</li> </ul> </li> </ul>
show_path_b utton	Defines the visibility of the Object Path button. When set to true, the Path button is available in WebEA's Navigation Bar. The Path button is used to display a list of

Packages/Objects from the current Object up to the Model Root.
<pre>Options: true or false Default: true Example: show_path_button = "false"</pre>
Setting this option to false can help in keep WebEA focused on a specific area of your Model, especially when used in conjunction with favorites_as_home = "true".

# Model update settings

This group of settings determine what insert/edit options are available to WebEA users.

Note: Within the Pro Cloud Server it is possible to configure a model as 'Read-only'; this setting in the Pro Cloud Server will override any WebEA update setting, forcing them to false.

Option	Description
add_discuss	Defines whether or not new discussions on Packages and elements can be added

	to the model. Note: This option is forced to false if 'show_discuss' has been set to false.  Options: true or false  Default: false  Example: add_discuss = "true"
add_objects	Defines whether or not new objects can be added to the model.  Note: this option will be internally set and restricted to 'false" for Pro Cloud Server Express installations.  Options: true or false  Default: false  Example: add_objects = "true"
add_diagram s	Defines whether or not new diagrams can be added to the model.  Note: this option will be internally set and restricted to 'false" for Pro Cloud Server Express installations.  Options: true or false  Default: false  Example: add_diagrams = "true"
add_objectty pe_ <type></type>	Defines whether or not elements of the given object type can be added to the

model.

These options are forced to false if 'add\_objects' has been set to false.

<type> can be one of:

- package
- review
- actor
- change
- component
- feature
- issue
- node
- · requirement
- task
- usecase

**Options:** true or false

**Default:** false

**Example:** add\_objecttype\_actor =

"true"

add\_object\_f
eatures

Defines whether or not element features can be added to the model.

Note: this option will be internally set and restricted to 'false" for Pro Cloud Server Express installations.

**Options:** true or false

	<b>Default:</b> false
	<b>Example:</b> add_object_features = "true"
add_objectfe ature_ <type></type>	Defines whether or not element features of the given type can be added to the model.  These options are forced to false if
	'add_object_features' has been set to false.
	<type> can be one of:</type>
	• tests
	• resources
	• features
	• changes
	<ul> <li>documents</li> </ul>
	• defects
	• issues
	• tasks
	• risks
	<b>Options:</b> true or false
	<b>Default:</b> false
	Examples: add_objectfeature_changes = "true"
edit_objectfe ature_resourc es	Defines whether or not the details of element resource allocations can be edited in the model.

	Note: this option will be internally set and restricted to 'false" for Pro Cloud Server Express installations.  Options: true or false  Default: false  Example:
	edit_objectfeature_resources = "true"
edit_objectfe ature_tests	Defines whether or not the details of element tests can be edited in the model.  Note: this option will be internally set and restricted to 'false" for Pro Cloud Server Express installations.  Options: true or false  Default: false  Example: edit_objectfeature_tests = "true"

# Model watchlist settings

The watchlist functionality allows users to quickly see a wide variety of objects that have changed recently in the model. WebEA users can configure their personal preferences to control what sort of objects they are interested in 'watching'.

All watchlist settings are prefixed by 'wl\_' and represent the default value for the model. However, once a user saves their own watchlist settings the model defaults will no longer be used.

In order to persist the watchlist preferences across sessions, WebEA saves them in a browser cookie. If the user's browser does not allow the saving of cookies, personal watchlist settings can not be persisted across sessions.

Option	Description
cookie_retent ion	Defines the period over which a WebEA user's set of Watch list options are stored. The value is the number of days that the cookies will be retained for.
	<b>Options:</b> any positive integer value
	<b>Default:</b> 365
	Example: cookie_retention = "180"
wl_period	Defines the default activity period of the model watchlist. The value is a number of days; for example, look for activity in the last 10 days.
	<b>Options:</b> any positive integer value <b>Default:</b> 0
	Example: wl_period = "10"
wl_recent_di scuss	Define whether or not the watch list should display a count of elements that

	have had discussions during the activity period.
	Options: true or false  Default: false
wl_recent_re views	Define whether or not the watch list should display a count of review elements that have been added or modified during the activity period.  Options: true or false  Default: false
wl_recent_di agram	Define whether or not the watch list should display a count of added/modified diagrams during the activity period.  Options: true or false  Default: false
wl_recent_el ement	Define whether or not the watch list should display a count of added/modified elements during the activity period.  Options: true or false  Default: false
wl_resalloc_a ctive	Define whether or not the watch list should display a count of elements with active resource allocations during the activity period.

	Options: true or false
	Default: false
wl_resalloc_t oday	Define whether or not the watch list should display a count of elements with resource allocations ending during the activity period.  Options: true or false  Default: false
wl_resalloc_ overdue	Define whether or not the watch list should display a count of elements with resource allocations that fall overdue during the activity period.  Options: true or false  Default: false
wl_test_recen tpass	Define whether or not the watch list should display a count of elements with tests that passed during the activity period.  Options: true or false  Default: false
wl_test_recen tfail	Define whether or not the watch list should display a count of elements with tests that failed during the activity period.  Options: true or false

	Default: false
wl_test_recen tdefer	Define whether or not the watch list should display a count of elements with tests that were deferred during the activity period.  Options: true or false  Default: false
wl_test_recen tnotchk	Define whether or not the watch list should display a count of elements with tests that were not checked during the activity period.  Options: true or false  Default: false
wl_test_notru n	Define whether or not the watch list should display a count of elements with tests that were not run during the activity period.  Options: true or false  Default: false
wl_feature_v erified	Define whether or not the watch list should display a count of elements with verified features during the activity period.  Options: true or false

	Default: false
wl_feature_re quested	Define whether or not the watch list should display a count of elements with requested features during the activity period.  Options: true or false  Default: false
wl_feature_c ompleted	Define whether or not the watch list should display a count of elements with features completed during the activity period.  Options: true or false  Default: false
wl_feature_n ew	Define whether or not the watch list should display a count of elements with new features added during the activity period.  Options: true or false  Default: false
wl_feature_in complete	Define whether or not the watch list should display a count of elements with incomplete features during the activity period.  Options: true or false

	<b>Default:</b> false
wl_change_v erified	Define whether or not the watch list should display a count of elements with verified changes during the activity period.  Options: true or false  Default: false
wl_change_r equested	Define whether or not the watch list should display a count of elements with requested changes during the activity period.  Options: true or false  Default: false
wl_change_c ompleted	Define whether or not the watch list should display a count of elements with changes completed during the activity period.  Options: true or false  Default: false
wl_change_n ew	Define whether or not the watch list should display a count of elements with new changes added during the activity period.  Options: true or false

	Default: false
wl_change_i ncomplete	Define whether or not the watch list should display a count of elements with incomplete changes during the activity period.  Options: true or false  Default: false
wl_document _verified	Define whether or not the watch list should display a count of elements with verified documents during the activity period.  Options: true or false  Default: false
wl_document _requested	Define whether or not the watch list should display a count of elements with requested documents during the activity period.  Options: true or false  Default: false
wl_document _completed	Define whether or not the watch list should display a count of elements with documents completed during the activity period.  Options: true or false

	Default: false
wl_document _new	Define whether or not the watch list should display a count of elements with new documents added during the activity period.  Options: true or false  Default: false
wl_document _incomplete	Define whether or not the watch list should display a count of elements with incomplete documents during the activity period.  Options: true or false  Default: false
wl_defect_ve rified	Define whether or not the watch list should display a count of elements with verified defects during the activity period.  Options: true or false  Default: false
wl_defect_re quested	Define whether or not the watch list should display a count of elements with defects reported or 'requested' during the activity period.  Options: true or false  Default: false

wl_defect_co mpleted	Define whether or not the watch list should display a count of elements with defects completed during the activity period.  Options: true or false  Default: false
wl_defect_ne w	Define whether or not the watch list should display a count of elements with defects added during the activity period.  Options: true or false  Default: false
wl_defect_in complete	Define whether or not the watch list should display a count of elements with incomplete defects during the activity period.  Options: true or false  Default: false
wl_issue_veri fied	Define whether or not the watch list should display a count of elements with verified issues during the activity period.  Options: true or false  Default: false
wl_issue_req	Define whether or not the watch list

uested	should display a count of elements with issues reported or 'requested' during the activity period.  Options: true or false  Default: false
wl_issue_co mpleted	Define whether or not the watch list should display a count of elements with issues completed during the activity period.  Options: true or false  Default: false
wl_issue_ne w	Define whether or not the watch list should display a count of elements with issues added during the activity period.  Options: true or false  Default: false
wl_issue_inc omplete	Define whether or not the watch list should display a count of elements with incomplete issues during the activity period.  Options: true or false  Default: false
wl_task_verif ied	Define whether or not the watch list should display a count of elements with

	verified tasks during the activity period.  Options: true or false  Default: false
wl_task_requ ested	Define whether or not the watch list should display a count of elements with requested tasks during the activity period.  Options: true or false  Default: false
wl_task_com pleted	Define whether or not the watch list should display a count of elements with tasks completed during the activity period.  Options: true or false  Default: false
wl_task_new	Define whether or not the watch list should display a count of elements with tasks added during the activity period.  Options: true or false  Default: false
wl_task_inco mplete	Define whether or not the watch list should display a count of elements with incomplete tasks during the activity period.  Options: true or false

	Default: false
wl_event_req uested	Define whether or not the watch list should display a count of elements with requested events during the activity period.  Options: true or false  Default: false
wl_event_hig h	Define whether or not the watch list should display a count of elements with events set to high during the activity period.  Options: true or false  Default: false
wl_event_inc omplete	Define whether or not the watch list should display a count of elements with incomplete events.  Options: true or false  Default: false
wl_decision_ verified	Define whether or not the watch list should display a count of elements with verified decisions during the activity period.  Options: true or false  Default: false

wl_decision_ requested	Define whether or not the watch list should display a count of elements with requested decisions during the activity period.  Options: true or false
	Default: false
wl_decison_c ompleted	Define whether or not the watch list should display a count of elements with decisions completed during the activity period.  Options: true or false
	<b>Default:</b> false
wl_decision_ new	Define whether or not the watch list should display a count of elements with decisions added during the activity period.
	Options: true or false
	<b>Default:</b> false
wl_decision_ incomplete	Define whether or not the watch list should display a count of elements with incomplete decisions during the activity period.
	Options: true or false  Default: false

# How to configure WebEA Localization

The physical text values of all labels and messages within WebEA are defined in a single file that is read when the web pages are being built. This allows WebEA customers to tailor the content of web pages displayed to their users.

WebEA's default language is English. As pages are built on the server, the WebEA application will check whether there is a defined localization for a string and use that. If a localized version of the string is not defined then WebEA will use the default English value.

The WebEA localization definitions are saved in the file 'webea\_strings.ini' in the '\includes\' folder. The localization file is saved in plain text format with each localized string being defined on a separate line with the syntax:

```
{default_english_string} = "{localized_string}"
```

#### Note that:

- Localized string values are enclosed by double quotes
- The configuration file supports comments; the semi-colon character starts a comment
- The supplied 'webea\_strings.ini' file includes a definition of all strings used within the WebEA application, therefore there is no need to add any new lines to the file

For example, on the login page the first label is "Select Model" in the English version; however, a French user would want to change this text to:

Select Model = "Sélectionnez le modèle"

## Replacements

The wording of some labels/messages within WebEA requires the names of items to be added to the string displayed. Such replacements are denoted by the %s placeholder. The localized versions of these strings should also include the %s placeholder in the appropriate position.

The other standard replacement that WebEA supports is the replacement of %NN% with a number. For example, in the Watchlist when WebEA detects that elements have been modified recently, this message is used:

%NN% recently modified element%S% = "%NN% recently modified element%S%"

%NN% will be replaced with a count of recently modified elements.

#### **Plurals**

Given the nature of the English language, some of the localized strings support the ability to display words in their plural form. WebEA supports the special substitution of %S% which will replace, %S% with 's' when the supplied number is greater than 1. Using our example, when a single element has been modified recently the message displayed on the watchlist page is:

1 recently modified element

However, when there are five recently modified elements, WebEA would generate the message:

5 recently modified elements

### **Advanced SSL**

## Adding trust to a Self-Signed Certificate

A self-signed SSL certificate can be signed with your own Certificate Authority (CA). This allows trust to be added to clients to avoid security warnings. The instructions for adding a CA to a client vary by operating system or browser used.

See Add Trust with a Certificate Authority (CA) for instructions on generating a CA and using it to sign server certificates.

WebEA uses PHP and cURL to communicate with a Pro Cloud Server. To enable PHP/curl to trust a new CA: Add/edit 'curl.cainfo' in php.ini to point to either a single root CA certificate or a CA bundle file (this is multiple crt files concatenated together).

#### [curl]

; A default value for the CURLOPT\_CAINFO option. This is required to be an

; absolute path.

curl.cainfo="C:\xampp\php\MyCompanyCA.crt"

Restart Apache/PHP.

# Single Sign-On (SSO) with WebEA

As with Enterprise Architect, WebEA can make use of the following Single Sign-On Systems:


- Windows authentication with Active Directory
- OpenID

The ability to use Single Sign-On for WebEA is based on the configuration of the Enterprise Architect Model itself.

## **Steps**

Ste p	Description
1	Using Enterprise Architect, configure the Model to use Single Sign-On.
2	Using Enterprise Architect, confirm that the Model can be accessed via Single Sign-On.
3	If you intend to use OpenID, ensure that your OpenID server configuration includes the WebEA login_sso.php page as a valid redirect/callback URI. For example,

	http://myserver/webea/login_sso.php
	Or (if the OpenID provider supports wildcards),
	http://myserver/webea/*
4	If you have not already, configure WebEA to access the Model.
	No WebEA configuration options are required specifically for Single Sign-On (WebEA will detect that Single Sign-On is enabled in the Model).
5	Login to the Model via WebEA.  The WebEA login screen will provide "Login with OpenID" and/or "Login with Windows ID" buttons, allowing you to log in via Single Sign-On.



### **Web Browser Considerations**

Single Sign-On support can vary depending on the Web Browser being used to access WebEA.

WebEA's Windows Authentication makes use of the NTML authentication protocol. Web Browsers typically require some configuration to make use of NTLM authentication. For example, see:

https://www.websense.com/content/support/library/web/host ed/iseries\_deploy/ntlm\_firefox.aspx

As with Enterprise Architect, for OpenID support an OpenID server must be configured and accessible by your Web Browser.

The OpenID server must support the 'OpenID Connect' standard and should be able to return a unique user identifier in the 'user\_info' request. This user identifier will be matched to a local model user.

### WebEA User Guide

Sparx System's WebEA is an external interface to Enterprise Architect models through which users can review and comment on a model, in real time via the web, on a range of mobile devices or a remote work station, without needing to install Enterprise Architect. The reviewer can be anywhere in the world, and does not need to be in an office, just somewhere where internet access is available. It is ideal for stakeholders and clients to see the work in which they are invested, and to comment on and discuss aspects of the model.

WebEA models can be configured to allow users to update element notes, add element features (such as tests and resource allocations) and even create Project Management elements (to record issues, changes and similar), or Use Cases, Requirements and system components.

WebEA is the interface to the model, so although you are using your web browser, the data shown is the same as that shown when you use Enterprise Architect. This means that all model updates occur in real time, so WebEA users can be confident that they are seeing the latest version of the model structure.

## **How to Open WebEA**

Open the web browser on your device and, in the address bar, type in the complete WebEA URL. Press the Enter key

or tap the Go key.

These are some examples of the complete URL that might be needed to open WebEA.

https://demo.sparxpublic.com

In the case where the web server has the IP of 11.22.33.44 and has been configured to use the non-standard port of 800, the complete URL would be:

https://11.22.33.44:800

If the WebEA application files were placed in a sub-folder called 'WebEA' under the web server's root folder, then the complete URL would be:

http://11.22.33.44:800/WebEA/

If the entered URL is a valid, the WebEA Login page is shown, which will show all the models that are available.



## **Acknowledgements**

WebEA incorporates certain components developed by third parties. Sparx Systems acknowledges the contribution made to the WebEA product by these components.

- jQuery v1.12.3 jQuery Foundation
- NicEdit ©2007-2008, Brian Kirchoff, under license from MIT
- Date Picker for jQuery v5.1.1, Keith Wood, under license from MIT

# Login

WebEA websites are configured to allow access to one or more Enterprise Architect models, each of which can be configured independently to only grant access to users with valid logon credentials. WebEA user validation supports two forms of security: 1) an access code and 2) standard Enterprise Architect model security. These two validation methods can be used independently or in combination in each model.

#### **Prerequisites**


Users of WebEA will need to be advised of their login credentials for each model, which will include:

- An access code, or
- A user ID and password, or
- Possibly all three

This data will be provided to you by your Web Administrator or by the Project Manager responsible for the model.

## Logging In

The first page that is displayed in WebEA is the 'Login' page, which lists the models available to you.




Select the model you want to open, then click or tap on either the Mobile, Tablet, or Desktop button. The button selected determines whether the Browser and Properties View will be enabled by default.


If access to your model requires only an access code, then the 'Login' page prompts you for this.

#### Note:


- The red asterix (\*) denotes a mandatory field.
- Access Codes are not required for Windows Authentication or OpenID authentication.



If User Security has been applied to the model, the 'Login' page prompts you for your user ID and password.



If the model requires both an access code and a user id/password, the 'Login' page prompts for both together:



#### Single Sign On

This feature is available from Enterprise Architect Release 14.1 and Pro Cloud Server Release 3.0 build 23.


If the Enterprise Architect model has been configured for Windows and/or OpenID authentication then the 'Login' page will show the relevant single sign buttons 'Login with OpenID' or 'Login with Windows ID'. Clicking the OpenID login button will redirect the user to the OpenID Server Authentication page. After authenticating with OpenID the browser will automatically return to WebEA and log the user in.

If the user is already authenticated with OpenID, the OpenID website might not be displayed, and the user will simply be logged in.

If the model is configured to also allow manual login then both the Single Sign On buttons and manual login fields will be visible on the Login page. If the option 'Restrict access to Windows & OpenID users only' is checked then the manual login fields will not be available.

#### See:

Single Sign-On (SSO) Options



If you do not have the authorization data, click or tap on the Back button to go back and select another model.

Otherwise, type in your access code and/or user ID and password, and click on the Login button.

# WebEA's layout

Having logged on to a model in WebEA, depending on how the model has been configured and the resolution of the Browser/Device, WebEA will typically display the Model root node/s in either the Browser (on the left), or in the Main Content area.

Alternatively, if the WebEA Model connection has been configured with a default diagram, then the diagram will be displayed.


From this point you can start navigating the model by selecting objects or links, review the organization and contents of the model elements, and read and add to discussions or reviews of particular structures.

Note: WebEA only supports single click when using a PC, or single touch when using a touch-enabled device.

The image below shows the WebEA screen after loading the example model, when no default diagram has been configured.



The image below shows the WebEA screen after loading the example model, when a default diagram has been configured.



The WebEA view can be broken into four sections: heading, navigation bar, content area and status bar.

Note: In order to support small screen devices, some layout

sections move or merge with others to minimize the amount of screen real estate needed. For example, the heading section merges with the Navigation bar when the screen height goes below 400 pixel<sub>s</sub>.

## Heading



WebEA's heading area displays the application logo in the top left corner, the name of the currently opened model, a search icon and a 'hamburger' icon. The search and 'hamburger' icons contain further options that are accessible when selected.

#### Search



The search icon provides access to the search functionality offered by WebEA. The functionality includes a number of standard searches, and the custom search.

Icon	Description
Goto item	
*	Select to display the 'Goto WebEA item'
	dialog, into which you paste (Ctrl+V) a
	WebEA item's unique ID that you have
	copied earlier, using the 'Object Link'

	option in the Hamburger menu (see the <i>Hamburger</i> table in this topic). Click on the Go button to load the details of the specified object.
Reviews	Select to display a list of all recently modified Review elements.  Note: The number of days that are considered 'recent' is defined as a configuration option for the model.
Discussions	Select to display a list of all elements to which a Discussion item has been recently added.
Diagrams	Select to display a list of all recently modified diagrams.
Elements	Select to display a list of all recently modified elements (new Discussion items are not regarded as modifications to the element).
Custom search	Select to display the 'Custom Search' dialog. WebEA provides a facility that enables you to search through the model for a specific item or group of items that have certain characteristics.

# Hamburger



The hamburger icon provides access to these options:

Icon	Description
Object Link	Select to display the 'Link to WebEA item' dialog, which shows the current object's unique ID and full URL. You can highlight the ID and press Ctrl+C to copy it, then at a later point use it in the 'Goto WebEA item' dialog to return directly to that page, as described in the Search table earlier.
	Alternatively, you can copy the full URL and send it to another user if you want them look at a particular item.
	Note, this option is only supported when displaying a specific Object (Diagram, Element or Package). It is not supported for the Watchlist, Matrix, etc.
Watchlist	Select to display the 'Watchlist summary'. The Watch List facility in WebEA helps

	you to quickly identify recent activity in the model.
Matrix	Select to display the 'Matrix Profiles'
bestrail	page, which helps you to select any matrix profile defined in the model and to display the associated Relationship Matrix.
Logout	Choose this option if you want to disconnect from the current model. After
	the logout process has run, the 'Login' dialog automatically displays.

# **Navigation Bar**



The Navigation bar provides information and buttons that assist in navigating an Enterprise Architect model.

Icon	Description
Home	Click on this button to return focus to the 'home' object for the current model. The home object is either the model's default diagram (if defined in the configuration file) or the model root Package.

Object Path	Click on this button to display the complete path of parent nodes, Views, Packages and elements for the current object, all the way to the model's root node.  You can click on any item in the list (except for the last one, which is the current object) and navigate directly to that object.  Note:  • When viewing the root node there will
	<ul><li>be only one entry, which is not selectable.</li><li>Optionally, this button can be hidden using the 'Show Path Button'</li></ul>
Refresh	Click on this button to refresh the current view. For example, if you are currently viewing a diagram and a user in Enterprise Architect has made changes to it since you opened it, simply click the Refresh button; WebEA will display the newly updated diagram.
Current object	This is a read-only text field that displays the name and object type (displayed as an image) of the current object.

### **Properties**



This option is only accessible when the screen is less than 800 pixels in width. When viewing a Diagram or the contents of a Package, this button can be used to view the properties of the Diagram/Package itself.


When using a screen width which is more than 800 pixels you can access the properties of a Diagram/Package by displaying the Properties View, using the Properties button in the Status bar (see the Status bar section below for details).

#### **Content Area**

WebEA's content area adjusts and adapts to display a custom layout for the currently selected item, depending on its type. For example, when a diagram is selected the content area consists entirely of the diagram image, but when a Package is selected the content area displays a view of child objects in that Package.

See the *Content Area* section later in this guide for more details.

## Status bar



The WebEA Status bar is displayed at the very bottom of the page, and provides the following options and information.

Browser	Click this button to hide/show the 'Browser' view on the left side of the main content area. This area will contain the currently selected object and a list of all of its child objects. Between the object name and the name of the first child
	object is a * icon; clicking on this icon refreshes the display to show the next-highest level of the hierarchy.  Note: This option is disabled when the screen is less than 800 pixels in width.
Properties	Click this button to hide/show the 'Properties View' on the right side of the main content area.  When viewing a diagram the Properties View allows you to access properties of an element without navigating away from the diagram.  When viewing an element, the Properties
	When viewing an element, the Properties

View allows you to have a Split View of the element's properties, displaying one feature in the Main View while also showing another in the Properties View (for example, you could add Discussions in the Main View while referring to the element's notes in the Properties View).

Note: By enabling this option, links in the Diagram View are changed to populate the Properties View instead of navigating to the selected object. It is important to realize that selecting objects in the Diagram View while the Properties View is displayed will not affect the navigation history, so you can select as many objects as you need in the current view and see their properties without navigating away from the current diagram.

Note: This option is only accessible when the screen is more than 800 pixels in width.

## About



Click this button to display the "About WebEA" screen. The About screen provides information regarding the version of WebEA, Pro Cloud Server, and OSLC, as well as License and Model information.

# Review element

If you have joined a review, the name of the Review element will display in the Status bar on the left side of the Properties button. Click on the name to display the Review Element in WebEA's main view.

#### iOS Scrolling

When accessing WebEA via iPad or iPhone the status bar will display "iPad Diagram Scrolling: Off" or "iPhone Diagram Scrolling: Off" respectively. Touch this text to toggle the option On/Off.

Typically images can be scrolled on mobile devices by touching/dragging on the image, however iOS browsers will not scroll if you are touching a clickable area (such as an element on a diagram). This could make scrolling difficult on diagrams which are densely populated with clickable elements.


iPad/iPhone Diagram Scrolling: On Diagram elements will not be selectable, allowing you to scroll by touching/dragging anywhere on the diagram.

iPad/iPhone Diagram Scrolling: Off Diagram elements will be selectable, however to drag the diagram image you will need to ensure you are not touching a selectable element.

#### **Content Area**

The main content area of WebEA consists of:

- The **Main View** in the center. This is used for displaying such things as diagrams and element properties
- Optionally, the **Browser** on the left. This is used to assist in navigating the model.
- Optionally, the **Properties View** on the right. This allows you to view properties of an element while simultaneously viewing something else (such as a diagram) in the main view.



#### **Details**



Main View	The Main View typically displays these types of content: - A <b>Diagram</b> Image - The <b>Properties</b> of an element
	- A <b>list</b> of objects that are contained in a specific Package (or objects that are children of a specific element). This object list is only accessible when the Browser is not displayed (as the Browser functions as an alternative).
Browser	The Browser assists with Navigation, and provides context for the object which is currently displayed in the Main View
Properties View	The Properties View displays properties of a selected object. When viewing a Diagram, it allows you to view some properties of an element without navigating away from the diagram.

# **Main View - Object List**

In Main View's Object List the child objects of a container are represented in one of three viewing styles: Icon, List or Notes view.

It is possible to define a default viewing style for a model, in the configuration file. However, you can also change the style via the icons in the upper right of the Object List.



#### **Icon View**

In Icon view, each object is represented by an image and object name. As an example, a root node with the name 'ASA Finance' would be represented by:



A View object with the name 'Class Model' would be represented by:



#### **List View**

In List view each object is represented as a row in a table, which includes columns for name, type, author and modified date. The earlier examples would be represented in List view like this:

Name	Туре	Author	Modified
ASA Finance	ModelRoot		2017-01-20 17:21:03
Name	Туре	Author	Modified
Class Model	Package	admin	2017-11-15 10:40:54

#### **Notes View**

In Notes view each object is represented by the object name and any text from the object's 'Notes' field.

## **Display Order**

In Object View, objects are displayed in the predefined order: Packages, diagrams and elements; if there are multiples of any object type then they will be sorted in alphabetical order. This is different to Enterprise Architect's behavior, which can allow elements to be manually ordered.

As an example:









## **Additional Symbols**

While navigating the model structure with WebEA you might see a number of symbols applied to the object images. Each symbol has a meaning: the • symbol indicates that the object contains children, whilst the • symbol indicates the object is locked to the current user.

The action taken when an item is selected is dependent on the object type of the item.

- For Packages, the default action is to navigate down one level of the Browser window and display the child objects contained within that Package
- For diagrams the default action is to open the diagram image
- For elements the default action is to display the Properties for the selected element

To view the properties of a Package while viewing it in the Object View, click on the button in the status bar to display the Properties View. Alternatively, on lower resolution screens (less than 800 pixels wide), where the Properties View is not available, you can click on the button to view the Package's properties.

If you navigate to a Package that does not have children, the

message 'No child element(s)' will be displayed.

## **Adding New Elements**

If the model has been configured to allow the addition of elements and the current user has the required permissions,


the New icon will be shown as the last element of a Package's object view. For more details see the *Object Creation in WebEA* Help topic.

#### **Notes**

• WebEA's <u>WebEA - Browser</u> acts as an alternative to the Object List. If the WebEA Browser is displayed then the Object List is not accessible.

# **Main View - Diagram**

When a diagram is selected, the Main View content area displays the entire diagram as a single image. As an example, this is the Pro Cloud Server diagram in the EAExample model:



Objects on the diagram are selectable and, based on the object type and if the 'Properties View' is visible, will behave slightly differently.

The behavior when the 'Properties View' is <u>not</u> visible:

- Packages: opens the select Package in the Object View mode
- Diagrams: opens the selected diagram image

- Elements: opens the selected element in the Main View
- Hyperlinks to external URLs: navigates away from WebEA and loads the external URL

The behavior when the 'Properties View' is visible:

- Packages: main properties are displayed in the 'Properties View'
- Diagrams: main properties are displayed in the 'Properties View'
- Elements: main properties are displayed in the 'Properties View'
- panel
- Hyperlinks: navigate to link target


#### **Notes**

• To view the properties of a diagram either display the Properties View, or (when using a screen width less than 800 pixels) click on the ① button in the Navigation bar

# **Main View - Object Properties**


When selecting an element in WebEA its properties are displayed either in the Main View, or the Properties View (if it is currently displayed). If the Properties are displayed in the Properties View (to the right side of EA's Main View) then you can use the Full Properties button to display the element's full properties in the WebEA Main View.

The Main View Properties consist of a section at the top with common element properties, followed by a row of feature buttons (Notes, Relationships, etc) which can be used to access specific features. By default the Notes are displayed.



## **Common Properties**

The common properties section displays an image representing the object's type, and its name, type and stereotype. This is followed by general information about the object, such as author, time and date created and last modified, the version, phase and status. Note, the Properties View can also be enabled and displayed alongside the Main View's Object Properties. In this case the author, version, and other characteristics will only be displayed in the Properties View.



- If the model has been configured to allow it, there will be an element 'Hamburger' icon that allows the creation of object features; see the *Object Creation in WebEA* Help topic for further details
- If the element has a regular Linked Document applied, a line with 'Linked Document' and an Open button will be displayed immediately under the object's name and type fields; clicking on the Open button will display the contents of the Linked Document
- If the element has an encrypted Linked Document applied, in addition to the 'Linked Document' label and

Open button a password text box displays; if you enter the correct password and click or tap on the Open button the contents of the encrypted document will be displayed

- If the element has a stored Document applied, a Download button (along with the label 'Stored Document') will be displayed; clicking on the Download button will save the document to the user's machine where they can use the appropriate application to view it
- If the element has an image asset applied, a Download button (along with the label 'Image Asset') will be displayed; clicking on the Download button will save the image to the user's machine where they can use the appropriate application to view it

#### **Selectable Features**

After the Common Properties a number of buttons are displayed that allow you to view other features of the object (including Location, Tagged Values, Attributes and Operations). By default, the element Notes will be selected and displayed.



To the right of the feature buttons is a filter button.

Click this button to toggle between the following display

#### modes:

- **Single** In this mode, clicking on a feature button will display only that feature type (Notes, Tagged Values, etc).
- All In this mode, all the elements features are displayed on the page, one after the other. Clicking a feature button will scroll down (if necessary) so that the section for that feature is visible.

Buttons are available for displaying these features:

- Notes: the notes of the current object
- Location: information relating to the current object's parent, any diagrams that the element appears on, and a list of instances that the element is a classifier of
- Tagged Values: a list of defined Tagged Values for the current object
- Relationships: a list of incoming and outgoing connections for the current object; clicking on the connector type will display the connector's properties
- Attributes: a list of all defined attributes for the current object
- Operations: a list of all defined operations for the current object
- Files: a list of Associated Files which have been defined for the current object
- Requirements: a list of all defined internal requirements (responsibilities) for the current object
- Constraints: a list of all defined constraints for the current

object

- Scenarios: a list of all defined scenarios for the current object
- Tests: a list of all defined tests for the current object; selecting a test from the list will display more information if you have the required permissions and the model has been configured correctly, clicking or tapping the pencil icon will allow you to edit the details of the selected test
- Resources: a list of all defined Resource Allocations for the current object; selecting a resource from the list will display more information - if you have the required permissions and the model has been configured correctly, clicking or tapping the 'Pencil' icon will allow you to edit the details of the selected resource allocation
- Features: a list of all defined 'feature' maintenance items for the current object; selecting a change from the list will display more information
- Changes: a list of all defined 'change' maintenance items for the current object; selecting a change from the list will display more information
- Documents: a list of all defined 'document' maintenance items for the current object; selecting a document from the list will display more information
- Defects: a list of all defined 'defect' maintenance items for the current object; selecting a defect from the list will display more information
- Issues: a list of all defined 'issue' maintenance items for the current object; selecting an issue from the list will

display more information

- Tasks: a list of all defined 'task' maintenance items for the current object; selecting a task from the list will display more information
- Events: a list of all defined events for the current object; selecting an event from the list will display more information
- Decisions: a list of all defined decisions for the current object; selecting a decision from the list will display more information
- Effort: a list of all defined effort items for the current object
- Risks: a list of all defined risks for the current object
- Metrics: a list of all defined metrics for the current object
- Discussions: a list of all formal review discussions and informal discussions on the element; if the current model has been configured to allow it, you can contribute to discussions on the current object for further information on these facilities, see the *Reviews in WebEA* and *Discussions in WebEA* Help topics

## **Opening Associated Files from WebEA**

If an Element has Associated Files defined then these file paths will be listed as hyperlinks in the 'Files' section. For security reasons, web browsers typically will not allow

local files to be opened directly via a hyperlink on a web page. In some cases the browser can be configured to allow this.


For example, for FireFox, see:

http://kb.mozillazine.org/Firefox\_:\_Issues\_:\_Links\_to\_Loca l\_Pages\_Don%27t\_Work

At the end of each file path is a Copy to Clipboard icon. This can be used to easily copy/paste the path (e.g. into Windows Explorer) and open the file.

#### WebEA - Browser

The WebEA 'Browser' displays a context sensitive view of a Package or Element and its children. It can be enabled via the 'Browser' option in the main 'Hamburger' menu which is located in the upper right corner of WebEA. When enabled, the Browser displays on the left side of WebEA's Main View.



If the currently selected object is a Package, or an element with children, then the Browser displays the object at the parent level, and the children below it.

If the currently selected object is a diagram or an element without children, then the Browser displays the object's parent, then its children (which include the current object and its siblings)

If the currently selected object is not the root, then the second item in the Browser is an up arrow, allowing

navigation to the next level up. Selecting an object in the 'Browser' panel will cause WebEA to navigate to that object.

#### **Favorites in the WebEA Browser**

WebEA Model connections can be configured to treat the user's 'Favorites' as the Home page (via the favorites\_as\_home configuration option). See the Refine Browser Content and How to configure WebEA models topics for details.

In this case the Browser behavior is changed to help focus on Favorites packages.

- When initially opening the Model, the Browser will display the current user's Favorites.
- Selecting a Package from the Favorites list will update the Browser to display the contents of the Package. To help keep the focus on the contents of the Favorites, the Browser will not include the Up arrow to go to the package's parent. When navigating down through nested packages you can simply use the Web Browser's 'Back' function to return to the previous page (i.e. the parent).
- You can return to the list of Favorites using WebEA's Home button.

# Favorites My Favorites Functional Requirements In Progress Use Case Administrators Getting Started

#### **Notes**

- The Browser panel is only visible if the screen is greater than 800 pixels wide.
- The Browser acts as an alternative to viewing the object list in WebEA's Main View. When the Browser is enabled the Main View Object List is not accessible.

# **WebEA - Properties View**

The WebEA 'Properties View' displays a context sensitive view of a diagram, package or element's properties. It can be enabled via the 'Properties' option in the main 'Hamburger' menu which is located in the upper right corner of WebEA. When enabled, the Properties View displays on the right side of WebEA's Main View.

The 'Properties View' displays the principle property details of the object currently selected in the main content area, these being the name, type, notes, creation and modification dates, version and location details.

By default, the 'Properties View' will also display the element Notes; however, you can select a different feature to display in this location by using the 'Select Feature' Hamburger menu (to the right of the 'Notes' heading).



#### Proposed

Version 1.0 Phase 1.0 2005-03-07 21:47:21 created by Frank McIver 2005-12-20 15:29:34 last modified



#### Location



Manage Users

맥 Traceability Diagram

□ View Account details

#### Notes



The Client's goal is to view the details of past bookstore transactions, if any.

The main purpose of the 'Properties View' is to allow users to quickly and easily see details of elements without navigating away from a diagram.

The 'Properties View' is also displayed while viewing the Full Properties of an object in WebEA's Main View. This allows you to access one feature of the element (such as Notes) in the 'Properties View' while also accessing another (such as Discussions) in the Main View.

## **Navigation Buttons**

When appropriate, the Properties View will also include navigation buttons that allow you to either display the object's full properties in WebEA's Main View, or view the element/Package's children.

Button	Description
Full Properties	This can be used to navigate to the object, showing its full properties in the Main View.
View Contents	If you have selected a Package or an Element with children, and the Browser is not currently enabled then an additional icon is displayed. This allows you to view the object's children in the object list/icon view.

## **Navigation Element Behavior**

Within Enterprise Architect it is possible to define a number of different element types that make it easier to navigate your model (Hyperlinks, Navigation Cells, etc). By default selecting one of these objects in WebEA will navigate directly to the target (instead of displaying its properties in the Properties View).

If necessary, you can change this behavior using the

'Configure WebEA models - via Text Editor' configuration option.

#### **Notes**

- The Properties View is only visible if the screen is greater than 800 pixels wide.
- Selecting elements on a diagram while the Properties View is shown will not effect the browsing history.

# **Object Creation in WebEA**

Depending on how the current model has been configured in the WebEA configuration file and your security access to the model, you might have the ability to create a range of objects in the model through WebEA. These objects include: Packages and diagrams; elements such as Use Cases, Requirements, Components, Changes and Issues; and features of elements such as Tests, Decisions, Defects and Events. You can therefore define additional scope or problems that have arisen, directly in the model, with precision and in detail, adding to the accuracy and quality of the solution that the model represents.

The Project Manager responsible for the model should guide you in how to create objects and in the purpose of you doing so.

In addition to adding new elements you might also be able to edit the Notes of any object regardless of type, and the details of element Tests and Resource Allocations for any element in the model, whether you have created it or not. See the *Edit Objects* Help topic.

## **Adding Objects**


You can quickly establish if you have the ability to create objects in WebEA by checking the <u>WebEA - Browser</u> or the <u>Main View - Object List</u>.

If you are able to create objects then the final item in the list will be a '<new>' button.

#### For example:



Click on this button to display the 'Add Object' page.



	• Package
	• Diagram
	• Review
	• Actor
	• Change
	• Component
	• Feature
	• Issue
	• Node
	Requirement
	• Task
	• Use Case
Technology	This is an optional field that is only visible when 'Diagram' is selected as the element type. It allows the selection of a Technology that provides an additional set of diagram types.
Diagram Type	This is an optional field that is only visible when 'Diagram' is selected as the element type. Click on the drop-down arrow and select the type of diagram to create.
Name	Type in an appropriate name for the object, preferably giving some indication

	of its purpose or function.
Notes	Type in a more detailed description of the element, such as why you are creating it and what other elements it might be associated with.
	You can format this text using the facilities provided in the Notes toolbar. These are:
	• Bold
	<ul><li>Italic</li><li>Underline</li></ul>
	<ul> <li>Numbered list</li> </ul>
	Bulleted list
	<ul> <li>Superscript text</li> </ul>
	<ul> <li>Subscript text</li> </ul>
	Set color of selected text
Add	Click on this button to add the new object to the Package in which you are creating it. This message displays:  Object added
	Either:
	• Work through the fields again, defining another new object in this Package, or
	• Click on the licon and select the Package line to return to the 'Hierarchy'

view of the Package, now containing
the new element

## **Adding Element Features**

You can, again, quickly establish if you have the ability to create element features in WebEA, by displaying the Properties of an element in WebEA's Main View - Object Properties; if the icon displays in the right corner of the element name/notes panel, you can add element features.

Display the Properties of the element to which you want to add a feature, and click on the icon. A menu displays offering options to add to the element each feature that you have the access permissions to create. These features might include:

- Other Objects
- Tests
- Resources
- Features
- Changes
- Documents
- Defects
- Issues
- · Tasks, or

#### Risks

Select the appropriate option; a dialog displays in which you complete the fields to define the feature for the element. Each type of feature has a different dialog; refer to these topics for the details appropriate to each dialog.

- Add Test Records
- Add Resource Records
- Add a Feature
- Add Change Requests
- Add a Document
- Add a Defect
- Add an Issue Notification
- Add a Task
- Add a Risk

#### **Notes**


- As suggested in the *Adding Element Features* section, you can also add an object to a Package or to another object within the Main View's Object Properties page; click on the 'Hamburger' icon and select the 'Add Object' option, and complete the 'Add Object' page as described at the start of this topic
- When using the Security 'Lock to Edit' mode, features and child elements can only be created if the element has been locked by the current user (via Enterprise Architect).

#### **Add Test Records**

Within an element, you can create a record for each Test that you want to add to the element.

#### Add a Test

Display the Properties of the element to which you want to add the Test record, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add Test' option. The 'Add Test to <element name>' dialog displays.



Mandatory fields on the dialog are indicated by a red asterisk (\*).

Complete the fields as directed here.

Field	Action
Test name	Type an appropriate and meaningful name for the Test.
	Click on the drop-down arrow and select

Class Type	the appropriate test group; that is:  Unit  Integration  System  Acceptance  Scenario, or  Inspection
Type	Click on the drop-down arrow and select the appropriate test type; that is:  Load Regression or Standard
Status	<ul> <li>Click on the drop-down arrow and select the appropriate test status; that is:</li> <li>Not Run (the most likely value for a new record from you)</li> <li>Pass</li> <li>Fail</li> <li>Deferred or</li> <li>Cancelled</li> </ul>
Run by	If the test has been run, click on the drop-down arrow and select the name of the person who ran it.

Last Run	If the test has been run, click on the calendar icon and select the date on which the test was most recently run.
Checked by	If the test has been run, click on the drop-down arrow and select the name of the person who checked the test execution and results.
Description	Type in a description of the test, what it is intended to show and why it is necessary. You can format this text using the facilities provided in the Notes toolbar. These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text  Subscript text  Set color of selected text
Input	Type a description of what actions or parameters are required as input to this test.  You can format this text using the facilities provided in the Notes toolbar.


Acceptance Criteria	Type a description of what criteria must be satisfied to indicate that the test has passed.  You can format this text using the facilities provided in the Notes toolbar.
Results	Type a description of the expected and/or actual results of this test.  You can format this text using the facilities provided in the Notes toolbar.
Add	Click on this button to submit the details and create the Test record on the selected element.  This message is displayed:  Test <name> was successfully added to <element name="">.  Either:  Work through the fields again, defining another new Test on this element, or  Click on the browser's Back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Testing' panel</element></name>

## **Add Resource Records**

Within an element, you can create a record for each Resource that you want to add to the element.

## Add a Resource

Display the Properties of the element to which you want to add the Resource record, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add resource' option. The 'Add resource allocation to <element name>' dialog displays.



Mandatory fields on the dialog are indicated by a red asterisk (\*).

Field	Action
Resource	Click on the drop-down arrow and select the name of the person to be allocated as the resource.
Role	Click on the drop-down arrow and select the role of the resource in this work; for example:  • Application Analyst  • Business Analyst  • C++ Programmer  • Project Manager
Start date	Click on the calendar icon and select the date on which the resource is expected to start the assigned work.
End date	Click on the calendar icon and select the date on which the resource is expected to complete the assigned work.
% Complete	Click on the up and down arrows to change the field value to the percentage completion of work that the resource has achieved.

## Description

Type in a description of the resource allocation - what the work is, why this (kind of) resource is required to do it, and any criteria that must be satisfied.

You can format this text using the facilities provided in the Notes toolbar. These are:

- . Bold
- Italic
- Underline
- Numbered list
- Bulleted list
- Superscript text
- Subscript text
- Set color of selected text

#### Add

Click on this button to submit the details and create the Resource Allocation record on the selected element.

This message is displayed:

Resource allocation for <name> was successfully added to <element name>.

- Work through the fields again, defining another new Resource Allocation on this element, or
- Click on the browser's back button to


9

## Add a Feature

Within an element, you can create a record for each 'feature' maintenance item that you want to add to the element.

## Add a Feature

Display the Properties of the element to which you want to add the feature, and click on the icon. Select the 'Add feature' option. The 'Add feature to <element name>' dialog displays.



Field	Action
Name	Type an appropriate and meaningful name for the feature.
Status	Click on the drop-down arrow and select the appropriate record status; that is:  New Verified, or Complete
Priority	Click on the drop-down arrow and select the appropriate priority value; that is:  High Medium, or Low
Requested by	Click on the drop-down arrow and select the name of the person requesting the feature.
Requested on	Click on the calendar icon and select the date on which the record was made.
Completed	If the feature has been completed/added,

by	click on the drop-down arrow and select the name of the person who complete it.
Complete on	Click on the calendar icon and select the date on which the feature was completed/added.
Version	Type in a version number or letter to indicate any evolution of the same feature. Generally, '1.0' indicates the first instance of a feature.
Description	Type in a description of the feature. You can format this text using the facilities provided in the Notes toolbar. These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text  Subscript text  Set color of selected text
History	Over time, enter any notes on the actions concerning this feature; you can format this text using the facilities provided in the Notes toolbar.

#### Add

Click on this button to submit the details and create the feature record on the selected element.

This message is displayed:

Feature <name> was successfully added to <element name>.


- Work through the fields again, defining another feature on this element, or
- Click on the browser's back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Features' panel

# **Add Change Requests**

Within an element, you can create a record for each Change Request that you want to add to the element.

## Add a Change Request

Display the Properties of the element to which you want to add the Change Request, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add change' option. The 'Add change to <element name>' dialog displays.



Field	Action
Name	Type an appropriate and meaningful name for the requested change.
Status	Click on the drop-down arrow and select the appropriate request status; that is:  New Verified, or Complete
Priority	Click on the drop-down arrow and select the appropriate priority value; that is:  High Medium, or Low
Requested by	Click on the drop-down arrow and select the name of the person requesting the change.
Requested on	Click on the calendar icon and select the date on which the request was made.

Completed	If the change has been completed, click on the drop-down arrow and select the name of the person who completed it.
Completed on	Click on the calendar icon and select the date on which the requested change was completed.
Version	Type in a version number or letter to indicate any evolution of the same change. Generally, '1.0' indicates the first instance of a change.
Description	Type in a description of the change, what it is intended to be and why it is necessary.  You can format this text using the facilities provided in the Notes toolbar. These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text  Subscript text  Set color of selected text

# History If there is any background to this change, such as previous versions, document them here (you might copy the 'Description' from the last version or iteration of this change, for example). It is recommended that you include a date

You can format this text using the facilities provided in the Notes toolbar.

stamp and user initials in the entry.

#### Add

Click on this button to submit the details and create the change request on the selected element.

This message is displayed:

Change <name> was successfully added to <element name>.


- Work through the fields again, defining another new change request on this element, or
- Click on the browser's back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Changes' panel

## Add a Document

Within an element, you can create a record for each 'document' maintenance item that you want to add to the element. A document could be used to record supporting documentation such as Help, release notes or user comments.

## Add a Document

Display the Properties of the element to which you want to add the document, and click on the icon. Select the 'Add document' option. The 'Add document to <element name>' dialog displays.



Field	Action
Name	Type an appropriate and meaningful name for the document.
Status	Click on the drop-down arrow and select the appropriate record status; that is:  New

	• Verified, or
	• Complete
Priority	Click on the drop-down arrow and select the appropriate priority value; that is:  High Medium, or Low
Requested by	Click on the drop-down arrow and select the name of the person who requested the document.
Requested on	Click on the calendar icon and select the date on which the record was made.
Completed by	If the document is complete, click on the drop-down arrow and select the name of the person who completed it.
Complete on	Click on the calendar icon and select the date on which the document was completed.
Version	Type in a version number or letter to indicate any evolution of the same document. Generally, '1.0' indicates the first instance of a document.

Description	Type in the details/contents of the document. You can format this text using the facilities provided in the Notes toolbar. These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text  Subscript text  Set color of selected text
History	Over time, enter any notes on the actions concerning this document; you can format this text using the facilities provided in the Notes toolbar.
Add	Click on this button to submit the details and create the document record on the selected element.  This message is displayed:  Document <name> was successfully added to <element name="">.  Either:  Work through the fields again, defining</element></name>


- another document on this element, or
- Click on the browser's back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Documents' panel

## Add a Defect

Within an element, you can create a record for each defect that you want to add to the element.

## Add a Defect Record

Display the Properties of the element to which you want to add the defect record, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add defect' option. The 'Add defect to <element name>' dialog displays.



Field	Action
Name	Type an appropriate and meaningful name for the defect.
Status	Click on the drop-down arrow and select the appropriate record status; that is:  New Verified, or Complete
Priority	Click on the drop-down arrow and select the appropriate priority value; that is:  High Medium, or Low
Reported by	Click on the drop-down arrow and select the name of the person reporting the defect.
Reported on	Click on the calendar icon and select the date on which the record was made.

Resolved by	If the defect has been resolved, click on the drop-down arrow and select the name of the person who resolved it.
Resolved on	Click on the calendar icon and select the date on which the recorded defect was fixed.
Version	Type in a version number or letter to indicate any evolution of the same defect. Generally, '1.0' indicates the first instance of a defect.
Description	Type in a description of the defect, what it is, what the solution might be, and why it is a problem.  You can format this text using the facilities provided in the Notes toolbar.  These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text  Subscript text  Set color of selected text

#### History

If there is any background to this defect, such as previous occurrences, document them here (you might copy the 'Description' from the last version or iteration of this defect record, for example). It is recommended that you include a date stamp and user initials in the entry.

You can format this text using the facilities provided in the Notes toolbar.

#### Add

Click on this button to submit the details and create the defect record on the selected element.

This message is displayed:

Defect <name> was successfully added to <element name>.


- Work through the fields again, defining another new defect record on this element, or
- Click on the browser's back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Defects' panel

## Add an Issue Notification

Within an element, you can create a record for each issue notification that you want to add to the element.

#### Add an Issue

Display the Properties of the element to which you want to add the issue notification, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add issue' option. The 'Add issue to <element name>' dialog displays.



Field	Action
Name	Type an appropriate and meaningful name for the reported issue.
Status	Click on the drop-down arrow and select the appropriate issue status; that is:

	• New
	• Verified, or
	• Complete
Priority	Defaults to 'High'. If necessary, click on the drop-down arrow and select the appropriate priority value; that is:  • Medium, or  • Low
Raised by	Defaults to the first name in the list of project users. If necessary, click on the drop-down arrow and select the name of the person raising the issue.
Raised on	Defaults to today's date. If necessary, click on the calendar icon and select the actual date on which the issue was raised.
Completed by	If the issue has been resolved, click on the drop-down arrow and select the name of the person who resolved it.
Completed on	Click on the calendar icon and select the date on which the issue was resolved.
Version	Type in a version number or letter to indicate any evolution of the same issue.

	Defaults to '1.0', indicating the first instance of an issue.
Description	Type in a description of the issue, what it is, what the solution might be, and why it is a problem.  You can format this text using the facilities provided in the Notes toolbar.  These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text  Subscript text  Set color of selected text
History	If there is any background to this issue, such as previous occurrences, document them here (you might copy the 'Description' from the last version or iteration of this issue, for example). It is recommended that you include a date stamp and user initials in the entry.  You can format this text using the facilities provided in the Notes toolbar.

#### Add

Click on this button to submit the details and create the issue report on the selected element.

This message is displayed:

Issue <name> was successfully added to <element name>.


- Work through the fields again, defining another new issue on this element, or
- Click on the browser's back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Issues' panel

## Add a Task

Within an element, you can create a record for each task that you want to add to the element.

## Add a Task Record

Display the Properties of the element to which you want to add the task record, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add task' option. The 'Add task to <element name>' dialog displays.



Field	Action
Name	Type an appropriate and meaningful name for the new task.
Status	Click on the drop-down arrow and select the appropriate task status; that is:  New Verified, or Complete
Priority	Defaults to 'High'. If necessary, click on the drop-down arrow and select the appropriate priority value; that is:  • Medium, or  • Low
Requested by	Click on the drop-down arrow and select the name of the person requesting the task. This defaults to the name selected for the previous record.
Reported on	Defaults to today's date. If necessary, click on the calendar icon and select the

	correct date on which the request was made.
Completed	If the task has been completed, click on the drop-down arrow and select the name of the person who completed it.
Completed	Click on the calendar icon and select the date on which the task was completed.
Version	Type in a version number or letter to indicate any evolution of the same task. Defaults to '1.0', indicating the first instance of a task.
Description	Type in a description of the task, what it is, what the objective might be, and why it is a required.  You can format this text using the facilities provided in the Notes toolbar.  These are:  Bold  Italic  Underline  Numbered list  Bulleted list  Superscript text

	Set color of selected text
History	If there is any background to this task, such as previous occurences, document them here (you might copy the 'Description' from the last version or iteration of this task, for example). It is recommended that you include a date stamp and user initials in the entry.  You can format this text using the facilities provided in the Notes toolbar.
Add	Click on this button to submit the details and create the task record on the selected element.  This message is displayed:  Task <name> was successfully added to <element name="">.  Either:  Work through the fields again, defining another new task request on this element, or  Click on the browser's Back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Tasks' panel</element></name>


# Add a Risk

A Risk is a condition that could cause the disruption, loss or compromise of a system. It can refer to either technical or business risks.

Within an element, you can create a record for each risk that you want to record against the element.

#### Add a Risk Record

Display the Properties of the element to which you want to add the risk record, and click on the icon. A menu displays offering options to add various features to the element. Select the 'Add risk' option. The 'Add risk to <element name>' dialog displays.



Mandatory fields on the dialog are indicated by a red asterisk (\*).

Complete the fields as directed here.

Field	Action
Name	Type an appropriate and meaningful name for the new risk.
Type	Type in the risk type.
Weight	Defaults to 1. Click on the up and down arrows to set a different weighting on the risk. There is no limit to the value that you can set, but within Enterprise Architect the usual value is a small number between, say, 1.0 (normal) and 5.0 (heavily weighted).
Description	Type in a description of the risk, what it is and what the mitigation might be. You can format this text using the facilities provided in the Notes toolbar. These are: Bold Italic Underline Numbered list Bulleted list

	<ul><li>Superscript text</li><li>Subscript text</li><li>Set color of selected text</li></ul>
Add	Click on this button to submit the details and create the risk record on the selected element.  This message is displayed: Risk <name> was successfully added to <element name="">.  Either:  Work through the fields again, defining another new risk on this element, or  Click on the browser's back button to return to the 'Properties' view of the element, which will be refreshed to show the new record in the 'Risks' panel</element></name>

# **Edit Objects**

Within any model in which you have the security permissions to create elements, you can also edit the Notes, Resource Allocation and Testing details of any object in which they occur.


Firstly, display the property (either the Notes, or a specific Test/Resource item) which you want to edit in WebEA's Main View - Object Properties.

On the right of the item field for these three properties you will see a / icon, which indicates that you have the ability to edit that property.

#### **Edit Notes**

To edit the notes of an object, click on the / icon for the field. The 'Edit note for <object type>' page displays.

#### 



You can add, delete and change text, and use the formatting tools in the Notes toolbar; that is, for a selected text string, add:

- · Bold
- Italic
- Underline
- Numbered List
- Bulleted List
- Superscript
- Subscript
- Text color

The final two toolbar buttons allow you to add or remove a hyperlink from some selected text.

To add a hyperlink, select the text in the editor, then click on the Add Hyperlink button. Enter the URL for the hyperlink, then click Apply.

To remove a hyperlink, select the text, then click on the Remove Hyperlink button.

Note, this function supports hyperlinks to Web URLs only.

You can also right-click on the selected text and select options from the browser context menu to:

- Undo the last change
- Move (cut) the text string into the buffer for pasting
- Copy the text string into the buffer for pasting
- Paste text from the buffer into the 'Notes' field
- Delete the selected text
- Select all the text in the 'Notes' field
- Search for the selected text string on the internet
- Turn spell-checking on and off (if on, possibly misspelt text is underlined in red)
- Add a different language dictionary to check spelling against (this would probably have been done already for your web browser)


When you have finished editing the text, click on the Save button. A confirmation message briefly displays and you are returned to the object 'Properties' view.

#### **Edit Tests**

The tests assigned to an element support a range of situations including user acceptance and scenario. You could be asked to define or perform tests on parts of a model of relevance to you as a customer or user, or you might want to add information obtained from other people you have asked to perform an evaluation. Therefore, you might need to edit test records to update them with your information.

To edit a test record, display the appropriate element in WebEA's Main View, click the feature button to display 'Tests' then select the appropriate test from the list.

Once the test is displayed click on the / icon. The 'Edit Test for <element name>' page displays.



# **Edit Test for <<element name>> page**

Mandatory fields on the dialog are indicated by a red asterisk (\*).

Complete the fields as directed here.

Field	Action
Test name	If necessary, type a new name for the Test.

Class type	In necessary, click on the drop-down arrow and select a different test group for the test; that is:  Unit Integration System Acceptance Scenario, or Inspection
Type	If necessary, click on the drop-down arrow and select a new test type; that is:  Load Regression or Standard
Status	If necessary, click on the drop-down arrow and select a new test status; that is:  Not Run  Pass  Fail  Deferred or  Cancelled
Run by	If the test has been run, click on the drop-down arrow and select the name of the person who ran it.

Last Run	If the test has been run, click on the calendar icon and select the date on which the test was most recently run.
Checked by	If the test has been run, click on the drop-down arrow and select the name of the person who checked the test execution and results.
Description	Type in a description of the test, what it was intended to show and - if the test has been run - what the test situation and results were.  You can format this text using the facilities provided in the Notes toolbar, as described in the <i>Edit Notes</i> section.
Input	Type a description of what actions or parameters are or were required as input to this test.  You can format this text using the facilities provided in the Notes toolbar, as described in the <i>Edit Notes</i> section.
Acceptance Criteria	Type a description of what criteria must be or were satisfied to indicate that the test has passed.  You can format this text using the


	facilities provided in the Notes toolbar.
Results	Type a description of the expected and/or actual results of this test.
	You can format this text using the facilities provided in the Notes toolbar.
Save	Click on this button to submit the details and update the Test record on the selected element.
	A confirmation message briefly displays and you are returned to the object 'Properties' view

#### **Edit Resource Allocation**

The resources allocated to an element can include reviewers in various roles, and you might be allocated as a resource yourself. Alternatively, you could have allocated another person as a reviewer. Therefore, you might need to edit a resource allocation to record either your own progress in a review, or the progress of the resource you have allocated.

To edit the resource allocation, display the appropriate element in WebEA's Main View, click the feature button to display 'Resources' then select the appropriate test from the list.

Once the resource is displayed click on the / icon. The 'Edit resource allocation for <element name>' page displays.



# Edit Resource Allocation for <element name> page

Notice that this page has a few more fields than the initial 'Add resource allocation ...' page.

Mandatory fields on the dialog are indicated by a red asterisk (\*).

Complete the fields as directed here.

Field
-------

Resource	If necessary, click on the drop-down arrow and select the name of a different person to be allocated as the resource.
Role	If necessary, click on the drop-down arrow and select a different role for the resource in this work.
Start Date	If necessary, click on the calendar icon and select a different date on which the resource started or is expected to start the assigned work.
End Date	If necessary, click on the calendar icon and select a different date on which the resource completed or is expected to complete the assigned work.
% Complete	Click on the up and down arrows to change the field value to the percentage completion of work that the resource has achieved.
Expected	Type in the number of whole time units the task is expected to take. The value must be an integer; you cannot record part units.  The unit of time you use will be

	identified by the Project Manager, and depends on the granularity of the work being recorded. Most tasks are completed in a number of hours or a number of days; use the smallest practical unit that you can record as a whole number, and use the same units for the expected, allocated and actual times.
Allocated	Type in the number of whole time units the task can be spread over. For example, you might expect the task to take 2 days of work performed at any point over a period of 5 days.
Actual	If the task is 100% complete, type in the number of whole time units it actually took.
Description	If necessary, edit the description of the resource allocation, perhaps to explain the changes you have made to earlier fields.
	You can format this text using the facilities provided in the Notes toolbar, as explained in the <i>Edit Notes</i> section.
	Before changing the text, you might want to copy it to paste into the 'History' field for editing there.


History	Optionally, paste or type in an explanation of what has previously taken place with this Resource Allocation. You can also format this text, using the facilities in the Notes toolbar.
Save	Click on this button to submit the details and update the Resource Allocation record on the selected element.  A confirmation message briefly displays and you are returned to the object 'Properties' view.

# **Reviews in WebEA**


Review elements are a convenient way for groups of users to collaboratively discuss one or more model objects and capture those discussions as a formal review. A Review element is a custom element that captures all discussions that you participate in over a period of time. That period begins when you select to 'join' the review, and ends either when you select to leave the review, or when you log out of the current model. You can also return to the review in a subsequent work session and your continuing discussions are also captured. The Review element would typically have a start and end date set to define the duration of the review.

When a Review element is created, a child diagram is also created, automatically. Both Enterprise Architect and WebEA consider any element added to this diagram as requiring comment during the Review. When the properties of the Review element are loaded in WebEA the 'Objects in Review' section will contain a list of all elements that have already been commented on or have been added to the Review diagram. This list provides a convenient way to quickly navigate to each element in the Review.

When the properties of a Review element are loaded in WebEA's Main View, the default feature which is displayed is a Summary of the Review. This includes the status, start and end dates, number of elements discussed and yet to be discussed, and a break down of review topics based on priority and status, as illustrated here:



The Summary is followed by 'Review Diagrams' and 'Objects in Review' sections.



The 'Review Diagrams' section provides links to the diagram which are associated with the review (I.e. those


which are children of the Review Element).

The 'Objects in Review' section displays a list of elements to be discussed during the review. Elements that have not yet been discussed are presented first in the list, followed by elements that have been commented on, showing each review topic. The name of the object acts as a hyperlink to that object.

# **Locating Reviews**


There are a number of ways in which to locate existing Review elements to join, or to switch to your active review (the review that you have already joined).

To check on recent Review elements available in the model, click on the 'Search' icon in the WebEA header and select the 'Reviews' option. This conducts a search for recent Review elements and lists them in the 'Search Results' view, with the most recently changed element at the top of the list.



You can click on the name of a Review in the list to load the details of the selected Review element, and then join or leave the Review as appropriate.

The name of your active Review is displayed in the WebEA's Status bar, and you can click on the name (in the Status bar) to load the details of the active Review element.




#### Join a Review

While the property details of a Review element are loaded, the Join Review button will be enabled.



Clicking on this button will join you to the review and link your discussions to the Review element. The display will automatically be adjusted to the change of state. These changes include:

• The addition of the joined Review element's name to the status bar



- The 'Review' section filtering elements to the current Review element only
- The 'Discussion' section's update/add actions being disabled

• The Join Review button being disabled, and the Leave Review button being enabled


The Join Review button might be disabled, for these reasons:

- You are already joined to a review on a different Review element
- The loaded Review is closed

The Join Review button and Leave Review button are only visible on Review elements when the 'participate\_in\_review' configuration option is set to true for the current model. See the *How to configure WebEA models* Help topic for more information.

# Add topics to a Review

When you have opened and read through the contents of a Review element, you can add your own review topics or respond to existing points. To do this you click on the name of the object you want to comment on, then select the 'Discussions' feature button.



Note, whilst you are joined to a review - the contents of the panel are filtered to show only the review comments for that review.

#### Add a Review Topic

To create a review topic on a new point, simply type into the 'Create Review Topic' field. When you have finished typing

your message, submit it by clicking on this button:

Note: WebEA does not support editing (or deleting) review comments, therefore you should take care to type messages in clearly the first time, and double check before submitting.

Depending on how the WebEA model is configured, you

might connect to it using your personal user ID, or as a single generic User that is shared by multiple people. In the second case, Sparx Systems recommends that each user identifies themselves in each message, either at the beginning or at the end.

Whilst you are adding comments to a review, at any point you can return to a posted topic and add or change its status and priority. To the right of the review topic text are two icons. The first is the 'Status' icon, and the second is the 'Priority' icon. The appearance of the icons depends on the current setting for status and priority. To set a status or priority, simply click on the appropriate icon and select from the listed options. These are:

- Status
  - Open
  - Awaiting Review
  - Closed
- Priority
  - III High
  - II Medium
  - I Low
  - <none>

#### Add a reply to a comment

If you want to respond to either a review topic or a reply to that topic, click or tap on the appropriate message. A blank field and button underneath the conversation thread will appear; type in your message and click or tap on this button:



Your reply is added to the end of the thread.

Note: Currently the review threads are only read from the model when the page is loaded, which means if other users make additional comments they will not be displayed until the page is reloaded or refreshed.

#### Review another element

Click on the name of the Review element in the 'Reviews' panel or in the page footer, to display the Properties view for that review element. Select another element in the review from the list.

#### Leave the current Review

When you have finished contributing to the review, you can either return to the Review element Properties view and click on the Leave Review button, or log out of the current model.



The Leave Review button will only be enabled when the details of the currently joined Review element are loaded.

# **Creating a Review**

Typically, only a Project Manager will create Review elements in Enterprise Architect, notifying the relevant users of their location so that each user can join and leave the review(s) as necessary.

However, a WebEA user might create a Review element as a direction to the Project Manager to set up. In this case you create the Review element by clicking on the 'New' icon in the Package hierarchy view, selecting 'Review' as the element type. The procedure is as described in the *Add Elements and Features in WebEA* Help topic.

You require specific access permissions to create a Review element; those permissions are totally separate from the permission to join a review.

# **Discussions in WebEA**

Enterprise Architect has a Discussion facility through which users can post short messages to have informal discussions with other users on a specific element or Package. As a WebEA user, if the model has been configured to allow Discussions to be viewed and added, you can also read and participate in these Discussions. The facility is very useful in informal reviews, as you can comment or respond immediately on a specific point as you come across it, without having to collate a list of comments and compose a relatively long document or email, or schedule a telephone call.

To access Discussions, when viewing the properties of an object in WebEA's main view, select the 'Discussions' feature button.

Note that if you are joined to a formal review, you can read existing Discussion points but you cannot respond to them or add new topics.

The input area shows as a blank field and a 'Discussion' button to save the entered text; if there has already been some discussion on the element, the comments of each Discussion display above the input field.


# Discussions Discussions Can we clarify - is the product code the external ISB number or an internal reference? 2017-05-16 11:58:46 AM roy chester Create new Discussion Create new Discussion

There are two types of discussion messages, an initial message (usually called a Discussion) and replies. Replies are responses to an initial message, and are displayed as child items.

#### **Avatars**

In Enterprise Architect there is an application option for the current users that controls if avatars of security users are displayed with each Discussion item. In WebEA this option is defined for a model in the configuration file; see the option *use\_avatars*.

When a model has been configured to 'use avatars' and the model has security enabled, then instead of displaying generic blue speech bubbles the author's avatar is displayed, as shown here:



# Starting a discussion

To start a discussion on a new point, simply start typing in

the blank field. If you want to have separate paragraphs, press the Enter key to start each new line.

When you have finished typing your message, submit it by

clicking on this button:



Note: WebEA does not support editing (or deleting) discussions, therefore you should take care to type messages in clearly the first time, and double check before submitting.

Depending on how the WebEA model is configured, you might connect to it using your personal user ID, or as a single generic User that is shared by multiple people ('Web User' in the first illustration). In the second case, Sparx Systems recommends that each user identifies themselves in each message, either at the beginning or at the end.

# Replying to a discussion

If you are reading an existing discussion and want to respond to either the opening point or a reply to that point, click or tap on the appropriate message. A blank field and button underneath the conversation thread will display; type in your message and click or tap on this button:

Your reply is added to the end of the thread.

Note: Currently the discussion threads are only read from the model when the page is loaded, which means if other users make additional comments they will not be displayed until the page is reloaded or refreshed.

# **Status and Priority**

If you are adding comments to a discussion, at any point you can return to a posted topic or reply and add or change its status and priority.

To the right of the discussion text are two icons. The first is the 'Status' icon, and the second is the 'Priority' icon. The appearance of the icons depends on the current setting for status and priority. To set a Status or Priority, simply click on the appropriate icon and select from the listed options. These are:

- Status
  - Open
  - Awaiting Review
  - Closed
- Priority
  - III High
  - II Medium
  - I Low
  - <none>

#### **Notes**

· As a WebEA user you cannot delete discussions or

replies; however they can be deleted using of Enterprise Architect

# Create and check Watch Lists


The Watch List facility in WebEA helps you to quickly identify recent activity in the model. Each user can tailor their Watch List to monitor activity in any of a wide range of objects and features with various characteristics. Whenever the Watch List Summary is generated, all object types of interested are checked for recent activity and a count of matched objects displayed. All matched object counts can be clicked on to display the list of objects that match the particular activity type.

Note: Each model has a default set of activity types that have been enabled in the WebEA configuration file; each user can override the model defaults and save their customized settings.


# **Watch Lists Summary**

You can select the Watch List facility by selecting the 'Watchlist' option in the 'Search' menu. This immediately displays the 'Watchlist summary' view that shows:

- Any activity that has recently been detected, for
- All objects and features that are to be monitored If there is no activity for a configured activity type, that activity type is omitted from the 'Watchlist Summary'. The display might look like this:



Every type of object on the report is represented by a line providing the number of objects that match the given criteria. The number of objects is a link which, if you click or tap it, displays a results page listing the specific objects that match the given criteria.




The watch list results page is the same as the custom search results page, in that if you then click or tap on an individual item in the list, the 'Properties' view will be displayed for the selected object. See the *WebEA's Layout* Help topic.

If you have finished checking the 'Watchlist summary', you can click on the OK button to return to the WebEA view you were displaying previously.

Alternatively, you can tailor the Watch List to provide information relevant to you; see *Configure the Watchlist*.

# **Configure the Watchlist**

If you want to customize the activity types monitored in your Watchlist summary, click or tap the configure button located in the Watchlist summary header. The 'Watchlist configuration' page displays.



In the 'Number of days' field, type the number of days that should be considered. This might be the number of days since you last used WebEA, or the number of days in a reporting period that you want to compare with.

For the remaining fields, select the checkbox against all items that you want to monitor and include in your watch list. The complete list is:

Recent:

- Discussions
- Active reviews
- Modified diagrams
- Modified elements
- Resource Allocations:
  - Active
  - Ending today
  - Overdue
- Tests:
  - Recently passed
  - Recently failed
  - Recently deferred
  - Recently not checked
  - Not run
- Changes, Defects, Issues, Tasks and Decisions:
  - Verified
  - Recently requested
  - Recently completed
  - New
  - Incomplete
- Events:
  - Recently requested
  - High Priority
  - Incomplete

The Select All and Deselect All options can be used to select or deselect all checkboxes.

Once you have finished choosing which items to monitor, click or tap on the Save button to save the configuration and redisplay the Watch List summary.

#### Note:

- All watch list options are saved based on current model and User ID for the current browser, and stored as cookies (where possible) so that the options are remembered between sessions
- If your browser does not allow the saving of cookies, then your customized watch list setting will only last as long as the current session

# **Relationship Matrix**

The Matrix facility in WebEA enables you to view the Relationship Matrix generated from any Relationship Matrix profile that has been defined in the model.

The Relationship Matrix is a spreadsheet display of relationships between model elements within a Package, or between elements in two different Packages. It is a convenient and simple tool for reporting and working on all the relationships in a selected structure. The relationships shown can be filtered according to:

- The element type of the source and target elements in each relationship
- The relationship type and direction
- The Package(s) in which the source elements and target elements are held

Those parameters can be defined in a Relationship Matrix profile; to display a matrix in WebEA you select one of the available profiles.

The matrix shows all the relationships of the specified type between source and target elements by:

- Listing the source Package elements down the side of the matrix
- Listing the target Package elements across the top of the matrix, and
- If a relationship exists between a source and target element, displaying an arrow indicating the direction of

the relationship


Clicking on a square containing an arrow displays the Relationship Properties screen for the relationship represented by that arrow. On that screen you can click on the source or target element names and display the Element Properties screen for those elements.

#### **Access**

On the WebEA header, click on the icon and select the 'Matrix' option. The 'Matrix Profiles' page displays.

#### **Matrix Profiles**

The 'Matrix Profiles' page provides a drop-down field that you use to list and select from the matrix profiles defined within Enterprise Architect. You cannot add to or edit these profiles.



When you select a matrix profile, the rest of the fields on the page will be populated with the values defined in the profile. Click on the View Matrix button to load the relationships selected under the profile, in a Relationship Matrix grid.


WebEA is only able to load complete matrix profiles; if an incomplete matrix profile is requested, this error message will be displayed:

This Matrix profile is incomplete. Use EA to save the profile with values in all fields


If this message is displayed, ask the Project Manager to update the Matrix Profile.

#### **Matrix**

This is a sample Relationship Matrix as displayed by WebEA. It is almost identical to what would be displayed in Enterprise Architect.



When you click on a relationship arrow - such as, in the example, the 'Manage Titles' to 'REQ019 - Manage Inventory' arrow - the Relationship Properties screen displays.




#### **Notes**

- A Matrix Profile can also be accessed via a Hyperlink or a Matrix Specification Artifact on a diagram.
- Matrix Profiles which use a Model Search to populate the source or target elements are not supported in WebEA.

# Search the model

WebEA provides a facility that enables you to search through the model for a specific item or group of items that have certain characteristics. This can help you to quickly locate objects of importance, such as elements you have created yourself (if you have the access privileges to do so).

You access the Search facility by clicking on the 'spyglass' icon in the WebEA header and selecting the 'Custom search' option.



# **Search Specification**


Define your search using these options.

Option	Description
Term	Type or paste in the string of characters or digits you want to locate - name, Notes text or the complete object ID. Be aware that for some DBMSs - such as Firebird or Oracle - searches are case-sensitive.
Search for	Select one of these object types to search: Diagrams Elements Packages Discussions, or Reviews If you select 'Discussions', the 'Search in' and 'Term' options are not relevant and so are grayed out and unavailable. The search is for elements having active discussions within the specified time period. Note: the 'Discussions' option is only available in models that have the show_discuss parameter set to 'true' in the WebEA configuration file, and the 'Reviews' option is only available when the participate_in_reviews parameter is set to 'true'.

Search in	<ul> <li>Select from the list of fields to search:</li> <li>Name</li> <li>Name, Alias and Notes (the proper name, an assigned alternative name, and any text written in the object's 'Notes' field)</li> <li>Author (the person who created the object)</li> <li>ID (the GUID of the object, displayed as the last item in the 'Properties' panel when you expand it)</li> </ul>
When	Select the period of time that should be searched. You can select to search for objects modified:  Today  Within the last 3 days  Within the last 7 days  Within the last 14 days  Within the last 30 days  Within the last 12 months  At any time
Run Search	Click or tap this button to execute the search and locate the objects that meet the search criteria.

#### **Search Results**

When you execute the search the results are displayed in the main content area.



The results provide the object name, type, author and last-modified date of each object that matches the search criteria. If you click on an item, the 'Properties' view will be loaded for that object.

# **Troubleshooting WebEA**

If WebEA users experience a problem, an error message will be displayed on the screen. This topic provides a list of common WebEA error messages that could occur. Each entry describes the situation that has occurred and provides guidance on how to correct the error.

# **WebEA Configuration Test**

On initial set up, these steps can be performed to help identify configuration issues:

Ste	Action
p	
1	On the Web Server machine, open a web browser and test access to the WebEA login page.  E.g. http://localhost/webea/login.php  Failing this, check that the Web Server has been set up as described in the WebEA Installation and Configuration topic.
2	On a client machine test access to the WebEA login page.  E.g. http:// <server name="">/webea/login.php  Failing this suggests there is a network/communication issue between the client and</server>

	the web server.
3	Before attempting to access a model via WebEA, confirm you can successfully open the model using Enterprise Architect's 'Connect to Cloud' option. Failing this, refer to the <i>Cloud Server Troubleshooting</i> Help topic.
4	In the webea_config.ini file, add a model connection with the minimum required options, as outlined here. Ensure these match the settings used when connecting via Enterprise Architect. Note, the 'sscs_db_alias' should match the value entered in the 'Model Name' field.
	sscs_protocol = " <protocol>" sscs_server = "<server address="" ip="" name="" or="">" sscs_port = "<port>" sscs_db_alias = "<model name="">" auth_code = "" ;leave this empty</model></port></server></protocol>
	If the Project has Enterprise Architect User Security enabled then also include: login_prompt = "true"  If the Protocol being used is HTTPS then also include:

	sscs_use_ssl = "true"
	If you are using HTTPS with a Self-signed certificate then also include: sscs_enforce_certs = "false"
5	Try accessing the model in WebEA. Failing this, the error returned by the WebEA login screen might help identify the cause of the issue.

# **WebEA Error Messages**

Issue	Comments
Server could not be found	<ul> <li>Server could not be found on the network!</li> <li>This error usually occurs when WebEA does not receive any kind of response from the specified server name (or IP number).</li> <li>Possible reasons:</li> <li>The server is turned off</li> <li>The server is behind a firewall and WebEA is unable to make a connection to it</li> </ul>

Connection refused	<ul> <li>There was no response from the server, check that Pro Cloud Server is running!</li> <li>Possible reasons:</li> <li>Pro Cloud Server is not installed</li> <li>Pro Cloud Server is not running</li> <li>Pro Cloud Server is not listening on the expected port</li> </ul>
OSLC not supported	<ul> <li>The server port is not configured to support OSLC.</li> <li>Possible reasons:</li> <li>WebEA communicates with Sparx Systems Pro Cloud Server via OSLC, but the defined Sparx Systems Pro Cloud Server has been configured to not allow OSLC requests for this Port.</li> <li>Using the Pro Cloud Server Configuration Client, check the configuration for the Port which you are using to access this model. Ensure the "OSLC Supported" option is enabled.</li> </ul>
Protocol Mismatch	Protocol and Port mismatch. Check that the correct protocol and port have been configured.  Possible reasons:  There is a mismatch between the

	connection settings; for example, 'sscs_use_ssl' has been set to true but a protocol of HTTP was specified
Incorrect login details	<ul> <li>The specified login details were not valid for the current model!</li> <li>Possible reasons:</li> <li>The supplied user ID and password combination did not match any user credentials defined in the model</li> </ul>
Connection timed out	<ul> <li>Request Error: Connection timed out after 5001 milliseconds.</li> <li>Possible reasons:</li> <li>Invalid Pro Cloud Server settings (sscs_*), WebEA cannot connect to the defined server/port</li> <li>Apache/PHP web server requires a proxy server to reach the Pro Cloud Server machine and the proxy settings defined in the .config file are incorrect or invalid</li> </ul>
Failed to Connect	Request Error: Failed to connect to xxx.xxx.xxx.xxx port yy: Connection refused  Possible reasons:  The 'sscs_port' option in the

	webea_config.ini file does not match the port setting in your Pro Cloud Server configuration file (SSProCloud.config); make them the same Note that, if the Pro Cloud Server is being re-directed via IIS, you must ensure this matches the IIS port used for the Pro Cloud Server.
The configured database is not defined	<ul> <li>The configured database is not defined in the Pro Cloud Server.</li> <li>Possible reasons:</li> <li>The 'sscs_db_alias' option in the webea_config.ini file does not correspond to the 'Database Alias' defined in Add Database Manager; correct the values so that they do correspond</li> </ul>
Secure connection is required	A secure connection is required for the selected model.  This message indicates that the "Require a secure and authenticated connection" option is enabled for this Model Connection/Database Manager.

	To access this model via WebEA you must use the HTTPS protocol. You must also use a Port which has "Require SSL" enabled, and has the "Authentication" option set to either Model or Global.
Problem reading the model root	<ul> <li>Problem reading the model root.</li> <li>Possible reasons:</li> <li>The WebEA options for the current model do not match a Pro Cloud Server configuration</li> <li>You are attempting to access a DBMS repository which has not had a Project transferred into it. See Step 4 on the Server Based Repositories help page.</li> </ul>
No response when selecting an Object	After WebEA loads the initial page (the model root or default diagram), there is no response to selecting objects.  Possible reasons:  Your browser does not have javascript enabled; re-enable it  The cURL PHP module/extension is not installed and enabled on the server; install/enable cURL on your web server  The PHP version is wrong; it must be greater than PHP 5.0 with all

	extensions supported
An unexpected response was received	An unexpected response was received, check the Pro Cloud Cerver configuration!  This error normally occurs while attempting to login or connect to a model from the initial page. The error message will display whenever the response from the configured Pro Cloud Server does not return the expected XML message.  Check that the defined Sparx Systems Pro Cloud Server details, like server name and port are correct and not those of a web server.
The selected database does not have Pro Features enabled	<ul> <li>The selected database does not have Pro Features enabled.</li> <li>This error normally occurs if the selected model does not have 'Pro Features' enabled.</li> <li>Possible reasons:</li> <li>In the Pro Cloud Server Configuration Client, the Database Manager for this model does not have the 'Enable Pro Features (OSLC, WebEA and Integration)' option enabled</li> <li>The Pro Cloud Server's license has expired and the server is now operating</li> </ul>

as the free, core edition of the Pro Cloud Server

• The License key entered is invalid and the Pro Cloud Server is operating as the core edition

Using the Sparx Systems Pro Cloud Server Configuration Client, check the Database Manager configuration. Ensure that the 'Enable Pro Features (OSLC, WebEA and Integration)' option is enabled.

# Diagram image not found

Diagram image not found.

This error indicates that the diagram exists in the model, but the image of the diagram has not been generated.

Possible reasons:

- The model does not have the 'Auto create Diagram Image and Image Map' option enabled in model-specific options
- The diagram was created in Enterprise Architect, but has not yet been saved
- Or, the user is on an old version (prior to build 1350) of Enterprise Architect and the Worker application is not running for this model (it has not been configured, it is not currently running,

or has not run since the diagram was saved)

Open the model in Enterprise Architect (build 1350 or later), enabled the 'Data Cache' options, and click on the 'Create' button as described in the 'Model Configuration' section of the 'WebEA Installation and Configuration' topic.

Alternatively, ensure that the Worker application is running for this model. See the 'How to configure automatic viewable components' topic for details.

# Resource not found

The item (element, Package or diagram) with this GUID could not be found in the current model.

#### Possible Reasons:

 The item has been deleted from the model.

To confirm that the item has been deleted, check the parent Package (or parent element) in WebEA.

If the error occurred when selecting an

	item on a diagram, the diagram image might have to be regenerated.
SSL Error	<ul> <li>Error: SSL certificate problem: unable to get local issuer certificate</li> <li>This error suggests you are attempting an HTTPS connection without having SSL enabled.</li> <li>Possible Reasons:</li> <li>The webea_config.ini file does not include sscs_use_ssl = "true" for this Model. Try adding this, then attempt to access the Model again.</li> </ul>
Self signed certificate error	Request Error: SSL certificate problem: self signed certificate  This error suggests you are attempting an HTTPS connection with SSL using a self-signed certificate, however WebEA has not been configured to allow self-signed certificates.  Possible Reasons:  The webea_config.ini file does not include sscs_enforce_certs = "false" for this Model. Try adding this, then attempt to access the Model again.
No	400 - User Security is enabled, however

credentials	no credentials were provided.
provided	Possible Reasons:
	<ul> <li>The Project has Enterprise Architect user security enabled; however, WebEA is not configured to either show a login prompt or automatically login with specific credentials</li> <li>Check that the webea_config.ini contains: login_prompt = "true"</li> <li>Or, all of these: login_prompt = "false" sscs_model_user = "<user id="">" sscs_model_user = "<pre>password&gt;"</pre></user></li> </ul>
Incorrect Access Code	The entered access code is incorrect!
	Possible reasons:
	• This model has been configured (in the webea_config.ini file) to require an access code for WebEA access. The access code which was entered is incorrect.
	Check the webea_config.ini file for the correct access code / "auth_code".
Model is	The selected model is shutdown.

#### Shutdown

#### Possible reasons:

• The Cloud Server Model connection which you are attempting to access is not enabled.

Using the Pro Cloud Server Configuration Client, check that the Database Manager is set to "Enabled".

#### Version Mismatch

Warning - WebEA / OSLC Version mismatch

Each release of the Pro Cloud Server includes an OSLC component and the WebEA component (php files). If you are using the OSLC component from one release and the WebEA component from another, then WebEA might not function as intended.

#### Possible Reasons:

 A new version of the Pro Cloud Server was installed, however the new version of WebEA was not copied to the Web Server

When updating the Pro Cloud Server to a newer version, ensure that WebEA is also updated. That is, after performing the installation of the Pro Cloud Server, copy

	the new WebEA files from the Pro Cloud Server installation to the relevant location on your web server.
Basic login fields not shown	<ul> <li>The basic login fields will not be visible when attempting to log in to a model under these circumstances:</li> <li>The webea_config.ini has sscs_model_user defined</li> <li>The model has the user option 'Restrict access to Windows &amp; OpenID users only' enabled</li> </ul>

# **Problems loading pages**

Issue	Comments
No response when clicking on diagram elements	<ul> <li>When clicking on an element on a diagram nothing happens.</li> <li>Possible reason:</li> <li>The element properties are being loaded in the Properties View, however the Properties View is automatically hidden due to a narrow screen/browser width (less than 800px).</li> </ul>

	From the hamburger menu at the top right of WebEA, select 'Properties' to turn off the Properties View.
Pages don't load correctly	After the server has been updated to a new version of WebEA, clients experience problems with pages loading incorrectly.  Possible reason:  The user's browser is using a cached version of WebEA's client side files, which is causing unpredictable results The solution is to clear the browser cache, to force the browser to download the latest version of the application files from the server; the process for clearing the cache is different for each browser/device - consult the user manual for your browser
Login page in Internet Explorer	The 'Login' page is not drawn correctly and appears different to other browsers; that is, the selection boxes next to each model name are not square.  All login attempts to models with authentication fail saying 'No model selected!'

#### Possible reasons:

• IE is running in 'Compatibility View' mode, which does not support HTML5 and CSS3; turn off 'Compatibility View' at least for the server hosting WebEA

# **Prolaborate**

The Enterprise Architect set of tools to deliver world-class modeling and design solutions to business, industry and companies around the world has been significantly expanded with the inclusion of Prolaborate in the Pro Cloud Server offering.

Prolaborate represents the next step in effectively delivering rich models to a much-expanded set of consumers. Whilst Enterprise Architect has become the pre-eminent modeling and design solution globally for modelers and designers wanting to visualize and understand complex systems, software and architecture, Prolaborate is the next step in delivering those models and designs to the broader community and in enabling high level executives, business process managers, process implementers, consultants, customers and other stakeholders to see their personal and curated view of the model in a way that they are personally comfortable with!

Prolaborate is a tailored set of views that reduce complexity, focus attention and increase the accessibility of model information for non-modelers and others who are more concerned with consuming the model than directly editing it (although this can occur). Prolaborate provides a social platform 'outside the model' that supports talking about the model from a different viewpoint to those actively engaged 'within the model'. Prolaborate also provides dashboards, impact analysis and other 'outside the model' features that

derive information from the model or provide unique windows into the model for a custom audience (such as Chief Executive Officers, Chief Information Officers and customers).

#### **Benefits:**

- Takes the next step beyond modeling
- A social and collaborative tool for everyone
- Highly focused and customized model views
- New ways of seeing and interacting with Enterprise Architect models
- New tools for decision and impact analysis based on model content
- A platform for 'out of model' reviews and discussions
- For C-level executives looking for critical and strategic information
- For model consumers reviewing or implementing process flows
- For customers and other stakeholders who want to review and discuss the model
- For developers and software teams
- For those unfamiliar with modeling who want to understand and share their viewpoint
- A rich and evocative environment tailored for individual domains
- Discover the hidden value in your Enterprise Architect models

• Engage with a broader audience - present and discuss at the 'right level'

#### For further information

Full documentation on Prolaborate is provided on the website. You can access this documentation by clicking on this link (Javascript must be enabled on your web browser).

https://prolaborate.sparxsystems.com/resources/documentation

# **Integration Plugins**

The Integration Plugins components represent a set of plugins (or extensions) for the Pro Cloud Server that enable data from external providers to be displayed within Enterprise Architect.

The Integration Plugins component is also known by name Server Based Plugin Interface (SBPI).

# **Install and Configure**

The Sparx Systems Pro Cloud Server product is installed using a standard Microsoft Windows Installer package that includes a number of optional components. One of these components is Integration Plugins, which is installed by default into the C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI\ folder (assuming a 64 bit machine is being used).

# Requirements

In order to install a particular Integration Plugin you must have:

- A licensed Pro Cloud Server
- Physical network access to a server hosting the external data
- User credentials to access the external data
- Enterprise Architect Corporate, Unified or Ultimate edition v14 or later

# What is in the Package?

The Integration Plugins folder initially consists of a Integration Server executable (SBPI.exe), a separate

executable (\*SBPI.exe) for each supported external product, a sample configuration file and a text file describing the manual installation and configuration steps.

Task	Script
Integration (SBPI) Server	The SBPI.exe application acts as the interface between the Pro Cloud Server and each of the plugins by translating Enterprise Architect requests, forwarding them to the appropriate plugin and then returning the generated response to Enterprise Architect.
Application Lifecycle Manager Plugin	The ALMSbpi.exe plugin interacts with the MicroFocus Application Lifecycle Manager product (previously known as HP Quality Center).
Autodesk Plugin	The AutodeskSbpi.exe plugin interacts with AutoCAD's file and management component AutoDesk.
Bugzilla Plugin	The BugzillaSbpi.exe plugin interacts with the web based defect/bug tracking system that was originally developed and used by the Mozilla project and is now licensed under the Mozilla Public License agreement.

Confluence Plugin	The ConfluenceSbpi.exe plugin interacts with Atlassian's Team Collaboration Software.
Dropbox Plugin	The DropboxSbpi.exe plugin interacts with Dropbox's web based file hosting service.
EA plugin	The EASbpi.exe plugin interacts with external Sparx Systems's Enterprise Architect Cloud-based repositories.
Jazz Plugin	<ul> <li>The JazzSbpi.exe plugin interacts with:</li> <li>IBM Rational DOORS Next Generation's requirements management tool</li> <li>Rational Rhapsody Design Management (DM)</li> <li>Rational Team Concert Change and Configuration Management (CCM)</li> <li>Rational Quality Manager (QM)</li> </ul>
Jira Plugin	The JiraSbpi.exe plugin interacts with Atlassian's issue tracking system.
Salesforce	The SalesforceSbpi.exe plugin interacts with Salesforce's Customer Relationship Management system.

ServiceNow Plugin	The ServiceNowSbpi.exe plugin interacts with ServiceNow's asset management component of its Cloud-based enterprise management system.
SharePoint Plugin	The SharePointSbpi.exe plugin interacts with Microsoft's web-based collaborative platform, SharePoint.
Team Foundation Server (TFS) Plugin	The TFSSbpi.exe plugin interacts with Microsoft's source code management.
Wrike Plugin	The WrikeSbpi.exe plugin interacts with Wrike's project management system.

# How to Set Up

The Integration framework consists of an Integration server (SBPI.EXE) application that starts one or more plugins (such as DropboxSbpi.exe and JiraSbpi.exe). The Integration Server and each Integration plugin can be configured to run either on the same machine as the Pro Cloud Server or on completely different machines. In the simplest configuration the Integration server and all

Integration Plugins are installed on a single server. There are two main advantages with this configuration:

- 1. The Pro Cloud Server will automatically start (and stop) all configured plugins whenever its Windows service is started (or stopped).
- 2. The Integration configuration GUI inbuilt into the Cloud Configuration client can be used to completely manage all aspects of the Integration configuration; see the *Steps Simple* table.

However if you elect to run the Integration Server or Integration plugins on different machine(s) to the Pro Cloud Server, each of the individual plugins must be manually configured as well as configured to start as Windows services with the correct parameters. See the *Steps - Manual* table.


# Steps - Simple

The Integration configuration GUI included in the Cloud Configuration client removes most of the complexity involved in configuring the Integration Server and Data Provider(s), therefore this is the recommended method for most users. However this configuration method is restricted to running all Integration components (\*SBPI.exe) on the same server as the Pro Cloud Server.

Step	Description

Configuring Pro Cloud Server for Integration Each installation of Sparx Systems Pro Cloud Server can be configured to communicate with a single Integration Server; the configuration options of this definition are defined as a series of registry settings, however the 'Integration' tab in the Cloud Configuration Client allows the definition and maintenance of the Integration Server options without the need for you to manually manipulate the registry.

This image shows the definition of an Integration Server with the default settings:



Configuring
Integration
Data
Providers

Each Data Provider (or Plugin) is defined as both a series of registry entries in [HKEY\_USERS\.DEFAULT\Software\S parx

Systems\SQLBridge\SBPI\Plugins\{uniq ue} and settings within a configuration file. Again the Integration tab in the Cloud Configuration Client allows the definition and maintenance of Integration Data Provider details without the need for

	the user to manually manipulate the registry and configuration files.
Configuring the Firewall	The Integration server (SBPI.exe) typically needs to be granted access through any local firewall so that Enterprise Architect clients can connect to it. The Pro Cloud Server installer will automatically create a Firewall exception that allows any incoming requests to be passed through to SBPI.exe; however, the default settings should be reviewed and adjusted to suit your environment.

# Steps - Manual

Important: these steps are only needed if the Integration components need to run on different machine(s) to the Pro Cloud Server, otherwise the *Steps - Simple* table should be used.

Step	Description
Configuring Pro Cloud Server for Integration	Each installation of Sparx Systems Pro Cloud Server can be configured to communicate to a single Integration (or SBPI) server. These configuration options

are defined as a series of registry settings. This is an example of all valid options for the Integration server:

[HKEY\_USERS\.DEFAULT\Software\S parx Systems\SQLBridge\SBPI\Server]

"Arguments"="-port 8080"

"Port"=dword:00001f90

"Path"="C:\\Program Files (x86)\\Sparx Systems\\Pro Cloud Server\\SBPI\\SBPI.exe"

"Protocol"="http"

"Server"="yourdomain.com"

- Arguments the arguments that are used to start the SBPI server, which include the port the server should listen to; for example, "-port 8080"
- Port a hexadecimal value, representing the port number that the SBPI server should be listening to, which value should match the value specified in the arguments; for example, dword:00001f90 (decimal 8080)
- **Path** the full path to the SBPI server's EXE; for example:

"C:\\Program Files (x86)\\Sparx

Systems\\Pro Cloud Server\\SBPI\\SBPI.exe" When SBPI.EXE and the Pro Cloud Server are running on the same machine, PCS will attempt to start the SBPI.exe in this location

- **Protocol** the protocol that should be used to communicate to the machine hosting the SBPI server; that is, http or https
- Server the name (or IP number) of the machine hosting the SPBI server (for example, yourdomain.com); it is important to realize that this address is forwarded to the client (Enterprise Architect) so that it can make direct requests, which means the name or IP must be resolvable from the client machines

**Note:** The SBPI server typically needs to be granted access through any local firewall so that clients can connect to it. The ProCloudServer installer will automatically create a Firewall exception that allows any incoming request to be passed through; however, the default settings should be reviewed and adjusted to suit your environment.

# Configuring External Data Sources

Each External Data Source is defined as a series of registry entries in

[HKEY\_USERS\.DEFAULT\Software\S parx

Systems\SQLBridge\SBPI\Plugins\{unique}, where {unique} is a unique UUID for the data source. This is an example of a complete External Data Source definition:

[HKEY\_USERS\.DEFAULT\Software\S parx

Systems\SQLBridge\SBPI\Plugins\{8534 89C1-4C22-4bad-9A8E-3098D07A3FC1 }]

"Arguments"="-port 8081 -config Jira1.config"

"Name"="Sparx Systems Sample account"

"Path"="C:\\Program Files (x86)\\Sparx Systems\\Pro Cloud Server\\SBPI\\JiraSbpi.exe"

"Port"=dword:00001f91

"Prefix"="jira"

"Protocol"="http"

"Server"="127.0.0.1"

"Type"="Jira"

**Arguments** - the arguments that should

be used to start the plugin, which include the port the plugin should listen to and the name of the configuration file; for example, "-port 8081 -config Jira1.config"

Name - a 'friendly' project name to describe the external data source, which is displayed to all Enterprise Architect users; for example 'Sparx Systems Sample account'

**Path** - the full path to the plugin's EXE; for example, C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\JiraSbpi.exe

**Port** - a hexadecimal value representing the port number that the external data source expects to receive requests on, which value should match the value specified in the arguments; for example, dword:00001f91

**Prefix** - a short unique name that is meaningful to the users and prefixes each link stored within the Enterprise Architect model; for example, jira::10001 (where 10001 is the Jira object ID)

**Protocol** - the protocol that should be used to communicate to the machine hosting the plugin, such as http or https **Server** - the name (or IP number) of the

machine hosting the plugin (for example, yourdomain.com or 127.0.0.1); it is important to realize that this address is relative to the machine hosting the SBPI server, therefore the name or IP must be resolvable from the SBPI host machine

Type - a generic name to 'group' external data sources within Enterprise Architect
Each External Data Source requires its own set of options to define the details of how the configured Plugin connects to the External Data Source. These settings are stored in a .CONFIG file that resides in the same location as the Plugin's .EXE file. For example, using the above definition a 'Jira1.config' would need to be created, and would contain information similar to this:

SERVER=example.com

PROTOCOL=https

**PORT=443** 

BASEURL=myproject

**USERNAME=** 

PASSWORD=

CREATEITEMS=false

MODIFYITEMS=false

POSTDISCUSSIONS=true

PROXY=10.0.0.0:3128

# PROXYBYPASS=<local>;10.\* IGNORESSLERRORS=true

**SERVER** - the name (or IP number) of the external data source's server, such as example.com

**PROTOCOL** - the communicate protocol, such as https

**PORT** - the port the external data source is configured to listen on, such as 443

**BASEURL** - when the external data source supports multiple 'projects', the BaseURL property identifies which should be used; for example, for Enterprise Architect SBPI the BaseURL is the DB Alias as defined in the PCS

**USERNAME** - optional - see Note1

PASSWORD - optional - see Note1

**CREATEITEMS** - defines if Enterprise Architect users can create items in the External Data Source - see Note2; default value: false

MODIFYITEMS - defines if Enterprise Architect users can modify existing items in the External Data Source - see Note2; default value: false

**POSTDISCUSSIONS** - defines if Enterprise Architect users can add

Discussions to items within the External Data Source - see Note2; default value: true

**PROXY** - optional - the server name or IP number and port of the proxy server, such as 10.0.0.0:3128

**PROXYBYPASS** - optional - a semi colon separated list of IP numbers that should not be sent through the proxy; for example, <local>;10.\*

**IGNORESSLERRORS** - optional - a boolean value to ignore any SSL certificate errors

#### Note1

If the external server supports OAuth 2 authentication (Autodesk, Dropbox and Wrike), when accessing from within Enterprise Architect, a browser window will open and prompt you to log in to the external account and allow Enterprise Architect to access your account.

Enterprise Architect never sees your credentials in this process, instead it is provided with a unique token to access the external account.

If the external server allows basic authentication, then the username and

password can be optionally set in the configuration file.

If the username and password are not specified in the configuration file, Enterprise Architect will prompt you for credentials to access the external data.

#### Note2

Not all external products support the creation and modification of their objects, for example Dropbox.

# Configuring Models for External Data Sources

In order for users of an Enterprise Architect model to connect to a given External Data Source, a 'binding' between the Enterprise Architect model and the External Data Source must be configured. This is performed by a series of registry settings in

[HKEY\_USERS\.DEFAULT\Software\S parx

Systems\SQLBridge\SBPI\Bindings\{unique}] for each model/external data source combination. In this string, {unique} is an 8 hexadecimal digit number uniquely identifying the binding. For example:

[HKEY\_USERS\.DEFAULT\Software\S parx

Systems\SQLBridge\SBPI\Bindings\B6E E6851]

"LocalModel"="eaexample"

"Plugin"="{853489C1-4C22-4bad-9A8E-3098D07A3FC1}"

**LocalModel** - the DB Alias of the model, such as eaexample

**Plugin** - the UUID of the external data source; for example, {853489C1-4C22-4bad-9A8E-3098D07 A3FC<sub>1</sub>}

# **Special Notes**

#### Using SSL at the Integration Server or Provider Level

If you choose to implement the HTTPS protocol at either the Integration Server or Integration Provider levels the Integration Executables (\*SBPI.EXE) will require a 'server.pem' file in the same folder as themselves, therefore if using the default installation path this would mean 'server.pem' should be placed into the C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI\ folder.

See sections SSL Certificates and Self-Signed Certificate using OpenSSL on the page Add a Port Definition for more

information on how to create a valid 'server.pem' file.

#### The Integration Plugin for Enterprise Architect requires

- The BaseURL as the model's DB Alias
- The defined model configured as 'Enabled' and 'Enable Pro Features (OSLC, WebEA and Integration)' in the Pro Cloud Server

# What data is returned by Integration Plugins

Each of the Integration plugins developed by Sparx Systems returns information based on a 'Filter' or position within the product's external data. Some products, such as Enterprise Architect, Jira and TFS, provide a mechanism to customize the data returned, whilst others simply return all information at a particular position within the data.

Note: For Enterprise Architect, Jira or TFS the filters must be configured prior to Enterprise Architect requesting that an Integration Plugin should connect to them.

Provider	Information returned
Application Lifecycle Manager	Information returned based on the internal list for Defects, Requirements and Tests.
AutoDesk	Information returned based on the

	contents of: Hubs   Projects   Folders
Bugzilla	Information returned based on the contents of: Product   Component   <all component="" in="" items=""></all>
Dropbox	Information returned based on the contents of: Folders
EA	Presents a list of 'External Model' searches as defined in the local model. see screen 'Find in Project'   External Models
Jazz	Information returned based on the contents of: (DoorsNG) - Folders
Jira	Presents a list of 'Favorite Filters'. See menu option Issues   Manage Filters
Salesforce	Presents all item types that have a 'List View'.
ServiceNow	Presents a list of user defined filters, grouped by the table they are based on.
Team Foundation Server	Presents a list of TFS global and 'My' queries

Wrike	Information returned based on the
	contents of: Accounts   Folders

#### **User Guide**


The 'Integration Plugins' component of the Pro Cloud Server runs as a series of executables (.EXE) that do not have a graphical user interface (GUI) themselves; however, this User Guide describes the configuration editor screen(s) that are included in the Pro Cloud Server's Configuration Client that can be used to configure the Integration Plugins.

The main screen of the Configuration Client (installed as part of the Pro Cloud Server) includes an 'Integration' tab that is divided into two main sections. The top half defines the details of the Integration Server (or SBPI Server) with the lower half displaying the details of the various 'Data Providers'; each of these sections is described in greater detail in this topic.

Note 1: If you are using the Token edition of the Pro Cloud Server, before configuring Integrations, ensure you have enabled the required Integration Provider/s via the Token Allocation options. See: Manage Allocations

Note 2: Any changes to the Integration Server or Plugins (made either through the Configuration Client or manually) will require a restart of the Pro Cloud Server

# **Integration Server**



All requests for external data from Enterprise Architect are sent to the Integration Server (via the Pro Cloud Server), which decides which Data Provider (or SBPI Plugin) needs to action the request.

Note: the Integration Server settings are only mandatory, when the 'Enabled' flag is checked. The combination of Protocol, Name and Port need to match the machine hosting the Integration Server (in this case the Pro Cloud Server) in order for Enterprise Architect clients to be able to communicate to it.

Item	Description
Enable Integrations	Default value: Checked This checkbox enables (or disables) Integration Plugins for the current Pro Cloud Server installation. When this value is checked it implies that the other fields (Protocol, Name, Port and Path) are now mandatory and the Integration Server definition can not be saved without a value in each field.
Load	This button loads the default values for

Defaults	the Integration Server settings into any empty field.  Note: if a field already has a value, then the 'Load Default' button will not change or update this existing value.
Executable Path	Default value: {PCS installation folder}\SBPI\SBPI.exe This value defines the complete path for
	the Integration Server's executable, and if defined, implies that the Pro Cloud Server should automatically start this application when it's own service starts up (assuming the Integration Server Enabled flag is checked).
	If the Pro Cloud Server is installed into the default location then this value should be C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI\SBPI.exe.
Save	This button saves any pending changes to the Integration Server settings and is only enabled when there are unsaved changes.
Protocol	Default value: HTTP When the 'Use Proxy' option is unchecked, this value defines both the Protocol the Integration Server will listen

	on and the Protocol Enterprise Architect client will use to communicate to the Integration Server.  When the 'Use Proxy' option is checked, this value defines the Protocol that the Integration server will listen with.
Name/IP	Default value: {blank} This value defines the machine name or IP of the server hosting the Integration Server. When the 'Use Proxy' option is unchecked, this value defines both the machine name hosting the Integration Server and the machine name Enterprise Architect client will send their Integration related requests to. It is important to remember that this value is supplied to the Enterprise Architect clients so the Name/IP must be resolvable by them and not the current machine. When the 'Use Proxy' option is checked, this value defines the Server Name/IP of the machine hosting the Integration Server, the Proxy is responsible for converting the client Name/IP requested by Enterprise Architect to this value.
Port	Default value: 8080

	When the 'Use Proxy' option is unchecked, this value defines both the Port that the Integration Server will listen on and the Port Enterprise Architect clients will send requests to.  When the 'Use Proxy' option is checked, this value defines the Port that the Integration server will listen on.
Ignore SSL Errors	Default value: unchecked This value defines if SSL related errors that occur while communicating to the Integration Server component should be ignored. The most common SSL errors are related to self signed certificates, by default a client does not treat self signed certificates as being secure, therefore in order to connect to server that use self signed certificates this option should be checked.
Use Proxy	Default value: unchecked This value defines if the Integration Server is operating behind a proxy and if Enterprise Architect clients are required to connect to one URL, but the Integration Server is physically listening for requests on a completely different URL. In most environments this option

	should be set to the default value of unchecked.  This option was introduced in Pro Cloud Server 3.0.23, earlier versions were not capable of working in an environment that used a Proxy.
Client Protocol	Default value: {Protocol} - as set when the 'Use Proxy' option is checked This value is only available when the 'Use Proxy' option is checked and defines the Protocol that Enterprise Architect client will use to communicate to the Integration Server.
Client Name/IP	Default value: {Name/IP} - as set when the 'Use Proxy' option is checked This value is only available when the 'Use Proxy' option is checked and defines the machine name or IP of the server clients should send Integration requests to. It is important to remember that this value is supplied to the Enterprise Architect clients so the Name/IP must be resolvable by them and not the current machine.
Client Port	Default value: {Port} - as set when the 'Use Proxy' option is checked

This value is only available when the 'Use Proxy' option is checked and defines the Port that Enterprise Architect clients will send requests for the Integration Server to, this implies that when the Integration Server starts, it will configure itself to start listening on the specified
port.

#### **Data Providers**

A single Pro Cloud Server can support any number of external Data Providers, and in turn each of the external Data Providers can be available to as many models as are supported by the installations license. Please note only Pro-enabled repositories (or database managers) can access external data providers. A Pro-enabled database manager is one that has the 'Enable Pro Features (OSLC, WebEA and Integration)' option checked.

Option	Descruption
Defined Providers	This list defines a summary of all defined external Data Providers.  Double-clicking an existing item will display the 'Edit Data Providers' screen.


Add	This button displays the "Add Data Provider" screen to allow the entry of a new external Data Provider. See Add/Edit Data Provider
Edit	This button displays the Edit Data Provider screen to allow the modification an existing external Data Provider definition. See the Add/Edit Data Provider Help topic.
Remove	This button permanently deletes the selected Data Provider and all of its Bindings.  Note: this button is only enabled when there is a Data Provider selected.
Bindings	This control displays a check list of all Database Managers that are Pro enabled (that is, the 'Enable Pro Features (OSLC, WebEA and Integration)' option is selected). A checked Database Manager allocates the current Data Provider to the given repository.
Check All	This button is a quick and easy way to allocate all defined Pro enabled Database Managers to the currently selected Data Provider.

Uncheck All	This button is a quick and easy way to unallocate all defined Pro enabled
	Database Managers from the currently selected Data Provider.

# Add/Edit Data Provider


The 'Add/Edit Data Provider' screen will be shown whenever you request to create a new Data Provider or edit an existing one. The screen's behavior will be identical in either mode, the one difference being that the details of the selected Data Provider will be displayed when the screen loads in Edit mode.

When you choose to add a new Data Provider, the screen will initially display as shown:



Wherever possible the 'Add/Edit Data Provider' screen will fill each field with a default value in order to make it easier for you; if the default values are not correct, simply

overwrite them. To this end, whenever the 'Provider' value is changed, a number of other fields will be set to the default values for the new Provider, such as the Data Provider's Prefix, the Integration Plugins' Executable Path and config filename, as shown here when Enterprise Architect is selected:



Note: When defining a Data Provider there are a number of mandatory fields (denoted with a '\*') that require a value before a Data Provider can be saved.

#### **Data Provider settings**

Item	Description

Name	This value represents the friendly name for the current Data Provider, it will be shown to users of Enterprise Architect.
Provider	This value specifies the Provider type of the current Data Provider; only supported values can be used. As mentioned, whenever this value is changed a number of other fields can be automatically updated to make data entry easier for the user.
Prefix	This value represents a short unique name to identify the current Data Provider. This value will be saved against every Enterprise Architect element that is linked to an external element.

# **Integration Plugin settings**

This group of settings related to the physical location of the Integration Plugin relative to the Integration Server, the combination of Protocol, Server Name and Port must be resolvable by the machine hosting the Integration Server, so that requests can be forwarded to it. In the simplest case the Integration Plugin will reside in the same folder as the

# Integration Server, ie C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI

Item	Description
Protocol	This value represents the protocol that the Integration Server should use to communicate to the Integration Plugin, in the simplest configuration this will be HTTP.
Server Name/IP	This value represents the Server Name or IP that the Integration Server should use to communicate to the Integration Plugin, in the simplest configuration this will be localhost (or 127.0.0.1).
Port	This value represents that the Integration Server should use to communicate to the Integration Plugin. Each Integration Plugin requires a unique Port number. The application automatically initializes this to 8081.
Executable Path	This value represents the physical path to the Integration Plugin executable file. If a value is specified the Integration Server will attempt to start this executable during it own startup routine.

Config	This value represents the physical
filename	filename of the configuration file for the
	current Integration Plugin, which must
	reside in the same folder as the
	Integration Plugin's executable.

#### **Provider Server settings**

This group of settings relate to the details of the external data provider, ie Dropbox, Jira or TFS. The Integration Plugin will use the defined details to connect to the remote system and retrieve data from it so that it can be sent back to Enterprise Architect. The combination of Protocol, Server Name and Port must be resolvable by the server hosting the Integration Plugin, which in the simplest case is the Pro Cloud Server.

Item	Description
Protocol	This value represents the protocol that the Integration Plugin should use to communicate to the external Data Provider.
Server Name/IP	This value represents the Server Name/IP that the Integration Plugin should use to communicate to the external Data

	Provider.
Port	This value represents the port that the Integration Plugin should use to communicate to the external Data Provider.
Base URL	Some external Data Providers allow for the concept of multiple repositories at a single location, for such Data Providers this field acts as a filter.  For example it is possible to use another Enterprise Architect model as an external data source, in the case of Enterprise Architect the Protocol, Server & Port determine the Pro Cloud Server, the Base URL is the DB Alias of the repository.
Link Base	Some external Data Providers allow for the concept of elements providing a direct external link to themselves, for such Data Providers this field acts as a base URL that the individual element's unique identifier can be appended to.  In the case of an Enterprise Architect external Data Provider, the Link Base field defines the WebEA address (including the model number) for the external data provider. ie

	"http://192.168.0.10?m=2"
User Name	This value represents the user name that should be used (in combination with the password) to access the data within the external system. If a value is defined in this field all Enterprise Architect users of the current Data Provider will use the same set of credentials to read the external system. Otherwise if the user name field is left empty, Enterprise Architect will prompt each user independently for their credentials.
Password	This value represents the matching password for the specified user name.
Create Items	Default value: unchecked This checkbox controls if Enterprise Architect users are able to create new items within the external system.
Modify Items	Default value: unchecked This checkbox controls if Enterprise Architect users are able to modify the details of external items within the external system.
Post	Default value: checked

Discussions	This checkbox controls if Enterprise Architect users are able to create discussions against elements within the external system.
Ignore SSL Errors	Default value: unchecked This checkbox controls if the Integration Plugin should ignore SSL related errors that occur as a result of communicating to the external system.

#### Logging settings

This group of settings relate to the how the Integration Plugin will create entries in it's log file(s). Since the Integration Plugins run without user intervention, it is important for them to be able to write to any messages or potential problems to a log file. However special consideration must be made to ensure that performance isn't impacted by writing to such files, which is possible if the log file continually grows without limits. It is also unreasonable to expect that manual intervention should be required to ensure that the size and number of log files don't impact performance. For these reasons each Integration Plugin has it's own set of log files and configuration options to manage its log files.

The current log file will always include a '1' on the end of its filename. A new log file will be created whenever the Integration Plugin is started or the physical size of the current log file reaches the Max File Size. When this occurs all existing files will be 'rolled over', meaning their file numbers will be incremented and a new '{filename}1.log' created. If the roll over process causes more files to exist than the 'File Count' setting allows, these additional files will be deleted.

Item	Description
File Count	Default value: 3 This value represents the 'rolling' number of log files that should be retained for the current Integration Plugin.
Max File Size	Default value: 1048576 This value represents the maximum number of bytes a log file can be before a new one is created.
Level	Default value: WARNING This value represents what maximum level of messages that should be written to the log file. The levels are: OFF, FATAL, WARNING, INFO and SYSTEM. A defined log level is

	inclusive of all lower levels, therefore if a Plugin is set to a log level of INFO then all FATAL, WARNING and INFO messages will be written to its log file.
Directory	(READ-ONLY) This field displays the physically location of where the log files for the current Data Provider will be saved.

# **Proxy settings**

This group of settings relate to how the Integration Plugin should communications to the External Data Provider when they are separated by a Proxy Server.

Item	Description
Server Name/IP	The server name (or IP) and port number of the Proxy Server. ie proxyserver.com:3131
Bypass	This field provides a mechanism for certain addresses to bypass the proxy; it accepts multiple values separated by semi-colons (;). For example, 192.168.*;*.localdomain.com;www.myd

	omain.com
User Name	If the Proxy Serer requires credentials, then enter the user name into this field.
Password	If the Proxy Serer requires credentials, then enter the password into this field.

# **Integrate Data from External Providers**

The Pro Cloud Server helps you to integrate data from external providers into an Enterprise Architect Cloud model. A variety of third-party providers can be connected to, including:

- Quality Center)

  Application Lifecycle Management (formerly HP Quality Center)
- - IBM Rational DOORS Next Generation's requirements management tool
    - Rational Rhapsody Design Management (DM)
  - Rational Team Concert Change and Configuration Management (CCM)
    - Rational Quality Manager (QM)
- Jira and Confluence
- Team Foundation Server
- Wrike
- . ServiceNow
- . 🛕 Autodesk
- 🔑 Bugzilla
- Salesforce
- SharePoint
- Stropbox and



# • Other Enterprise Architect models

See the Install and Configure Help topic for information on how to configure each provider.

All integrations offer support for linking objects and elements from the external system into an Enterprise Architect client. The Integration window supports browsing the external provider's items and retrieving lists of elements and objects based on the provider's queries. Capabilities include:

- Link an Enterprise Architect element to an external object
- View external element properties
- View and in some cases add to, external object discussions
- Export links to WebEA URL's that correspond to the current model
- Open external items in a web browser
- Import elements
- **Export elements**

From Enterprise Architect Release 14.1 it is possible to link a non-Cloud model to Integration Plugins configured on a Pro Cloud Server.

See the *Cloud Page* Help topic for configuration options.

#### Access

Ribbon	Specialize > Tools > System Integration > Open External Data
	To view a list of all elements that are linked to external items:
	Specialize > Tools > System Integration > Show All Linked Items
Context Menu	<ul> <li>In a diagram or the Browser window, for elements that are already linked to an external item:</li> <li>Right-click on element &gt; Specialize &gt; External Properties</li> </ul>

#### **Features**

Feature	Description
Pro Cloud Server Configuratio n	Each external provider needs to be configured on the Pro Cloud Server to enable connection. Multiple configurations can be made for each provider (such as connecting to two separate Jira servers).
Authorization	If the Integration Provider requires authorization the user will be prompted to

	enter their credentials. If the provider supports it, a new internet browser window will open and prompt the user to log in to the Integration Provider and allow Enterprise Architect access to its resources. Alternatively, a simple dialog will pop up asking for the user's credentials, with the option to securely store these in the current model. If stored in the model the credentials will only be used for the current user.
Navigate External Provider	Find external items to link by navigating the external provider.
External Item Details	Select an external item from the list to see its properties, notes and discussions.
Link External Items	External items can be linked to Enterprise Architect as a generic «ExternalReference» stereotype or as another element type.
Add WebEA Link	Hyperlinks to WebEA can be added to the external item so that a user can quickly open the WebEA element from the external source.  Right-click on a local linked element in

	the list and select 'Add WebEA Hyperlink to External Object'. This will update the external item with a link to the WebEA element that is linked to it. Note that not all provider types have a 'link' mechanism. Where none exists, some providers might allow adding the link as a comment on the item.  Ensure that the model has a valid WebEA address set in the model options.
Configuration	Each integration provider comes with a set of default mapping values which determines what type of local element is created in Enterprise Architect, as well as which fields are copied to the new element. These mappings are configurable via the 'Configure' option on the Integration window toolbar menu.  Users must have the 'Configure External Data Sources' permission to access this functionality.
Troubleshoot ing	<ul> <li>The System Output window will show any errors while attempting to retrieve data from the external providers</li> <li>The Pro Cloud Server outputs log files for each external provider</li> </ul>

#### **Notes**


- 'Integration' requires a Pro Cloud Server and is only available to Cloud models
- 'Integration' is currently provided with the Corporate, Unified and Ultimate editions of Enterprise Architect
- If you select two or more elements at the same time, you can perform an operation on all of the selected elements at once
- For WebEA links to work a valid URL must be set for the WebEA address (see the *Cloud Page* Help topic)

# **Navigate External Data**


Each integration provider can be navigated through to show lists of external items that can be linked to Enterprise Architect. Each provider might provide a slightly different mechanism for navigation based on how it stores its data. Some provide a simple folder hierarchy, while others provide for user defined filters. See 'What data is returned by Integration Plugins' on Install and Configure for details of each provider.

## **Navigate the Hierarchy**

Begin navigation by selecting the provider type from the first drop-down menu.




Next, each provider type offers a slightly different navigation system; for example, Dropbox allows for browsing the folder structure, whilst Jira give a list of projects followed by a list of user queries.




#### **Item List**

At each navigation level, if available, a list of items corresponding to the navigation level will populate the left-hand panel.



Any local Enterprise Architect elements that are linked to the external item will be shown as a child of the external item.



#### All Items Linked to Model

At each navigation level there is an option to show all local

Enterprise Architect elements that are linked to the selected external data source. Select 'All Items Linked to Model' and choose a recent time period (7, 30 or 90 days, or 'All') to show.

Choose 'All Items Linked to Model' on the root navigation level to see the linked items for all external providers.

This view is different to the regular list as it shows the local Enterprise architect element on top, and the external linked item as a child of the local element. All the same context menu items are available in the view.

As a team, we can finish the sprint by clicking the cog icon next to the
 As a team, we can finish the sprint by clicking the cog icon next to
 As a user, I'd like a historical story to show in reports
 As a user, I'd like a historical story to show in reports


#### **Show Items Linked to Current Context**

In the integrations menu, select 'Items Linked to Current Context' to show only the external items that are linked to the currently selected local element. That is, select an item in the Browser window and see the external items that are linked to it.

This view is the same as for 'All Items Linked to Model'.


### **External Item Details**

When an external item is selected in the list, the item's details are retrieved and displayed.



## **Properties**

Select an external item from the list to view its External Properties. This window shows all available properties of the external item, as defined by the external provider.



Properties that will be used when creating a linked local element are show in the top group 'Mapped Properties' while all other properties are grouped in 'Other Properties'. The property mapping can be configured in <a href="Configuration">Configuration</a>.

#### **Notes**

The external item's notes or description is shown below the properties. Note that not all external providers have a notes or description field.


#### **Discussion**

Select an external item from the list to view its External Discussions. This window shows the discussions or comments of the external item.

New discussions can be posted by typing into the top box

and pressing 'Send'. The username used will be that is authorized on the Integration Provider. If generic credentials have been added to the server configuration then the local model's user name will be added to the start of the comment as well.

Show or hide the discussions by clicking the icon in the top-right corner.



#### Note:


- To post an external discussion the Integration Provider must be configured to allow this on the Pro Cloud Server (allowed by default)
- Not all external providers have discussions or comments

# **Linking Items**

# **Create Linked Element in Enterprise Architect**

To create a new element in the Enterprise Architect model linked to the external item:

- Right-click on an external item in the list.
- Select Create Local Element
- Select either the default type (see <u>Configuration</u>) or «External Reference»
- Select which Package the element will be created in
- Optionally add the new element to an open Diagram



The local element will be filled in with the values defined in the Field Mapping in Configuration.

Once linked, the local element will show under the external item:

**Note:** Select multiple items to create multiple elements at the same time. All elements will be created with either the default type or «ExternalReference»

## Link an Existing Enterprise Architect Element

An existing element in Enterprise Architect can be linked to an existing item in the external provider by dragging the local element from the Browser window and dropping it onto the external item.

#### Create a Linked Item in the External Provider

Existing local elements in Enterprise Architect can be added to the External Provider in this way:


- 1. Select the local Enterprise Architect element (in the Browser window).
- 2. Browse the external provider and select the required destination location.
- 3. In the External Data Menu, select 'Create Linked Item'.

#### Note:

- To create a new external item, the Integration Provider must be configured to allow this on the Pro Cloud Server (it is disallowed by default)
- Not all providers allow for creation of new items

# **Update Local Element ('Pull' changes)**


If either the local element or external item have been modified since the items were created or linked, an indicator will be shown on top of the item's icon. Right-click on the linked Enterprise Architect element and select the 'Pull - Update Local Element with External Data' option.



**Note:** If the local element has been modified since the link was created then its changes will be overwritten with the external data.

## **Update External Item ('Push' changes)**

If either the local element or external item have been modified since the items were created or linked, an indicator will be shown on top of the item's icon. Right-click on the Enterprise Architect element and select 'Push - Update External Item with Local Data'.




#### Note:

- If the external element has been modified since the link was created then its changes will be overwritten with the local data.
- To update an external item the Integration Provider must be configured to allow this on the Pro Cloud Server (disallowed by default).

## **Synchronize All Local Elements**

All local linked elements from a provider can be quickly updated with new data from the external provider's items.

- 1. Browse to the external provider to be synchronized
- 2. In the External Data menu, select 'Synchronize Local Linked Elements'
- 3. Tick the fields that should be updated with any new data from the external item. Note that any local changes in the Enterprise Architect element in these fields will be overwritten with the external data.
- 4. The bottom of the window indicates how many local elements will be updated (note that it is unknown at this point if there have been any changes to the external item)
- 5. Click 'Synchronize'



# Configuration

Each integration provider comes with a set of default mapping values which determines what type of local element is created in Enterprise Architect, as well as which fields are copied to the new element. These mappings are configurable for each client model.

#### **Permission**

Users must have the 'Configure External Data Sources' permission to access this functionality.

#### **Access**


Integration window toolbar
----------------------------

## **Type Mapping**

This defines the element type that will be created when

'Create Local Element' is selected.


To create a new mapping, select the External Type, and use the toolbox selector to select the local element type.



## **Field Mapping**

This defines the element type that will be created when 'Create Local Element' is selected.

To create a new mapping, select the External Type, and use the toolbox selector to select the local element type.



#### **Notes**

- Each mapping can be reset to default values by clicking 'Reset to Defaults'.
- If no type mapping is specified for a specific type, then the mapping for type 'Default' will be used.

# **Troubleshooting**

## **Integration Server messages**

There are a number of error messages that could display during the definition of the Integration Server settings; most are self explanatory. This table describes the most common error messages.

Error Message	Description
Please enter a value for [field_names] . The Integration Server can only be saved (while enabled) when all mandantory fields have a value	Reason: When the Enabled flag is checked, all remaining Integration Server fields are mandatory. This message occurs when one or more Integration Server fields are empty and the Enabled flag has been checked. [field_names] represents a placeholder for a comma separated list of field names that are empty.
The executable name of	Reason: The 'Executable Path' field has a value but it does not include the filename "\SBPI.exe", which is the only valid

SBPI.EXE was expected	filename that can be used.
The specified Integration Server path of [full_path] does not exist or is invalid	Reason: The 'Executable Path' field has a value but the path portion of the specified value is not valid or does not exist on the Pro Cloud Server machine.
The specified Port is a duplicate of [duplicate_pl ugin_name]	Reason: The 'Port' field has been assigned a Port number, however it is a duplicate of a port being used by the Integration Data Provider with the name [duplicate_plugin_name].

## **Integration Data Provider messages**

There are a numerous error messages that could display during the definition of a Integration Data Provider; most are self explanatory. This table describes the most common error messages.

Error Message	Description

Please enter a value for [field\_names]. An Integration Provider cannot be saved without all mandatory fields being assigned a value.

Reason: To minimize the chance of defining an invalid Data Provider the application ensures that all mandatory fields are given a value. [field\_names] represents a placeholder for a comma separated list of field names that are empty.

Ports needs
to be unique
across all
Providers, the
port value of
[new\_port]
has already
been used by
[other\_provid
er]

Reason: A Port number has be defined for the current Data Provider, however the value is a duplicate of another provider's port.

The specified execution path for the provider does not exist or is

Reason: The 'Execution Path' for the data provider has been assigned a value, however either the path, filename or both cannot be found on the local machine.

invalid, [full_path]	
The specified Port is a duplicate of the Integration Server	Reason: A Port number has be defined for the current Data Provider, however the value is a duplicate of port used by the Integration Server.
Failed to rename config file [old_filenam e] to [new_filenam e]	Reason: When the user changes the config filename of an existing Data Provider the Cloud Server must rename the old filename to the new one. This message will be shown if the rename task is not successful, (which can occur if the file is in use by another process) and this case manual intervention is the only way to resolve this issue.
Prefixes needs to be unique across all Providers, the prefix value of [new_prefix] has already been used by	Reason: A Prefix has be defined for the current Data Provider, however the value is a duplicate of prefix used by another provider.

[other_provid er]	
Config filenames needs to be unique across all Providers, the config filename of [new_filenam e] has already been used by [other_provid er]	Reason: A Config filename has be defined for the current Data Provider, however the value is a duplicate of config filename used by another provider.

## **General Troubleshooting**

This table provides general advice to help identify and resolve common issues with the Integration component of the Pro Cloud Server.

#### **Problem Description**

Problem: After making changes to the Integration definitions of the Server or Data Providers, the Enterprise Architect users do not notice any differences.

Reason: After changing the Integration configuration was the Pro Cloud Server restarted? If not restart the Pro Cloud Server.

Problem: A newly configured Integration Data Provider is not listed in the navigation breadcrumb of Enterprise Architect (after the Pro Cloud Server has been restarted).

Reason: Confirm that the currently open Model has a Binding entry for the Data Provider. See the Bindings item in <u>User Guide</u> topic for details.

Problem: Selecting items within the Integration navigation breadcrumb of Enterprise Architect seem to have no effect.

Reason: It is possible that errors (or warnings) are occurring which are logged to the System Output Window, therefore make sure the System Output Window is shown while using the Integration window.

Problem: General errors seem to be occurring however no useful information is shown in the System Output Window.

Resolution: Each Integration Data Provider has the capability to write detailed entries to a log file, to ensure that the most detailed information is written, change the

log level for the Data Provider to SYSTEM (restart the Pro Cloud Server) and then retry the same action in Enterprise Architect. Then review the Data Provider's log file, ie in C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\SBPI\Logs on the Pro Cloud Server.

# **Visibility Levels**

The 'Visibility Levels' feature within Enterprise Architect provides the ability to restrict access to certain sections of a model. Only models hosted by a Pro Cloud Server are able to make use of this feature. Visibility Levels are implemented by taking advantage of the Row Level Security feature included in Oracle 8+ and Microsoft SQL Server 2016 (onwards).

Row Level Security is a security feature that controls what rows of data an individual database users can access. Traditional database security only provides the ability to control the permissions of a user at the table level, ie can they read, write or delete data in a particular table. Since Row Level Security functionality is implemented by the database, it is impossible for users to bypass security implemented at the application level, by writing their own scripts or databases queries. That is, the database ensures that users can only view and update data they are authorized to access.

Given that Row Level Security is implemented by the database, most of the configuration for Enterprise Architect and the Pro Cloud Server to support it is performed directly in the database without needing to change the application code base, which means there is less to go wrong from an application perspective.

# **Database / Application Users**

It is important to understand the distinction between database and application users. The introduction mentions that visibility levels are based on Database User permissions. In the Sparx System Pro Cloud Server environment, each Database Manager is defined with all of its connection details (including the user and password) to a given database. It is the database user, the user identified in the connection details, that visibility levels are based on.

This concept is not to be confused with Enterprise Architect model users; that is, the user ID/password that is entered when accessing a security enabled model. This is an application user.

Note: Enterprise Architect's model security is not mandatory, whereas all DBMSs require a database user to be defined in order to access data within the database.

#### How it works

In addition to their normal permissions, database users are granted access to one or more visibility levels. A new column, VIS\_LVL (Visibility Level), is added to 24 critical tables within the Enterprise Architect database. This field stores the visibility level that is required to view or update this record.

For each of the 24 tables, a security policy is defined that ensures each database user only sees records that their assigned visibility level is authorized to view.

Database triggers are then used to maintain the value of the VIS\_LVL columns in all tables for all child objects and elements. For example, setting the visibility level of a Package in Enterprise Architect's Browser window will update the selected Package and all of its children to the entered visibility level.

Note: The base scripts supplied by Sparx Systems support 20 'levels' of security (that is, 1 to 20); however this can easily be adjusted by manually changing the number of rows that are inserted into the T\_VISIBILITYLEVELS table at the beginning of the script. Level 0 is a special case, representing the default value; it implies that all database users (even those without an assigned visibility level) can view or update records of this level.

#### The Drawback

As with most things, enabling Visibility Levels entails a cost when compared to the same model without Visibility Levels being enabled. Row Level Security in both SQL Server and Oracle imposes extra processing on the database server each time data is selected. The impact of this extra processing on database performance is difficult to estimate, as it depends on the type and amount of data being selected. Enterprise Architect's support of Visibility Levels has been designed with efficiency in mind; however, the performance will inevitably be reduced when Visibility Levels are enabled.

# **Install and Configure**

The Sparx Systems Pro Cloud Server product is installed using a standard Microsoft Windows Installer package that includes a number of optional components. One of these components is Visibility Levels, which is installed by default into the C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\VisibilityLevels\ folder (assuming a 64bit machine is being used). If necessary, you can change the install location of the Visibility Levels files.

## Requirements

In order to use Visibility Levels you must have:

- A licensed Pro Cloud Server
- An Oracle 8+ or SQL Server 2016+ based Enterprise Architect model/repository that uses the EA1220 schema definition
- An SQL based management console tool that supports the execution of SQL scripts
- Enterprise Architect build 14.0 or later
- Enterprise Architect Ultimate Edition for assignment of Visibility Level on a Package

## What is in the Package?

The Visibility Levels folder consists of a number of SQL script files that will either apply or remove the required database changes to an Enterprise Architect model so that it can support the DBMS's native Row Level Security feature.

The implementation of Row Level Security in Oracle is completely different to the implementation in SQL Server. While the end result behaves the same way, the physical objects that are needed by each DBMS are sufficiently different for each to need its own creation script.

Task	Script
Apply Visibility Level changes to Oracle model	EASchema_VL_Updates_Oracle_1220.s  ql - Oracle SQL script that will update an existing Enterprise Architect Oracle based repository so that it supports Visibility Levels, by creating a set of functions, procedures, policies, triggers and columns.
Apply Visibility Level changes to SQL Server model	EASchema_VL_Updates_SQLServer_12 20.sql - SQLServer specific SQL script that will update an existing Enterprise Architect MS SQL Server based repository so that it supports Visibility Levels, by creating a set of functions, procedures, policies, triggers, roles and columns.

Remove Visibility Level changes from Oracle model	EASchema_VL_Removal_Oracle_1220.s  ql - Oracle SQL script that will remove the functions, procedures, policies, triggers, roles and additional columns that were added to support Enterprise Architect's Visibility Levels.  Note: All basic Enterprise Architect modeling data will remain unchanged by the removal script.
Remove Visibility Level changes from SQL Server model	EASchema_VL_Removal_SQLServer_1 220.sql - SQLServer SQL script that will remove the functions, policies, triggers, roles and additional columns that were added to support Enterprise Architect's Visibility Levels. Note: All basic Enterprise Architect modeling data will remain unchanged by the removal script.

#### How to execute

In order for an Enterprise Architect model to support Visibility Levels, the appropriate update script must be executed on that model's database. The script is standard SQL, so any tool can be used; however, you must connect using an ID with owner privileges because updates will be made to the physical schema.

## **Script Execution for Oracle**

- 1. Identify the Enterprise Architect model database to which to apply Visibility Levels.
- 2. Ask all users to log out of the model.
- 3. (Optional step) Physically stop any further user access to the database; for example, disconnect the server from the network.
- 4. Perform a complete backup of the database.
- 5. Open your SQL console of choice and connect to the database as the owner.
- 6. Load the Oracle script ('EASchema\_RLS\_Updates\_Oracle\_1220.sql') into the console.
- 7. Review the comments at the top of the script, in particular the section that outlines the tasks that need to occur before running the script.
- 8. Make the needed adjustments to the script for your environment/preferences.
- 9. Execute the script.
- 10. Follow the set of instructions documented at the top of the script in the 'Do the following AFTER running this script' section

- 11. Perform a second complete backup of the database, as a restore point.
- 12. Define the Database Managers in the Pro Cloud Server (refer to the *Defining Visibility Level Aware Database Managers* table in the Visibility Levels *User Guide*).
- 13. (Optional step) If Step 3 was performed, re-enable regular user access to the database.
- 14. Open Enterprise Architect Ultimate edition, connect to the Pro Cloud model with the highest Visibility Level (as defined in step 12) and set the Visibility Level on all Packages to their required values.

## Script Execution for MS SQL Server

- 1. Identify the Enterprise Architect model database to which to apply Visibility Levels.
- 2. Ask all users to log out of the model.
- 3. (Optional step) Physically stop any further user access to the database; for example, disconnect the server from the network.
- 4. Perform a complete backup of the database.
- 5. Open your SQL console of choice and connect to the database as the owner.
- 6. Load the SQL script ('EASchema\_RLS\_Updates\_SQLServer\_1220.sql').
- 7. Review the comments at the top of the script, in particular

- the section that outlines the tasks that need to occur before running the script.
- 8. Make the needed adjustments to the script for your environment/preferences.
- 9. Execute the script.
- 10. Follow the set of instructions documented at the top of the script in the 'Do the following AFTER running this script' section
- 11. Perform a second complete backup of the database, as a restore point.
- 12. Define the Database Managers in the Pro Cloud Server (refer to the *Defining Visibility aware Database Managers* table in the Visibility Levels *User Guide*).
- 13. (Optional step) If Step 3 was performed, re-enable regular user access to the database.
- 14. Open Enterprise Architect Ultimate edition, connect to the Pro Cloud model with highest Visibility Level (as defined in step 12) and set the Visibility Level on all Packages to their required values.

### **User Guide**

The functionality of the Visibility Levels feature is primarily restricted to System Administrators, in order to set up and configure models to limit access to certain Packages in a model. Generally, users will not be aware of Visibility Levels; they simply will not see certain Packages in the model.

# **Defining Visibility Level Aware Database Managers**

For the most part, defining Database Managers in the Sparx Systems Pro Cloud Server Configuration Client is the same process as for non Visibility Level database managers. These are the exceptions:

DB MS	Discussion
Or ac le	All Oracle connections require a 'DefaultSchema={schema_name};' option manually added to the connection string, where {schema_name} is the physical name of the schema that owns the Enterprise Architect tables. For example:  Provider=OraOLEDB.Oracle.1;Password=pass;Persi

st Security Info=True;User ID=user1;Data
Source=ORA\_SN;DefaultSchema=owner\_user;
In a typical Oracle connection to an Enterprise
Architect model the 'User ID' option is both the
owner of the tables and the user credentials that are
being used to access the data. However, in a model
using the Visibility Levels feature, these options are
different, so the 'DefaultSchema' option has been
added to define the table owner.

M icr os of t S Q L Se rv

er

All SQL Server connections require an 'Alias' field value that uniquely identifies the database manager on the current server. The 'Alias' value is the name by which Enterprise Architect users know the model. In previous versions of the Pro Cloud Server, the database manager alias for SQL Server-based connections was automatically determined by the database name, which meant that each SQL Server database could only ever have one database manager defined in the Pro Cloud Server. Now with the use of the 'Alias' field a single database can have an unlimited number of database managers defined.

# **Enabling the Extended OLSC Interface on a Database Manager**

In order for the Pro Cloud Server to allow the use of Visibility Levels in a model the 'Enable Pro Features (OSLC, WebEA and Integration)' option must be selected. This is achieved by opening the Sparx Systems Pro Cloud Server Configuration Client application (SSProCloudClient.exe) connecting to the appropriate server. You then select the database manager in the list and click on the Configure button. On the resulting Configure Database Manager screen select the 'Enable Pro Features (OSLC, WebEA and Integration)' checkbox.

## **Visibility Level Administration**

When the Ultimate edition of Enterprise Architect is used to connect to a model that has Visibility Levels configured, there is an additional menu item, 'Set Visibility Level...' available under the 'Package Control' context menu of each Package object in the Browser window.

If your model has security enabled, then all application users that require access to the 'Set Visibility Level...' menu item will need to be allocated the 'Visibility Level Admin' or 'Administer Database' security permission, using standard Enterprise Architect permission assignment.

## Set a Package's Visibility Level

From within the Ultimate edition of Enterprise Architect, the Visibility Level of a Package can be set using the Browser window context menu item 'Package Control | Set Visibility Level...'.

This menu item will only be available in models that have been set up for Visibility Levels, are being accessed via a Pro Cloud server connection and the user has a Ultimate License.

Once a Visibility Level has been set on a Package, that Package and all of its children can be viewed, accessed and updated only by users with the corresponding access level.

To remove a visibility level from a Package (and all its children), simply set the Visibility Level back to unrestricted.

## Visibility Levels users can apply

Users can only set the Visibility Levels on Packages to levels the current database user has access to. For example, an Enterprise Architect client connected to a Cloud connection that uses a database user that has been assigned levels 3 & 4 can update the Visibility Level of any Package to the levels unrestricted, 3 or 4.

# **Troubleshooting**

### 'Set Visibility Level' menu is not available

The 'Set Visibility Level' menu item can be hidden from users for a number of reasons:

- You are not connecting to the model via a Cloud connection
- You are not using Enterprise Architect release 14 (or above)
- You are not using the Ultimate edition of Enterprise Architect
- The Cloud Server you are connected to has an expired license and is now operating as the free edition
- The model you are connecting to is NOT Oracle or MS SQL Server based
- The model in the Cloud Server you are connecting to is not configured with the 'Enable Pro Features (OSLC, WebEA and Integration)' option
- The model you are connecting to has not been configured/adjusted for Visibility Levels (that is, the update script has not been run against the database)
- The currently logged on application user has not been granted access to the 'Visibility Level Admin' Enterprise Architect security permission.

## **Floating License Server**

The Sparx Systems Key Store server has been available for many years, providing users of Enterprise Architect with the ability to manage their floating licenses. Up until version 2.1 of Pro Cloud Server, Floating License functionality was only offered as an independent Microsoft Windows service. Now that it has been integrated into the Pro Cloud Server, users only need to install, configure and maintain one Microsoft Windows Service for all their Enterprise Architect needs.

# **Install and Config**

The Sparx Systems Pro Cloud Server product is installed using a standard Microsoft Windows Installer package that includes a number of components. The Floating License Server is included in the main 'Pro Cloud Services' component. It is possible to change the install location of the Pro Cloud Server; however this document assumes the default install location of C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\ (assuming a 64 bit machine is being used).

**Important:** All communications to the Pro Cloud's Floating License Server are performed via HTTPS, therefore to use the Pro Cloud Server's Floating License Server functionality at least one Port has to be configured to use the HTTPS protocol and a valid certificate/private key file is defined in the Pro Cloud Server's Services folder. See the *Self-Signed Certificate using OpenSSL* section in <u>Port Configuration</u> for more details.

The main Pro Cloud Server's configuration file (SSCloudService.config) defines two settings related to the Floating License Server, FLOATLIC\_PATH and FLOATLIC\_CONFIG.

The FLOATLIC\_PATH option defines the path and file name of the Key Store file; by default this is:

%SERVICE\_PATH%\sskeys.dat where "%SERVICE PATH%" is replaced with the physical

path of the 'Services' folder (that is, 'C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service').

The FLOATLIC\_CONFIG option defines the path and file name of the Key Store group file; by default this is:

%SERVICE\_PATH%\ssflsgroup.config

# Floating License Server Group Configuration File

The Pro Cloud Server's Floating License Server component installs a configuration file called ssflsgroup.config into the Service folder (C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\ssflsgroup.config). This files defines 'groups' of users that can obtain Licenses from the Floating License Server, and also controls which Enterprise Architect Product Licenses each group can utilize.

A group is identified by a group name and a set of credentials (user ID and password) which will be used to securely communicate to the Floating License Server over HTTPS.

The Floating License Server's configuration file will typically consists of multiple group definitions, each group definition needs to be defined as shown:

#### **GROUP**

Name=human\_resources
UserName={user name}

Password={password}

IsManager=false

**ENTITLEMENT** 

Product=UltimateSuite

Academic=false

Limit=10

**END ENTITLEMENT** 

**ENTITLEMENT** 

•

**END ENTITLEMENT** 

**END GROUP** 

#### **Group Definition Properties**

A Group definition begins when the token **GROUP** is encountered on a new line, and extends until the token **END GROUP** is found on a new line.

Property	Description
Name	The common name of the Floating License group.
UserName	Required. Specifies the User ID for the Floating License Group.

Password	Required. Specifies the Password for the Floating License Group.
StartDate	Optional. Used in combination with the EndDate property to define the date range that the Group can be used.
EndDate	Optional. Used in combination with the StartDate property to define the date range that the Group can be used.
Entitlement - Section	Each Group can define multiple Entitlements. An Entitlement definition begins when the token ENTITLEMENT is encountered on a new line, and extends until the token END ENTITLEMENT is found on a new line.  Each Entitlement definition accepts each of these sub-properties:  Product={Product Code} - The product that this entitlement gives grants access to this group.  Academic={true or false} - Determines if this entitlement applies to the academic edition of the specified Product.  Limit={number} - Optionally restrict the number of Product keys available to this group.

	The valid Product codes are:
	<ul> <li>Professional</li> </ul>
	<ul> <li>Corporate</li> </ul>
	<ul> <li>UnifiedSuite</li> </ul>
	<ul> <li>UltimateSuite</li> </ul>
	• BPSimExecution
	• EclipseIntegration
	• MDGCodeAnalysis
	• MDGDDS
	• MDGDoors
	<ul> <li>MDGLinkEclipse</li> </ul>
	• MDGLinkVS
	• MDGRealTime
	• MDGSysML
	• MDGTogaf
	• MDGTogar • MDGUPDM
	<ul> <li>MDGZachman</li> </ul>
	<ul> <li>OfficeIntegration</li> </ul>
	• RaQuest
	<ul> <li>TCSEIntegration</li> </ul>
	• TCSESuite
	<ul><li>VSIntegration</li></ul>
	• V SIIICGIANON
IsManager	Optional. Specifies whether members of
	this group are permitted to perform

management operations (such as add/remove keys) on the keystore.  Default Value: false	
--	--

### **Configuration Changes**


Changes to the Pro Cloud Server's Floating License Group file can be made while the Pro Cloud Server is running, without the need to restart it. The Floating License Server component will detects the last modified time, if the configuration file has changed since it was last read the entire contents of the file is re-read.

#### **User Guide**

This topic (the Floating License Server User Guide) mainly describes how to use the Floating License Configuration Client, a purpose written application which allows environments that use Enterprise Architect to easily manage their floating licenses.

# Floating License Configuration Client

Administration of License keys that are stored in the Pro Cloud Server's Floating License Server are managed by a Windows application installed in the Client folder (C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Client\SSFloatLicClient.exe).



When the Floating License Configuration Client application is first started it will attempt to open a connection to the most recent Floating License Server or KeyStore, if this is the first time running the Configuration Client, you will be automatically prompted for the connection details of a Floating License Server. See <u>Floating License Server</u>

Connections for more details

The Floating License Configuration Client application is capable of performing actions that can be broadly classified into two different areas. Floating License Server based actions and Key based actions.

The Floating License Configuration Client is capable of connecting and administering multiple Floating License Servers and Shared KeyStores at any given time. The 'Floating License Servers/ Key Stores' list (in the upper left) will display each store that the Configuration Client has a connection to.

Floating License Server based Actions

Floating License Server Connections

Set Shared Key Lease Periods

Migrate Shared Keys between Stores

Selecting a connected store from the 'Key Store' list will enable the user to maintain the keys assigned to that store, using these functions:

**Key based Actions** 

**Add Shared Keys** 

Release Shared Keys

**Delete Shared Keys** 


# **Floating License Server Connections**

The top left corner of the 'Floating License Configuration Client' screen displays a list of connected Floating License Servers and Shared Keystores. Each entry in the list can be one of three different types of store:

- 1. Floating License Server based (prefix: https://)
- 2. Shared KeyStore or network based (prefix: ssks://)
- 3. File based

The type of store can be determined by the connection's prefix (or lack of it); the network and file based keystore types are historical, from earlier versions of the Floating License Server.

Floating License Server actions can be performed by selecting a Floating License Server/KeyStore item in the list and then selecting a menu item from the 'File' menu, or simply right-clicking on an item in the list; the menu options shown are:




#### Create...

Selecting the Create... menu option allows for the creation of a new file based keystore.

#### Link to...

Selecting the Link to... menu option will prompt the user for the connection details of a Floating License Server (or key store) to be added to the list of connected stores.



#### **Unlink**

Selecting the Unlink menu option while a Floating License Server is selected in the list will release the Floating License Configuration Client's connection to the store and remove it from the list.

#### **Delete**

Selecting the Delete menu option while a file base Key Store is selected in the Key Store list will physical and permanently delete the file used to store the keys. This option is disabled when the selected Keystore is either a Floating License Server or shared network KeyStore.

#### Migrate to...

Selecting the Migrate to... menu option while a file base Key Store is selected in the Floating License Server / Key Store list will allow the migration of keys from one store to another. This option is disabled when the selected store is either a Floating License Server or shared network KeyStore based. See Migrate Shared Keys between Stores section for more details

#### Options...


Selecting the Options... menu option will display the Options screen for the selected Floating License Server. See Set Shared Key Lease Periods section for more details

# **Set Shared Key Lease Periods**

Normally in an environment that requires licenses to be shared, an Enterprise Architect user 'releases' the license they have 'leased' immediate upon closing the application. However in an environment where Enterprise Architect users work offline for periods of time (for example, using laptops) this type of configuration would not allow an offline user to open Enterprise Architect once they have disconnected from the main network.

For this reason a Floating License Server / Key Store can be configured to have a longer retention period and the 'auto check on exit' option can be disabled.

To administer the lease period of a Floating License Server / Key Store, select a store from the list and then select the 'Tools | Options' menu option. The 'Keystore Options' dialog is then shown.




(Alternatively, you can right-click on the Floating License Server / Key Store name in the list and select the 'Options...' context menu item)


# Migrate Shared Keys between Stores

You might want to upgrade from a legacy file or network based Key Store to a new Pro Cloud Server Floating License Server. This process effectively removes all keys from the original keystore, leaving it empty, and places the keys into the Floating License Server.

To migrate shared keys from other keystores, you will first need to define a connection to each source keystore, using the File | Link To menu item. Then making sure the source keystore is selected in the list, select menu item File | Migrate to...




The 'Migrate Keystore File' screen will be shown:




Click on the [ ... ] button on the right of the Destination field, and browse for the details of the Floating License Server into which the shared keys are to be transferred. Click on the OK button to migrate the shared keys from the source to the destination Floating License Server.

# **Add Shared Keys**

To add shared keys to a Key Store, select the 'Floating License Server / Key Store' in the list, and then select 'Key | Add...' from the main menu.



Alternatively, right-click on 'Keys contained in this store' list and select 'Add...'.




# **Release Shared Keys**

It is usually not necessary to manually release a shared key from a workstation, as this happens automatically if:


- The keystore's AutoCheckin option has been enabled and you close all running instances of Enterprise Architect on your workstation
- The lease on the key expires.

However, if further users want to access Enterprise Architect and there is some technical anomaly that has prevented the return of a key, you can manually release the key using the Sparx Systems Floating License Configuration Client.

To release a key from its active association with a particular workstation, click on the key in the 'Keys contained in this store' list, and then select the Key | Release menu item.




(Alternatively, click on the Release Key icon in the toolbar, or right-click on the key and select the Release context menu option.)




# **Delete Shared Keys**

To delete a key from the selected Floating License Server / Key Store, open the Floating License Configuration Client, click on the key in the 'Keys contained in this store' list, and then select the Key | Delete menu option.



(Alternatively, click on the Delete Key icon in the toolbar, or right-click on the key and select the Delete context menu option.)



# **Troubleshooting**

If users experience a problem with the Pro Cloud Server's Floating License Server the error message will either be displayed on the screen for Floating License Configuration Client related errors or written to the Pro Cloud Server's log file when an error occurs within the Pro Cloud Server. This topic provides a list of common Floating License related errors that could occur. Each entry describes the situation that has occurred and provides guidance on how to correct the error.

# Configuration related Floating License Server errors

Issue	Comments
EA Users are not able to connect to a Floating License Group	<ul> <li>Enterprise Architect users cannot connect to a defined Floating License Group, even when the entered details exactly match the definition.</li> <li>Possible reasons:</li> <li>The Pro Cloud Server configuration file does not contain a valid PCS license key, therefore all Pro Cloud features will be disabled.</li> <li>If an entitlement in the Floating</li> </ul>

	License Group file is defined with an invalid Enterprise Architect product, the entire Group will be disabled. Check the Pro Cloud Server's log file for error messages, the invalid product will be mentioned by name and line number.
The Key Store connection screen in EA does not include HTTPS option	<ul> <li>In order for Enterprise Architect to connect to the Pro Cloud Server's Key Store, a protocol of HTTPS is required for secure communications.</li> <li>Possible reasons:</li> <li>A version prior to Enterprise Architect version 14 is in use</li> </ul>
The Key Store connection screen in EA cannot perform a successful 'Test'	<ul> <li>Your client is not able to communicate with a Pro Cloud Server using the supplied details.</li> <li>Possible reasons:</li> <li>Pro Cloud Server is not installed</li> <li>Pro Cloud Server is not running</li> <li>Pro Cloud Server is not listening on the expected port using HTTPS</li> <li>There is not network connectivity between the client and server</li> <li>A firewall is limiting communications</li> </ul>

between the client and server	
between the enemi and server	

# **Errors while using Floating License Configuration Client**

Issue	Comments
Could not open keystore at [FilePath]. The file does not exist and could not be created	The service was unable to open the key store file specified by the FLOATLIC_PATH property in the Pro Cloud Server configuration file (SSProCloud.config).  Ensure that this path exists, and that the user account the Pro Cloud Server Windows Service is running under has the necessary permissions to read and write to the specified file.
The Floating License Configuratio n Client is not able to connect	The machine running the Floating License Configuration Client is not able to communicate with a Floating License Server using the supplied details.  Possible reasons:  Pro Cloud Server is not installed Pro Cloud Server is not running

• Pro Cloud Server is not listening on the expected port using HTTPS There is no network connectivity between the client and server A firewall is limiting communications between the client and server The Pro Cloud Server configuration file does not contain a valid PCS license key, therefore all Pro Cloud features are disabled, including the Floating License Server The entered user credentials do not match any of the defined Floating License Groups in 'ssflsgroup.config' The user credentials for the entered Floating License Group have not been defined as 'IsManager=true' If an entitlement in the Floating License group file is defined with an invalid Enterprise Architect product, the entire Group will be disabled; check the Pro Cloud Server's log file for error messages - the invalid product will be mentioned by name and line number Could not No file path was specified in the property in the configuration file. open keystore, no

keystore file specified	Type a file path into the FLOATLIC_PATH configuration property that the user account the Pro Cloud Server Windows Service is running under can read and write to.
Invalid or missing keystore file - Keystore file cannot be opened by this version of the service or the file has been corrupted	The keystore file specified by the configuration property FLOATLIC_PATH is either incompatible with the current version of the Floating License Server, or has somehow been corrupted on the file system.  Restore the key store file specified in the configuration property FLOATLIC_PATH from a recent backup, or contact Sparx Systems Support for assistance.
Key file has been moved	The key store file specified by the configuration property FLOATLIC_PATH is locked to the serial number of the hard drive it is created on. If the key store file is moved from this hard drive, then other Floating License Servers are unable to open it. If the key store file has been moved, restore the file to its initial location. Certain RAID configurations can affect

how the hard drive's serial number is presented to the Floating License Server. Thus, it is recommended that you house the key store file on a non RAID drive, wherever possible.

# **Errors while using Enterprise Architect and the Floating License Server**

Issue	Comments
Checkout Failure: There are no more available keys for this product in the key store	Keys for this product exist; however, they are all checked out to other users.  If this error is frequently reported, consider limiting the use of the product across your enterprise or purchasing more keys to meet the demand for the product.
Checkout Failure: The key store does not contain any keys for this	This keystore does not contain keys for the requested product. Keys for the product might have been provided by the keystore in the past, but have since been removed.  Uninstall the product and return any

product	shared keys on the client machine.
Checkin Failure: Key not found in keystore.	The key being checked in has either been deleted since it was checked out, or was checked out from another keystore.  Ensure that users return any shared keys to the key store they were leased from before swapping Floating License Servers / key stores.

# Additional Functionality Using the Cloud

Even without a license, the Pro Cloud Server provides the facility of connecting to models over a secure http connections (HTTPS). It also makes it possible to use these additional facilities on or within your models:

- OSLC Requirements Management
- Reusable Asset Service (RAS)
- Scheduled Tasks

### **OSLC Requirements Management**

OSLC is an initiative to provide easier integration between Requirement Management tools. It uses HTTP to list, add, modify and delete requirements. The service provider definition to direct any OSLC client to is:

col>://<server>:<port>/<model\_name>/oslc/sp/

For example, if you were connecting to a server running on your own machine using the default settings, the connection would be:

http://localhost:804/model/oslc/sp/

Note, this is available in even an unlicensed Pro Cloud Server installation. The licensed Pro Cloud Server provides the OSLC RESTful API ("OSLC Architecture Management v2.0") which offers much greater access to data in your Pro Cloud Models.

### Reusable Asset Service (RAS)

The RAS portion of the Cloud Server helps you to define Packages that can be used in any model. When a Package is requested, Enterprise Architect and the Cloud Server will track cross-Package dependencies and make available everything required by that Package.

#### **Scheduled Tasks**

The Cloud Server includes optional support for running time-based updates to data. Currently, this is applied to updating a Time Series chart automatically to provide a dynamic view of how a model is changing over time. You can set different time scales for these updates, such as daily, weekly or monthly.

#### **Notes**

• This facility is available through the Corporate, Unified or Ultimate editions

# **Reuseable Asset Service (RAS)**

Within a large organization, groups of users can be separated by geographical distance be on different networks. This can make it difficult to share common data, standards and modeling structures, without the complexity of using external Version Control tools or manually distributing XMI files between projects. Enterprise Architect has a Reusable Asset Service (RAS) that provides a simple and convenient mechanism for modelers to distribute or download reusable model structures, information, corporate directives and standards. The shared repository is accessible via a Cloud connection, making it accessible for distributed teams. The person who sets up the reusable data can retain governance of the resource or asset, whilst users of the service can easily review the currency of the information and download the latest versions into their models or file folders.

The RAS gives distributed teams convenient access to a single 'source of truth' for shared data, including project milestones, architectural frameworks and industry standards.

#### **Reusable Assets**

Reusable Assets consist of:

- Packages containing elements, diagrams and structures (as drawn from any point within the Browser window), and
- Files in a range of text, code and graphic formats,

including .eap files

An asset can be, for example:

- A common Class library or framework
- A set of common Requirements or Use Cases
- A draft specification document
- Marketing collateral

### **Storage Structure and Use**

Reusable Assets are held in a remote registry, accessed through a Cloud connection. The registry contains any number of Storages, which can either be left unprotected for any user to create, or change-restricted by an Administrator password. Each Storage can contain any number of Asset Packages holding modeling structures, and files containing textual or graphical information and data. When a user creates a Storage, they can protect the contents from being updated in the Registry or downloaded into a model, using password protection defined by that user.

For each Package, the RAS automatically identifies the:

- Version of the Package held in the registry
- Diagrams and elements (including child Package elements) contained by the Asset Package
- Dependencies on parent Packages of any external elements that the Asset Package references
- Dependencies on MDG Technologies

Any user, regardless of password protection, can freely browse and identify the contents of a Package held in a Storage - including displaying the diagrams - without importing the material into a model. A user that has imported an Asset Package into their model can compare their model Package against any version of the Asset Package, to check for and assess any differences between them.

#### **Notes**

• The Reusable Asset Service is available in the Corporate, Unified and Ultimate editions of Enterprise Architect

#### **Connect to the Asset Service**

The Reusable Asset Service provides model structures and documents to you from one or more registries on remote systems. You access these registries through a Cloud connection to the appropriate server. The connection details should be provided to you by your System Administrator or Reusable Asset Service Administrator.

#### **Access**

Ribbon	Publish > Model Exchange > Reusable
	Assets

#### **Connect to Assets**

Option	Detail
Registry	This field normally defaults to the last-used registry name. If the field is empty, or if you want to switch to a different registry, click on the button to the right of the field.

The 'Cloud Connection' dialog displays. Using the information provided by your administrator, type in the server name, URL and the name of the model hosting the registry data. For example, if you wanted to download the UBL Frameworks into your model, you would specify the server 'sparxcloud.com' and the model name 'modelpatterns'. If advised by your Administrator, type in the user name and password for the server.

Click on the OK button; the 'Registry' field now shows the server name.

#### Storage

If there is more than one Storage available in the Registry, this field defaults to the first listed in the Registry. To check for or select other Storages, click on the drop-down arrow at the right of the field. Click on the Storage to review. For example, if you were downloading UBL frameworks, you would select 'UBL' in the list.

The 'Registry Browser' tab displays the Packages registered in the selected Storage.

• The Reusable Asset Service is available in the Corporate, Unified and Ultimate editions of Enterprise Architect

#### **Browse Assets**

When you select a Storage in the Reusable Asset Service, the 'Registry Browser' tab immediately displays a list of the Packages registered in that Storage. You can review and use these Packages using the context menu and buttons on the tab.

You can review the properties and contents of the selected Package in the Storage, and access any files in the Storage, using the tabs in the lower half of the Reusable Asset Service view, underneath the 'Registry Browser' tab.

If you have left the Registry Browser open for a while and there is a possibility that the Registry has been changed, you can click on the icon in the Reusable Asset Service toolbar to refresh the Browser with the latest contents of the Registry.

#### **Access**

Ribbon	Publish > Model Exchange > Reusable
	Assets > Registry Browser

#### **Review Assets**

Option	Detail
Toggle Filter Bar	Right-click on the column headings and select this option to show or hide the Filter Bar on the display.
<filter bar="" fields=""></filter>	Type in the appropriate characters to list only Packages that have that string of characters in the values in the corresponding column.
Package	This column shows the name of the Packages held in the selected Storage.
Version	This column defaults to the most recent version of each Package held in the selected Storage.
	You can click on the drop-down arrow at the end of a field and select a different version of the corresponding Package, if any have been registered.
Last Registered	This column shows the date and time at which the currently-listed version of each Package was registered.
Registered	This column shows the user name of the person who registered the currently-listed

By	version of each Package.
Import	Click on a Package name and click on this button to begin to import either the Package alone or the Package and its dependent structures into your model. You can perform the same action by right-clicking on the Package name and selecting the 'Import from Registry' menu option.  If the Package from the Registry already exists in your model, it is deleted and replaced by this import.  For a:
	<ul> <li>'Learning Center Library' Storage, the 'Download Library' dialog displays</li> <li>'Reference Data Library' Storage, the 'Import Reference Data' dialog displays</li> <li>'Source Code Library' Storage, the 'Save As' dialog displays</li> </ul>
Compare with Package in Model	If you have previously imported a Package from the Registry into your model, you can right-click on the Package name in the Registry Browser and select this option to compare the imported Package with the Registry version, and show any differences.

	The system automatically selects the model Package from the Browser window.
Find in Project Browser	If you have previously imported a Package from the Registry into your model, you can right-click on the Package name in the Registry Browser and select this option to highlight the corresponding Package in the Browser window.

- Some of the other options available on the Registry Browser are used to set up assets in the Registry
- If the Storage is password-protected, a prompt for you to enter a password displays when you select to perform an operation on the data; in this situation, you need the 'Read-only' password to process the information from the Storage, and the 'All-access' password to change the information in the Storage
- The 'Registry Browser' tab will be empty for a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage the contents of these Storages will be available in the 'Storage Files' tab of the Reusable

#### Asset Service view

### **Asset Properties**

When you select a Storage and a Package in the Registry Browser, the first four tabs in the lower half of the Reusable Asset Service view are updated with information from the Package. The 'Asset Properties' tab is a read-only view of the properties of the selected Package itself.

#### **Access**

Open the Reusable Asset Service window using one of the methods outlined here.

Select a Package, then click on the 'Asset Properties' tab to display properties for that Package.

Ribbon	Publish > Model Exchange > Reusable
	Assets

### **Review Package Properties**

Field	Detail
Package	Displays the name of the selected Package.

GUID	Displays the Global Unique Identifier of the Package.
Version	Displays the version reference (such as 1.1 or Beta) of the Package.
Author	Displays the user ID of the person who created the Package (the Package Author).
Created Date	Displays the date and time at which the selected version of the Package was created (that is, registered) in the Registry.
Modified Date	Displays the date and time at which the selected version of the Package was last modified (that is, re-registered) in the Registry.
Comments	Displays any comment recorded against the Package when it was registered in the Storage.
Notes	Displays the notes recorded against the Package when it was registered in the Storage.

• The 'Asset Properties' tab will be empty for a 'Learning Center Library', 'Reference Data Library' and 'Source Code Library' type Storage

### **Package Contents**

When you select a Storage and a Package in the 'Registry Browser', the first four tabs in the lower half of the Reusable Asset Service view are updated with information from the Package. The 'Contents' tab lists the diagrams and elements (including child Packages) held in the selected Package, listing the two types of object separately. You can organize the information within a column into alphabetical or reverse-alphabetical order for ease of reference, and use the Filter bar to filter the display to show only items with values containing specific characters or digits.

#### **Access**

Open the Reusable Asset Service window using one of the methods outlined here.

Select a Package, then click on the 'Contents' tab, to display the contents of that Package.

511	
Ribbon	Publish > Model Exchange > Reusable
	Assets

### **Review Package Contents**

Option	Detail
Content Type	Click on this button to toggle between listing the Package diagrams first and listing the Package elements first.
Toggle Filter Bar	Right-click on the column headings and select this option to show or hide the Filter Bar on the display.
<filter bar="" fields=""></filter>	Type in the appropriate characters to list only elements and diagrams that have that string of characters in the values in the corresponding column.
Content Type: Diagram Content Type: Element	These are the headers for the two types of object listed in this tab.  Click on the appropriate expansion box to hide or show the list of diagrams or elements under the heading.
Name	Displays the name of the element or diagram available in the Package.
Type	Displays the type of the element or diagram, such as UseCase or Use Case diagram.

GUID	Displays the Global Unique Identifier of the element or diagram.
Content Type	Displays the object type of the item - Element or Diagram.
Find in Project Browser	Right-click on an element or diagram line and select this option to see if the element or diagram also exists in your model and, if it does, to highlight it in the Browser window.
View Diagram	Right-click on a diagram name and select this option to display the diagram within a labeled frame, as an image.  Alternatively, double-click on the diagram name.

• The 'Contents' tab will be empty for a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage

### **Package Dependencies**

A Package held as an asset in the Reusable Asset Service registry might contain elements and diagrams that have relationships with objects in other Packages. The Packages containing these 'external' objects will also have been added to the Registry to support the first Package, and will be listed in the 'Registry Browser' tab along with other (unrelated) Packages. You can establish whether the selected Package in the Registry Browser has links to other Packages in the Registry, and which they are, by reviewing the 'Dependency' tab.

Package A depends on Package B if any of these constructs (or their Tagged Values) in Package A references elements in Package B:

- Elements
- Attributes
- Operations
- Operation Parameters
- Diagrams
- Connectors

#### Access

Open the Reusable Asset Service window using one of the methods outlined here.

Select a Package, then click on the 'Dependency' tab, to display a list of Dependencies for that Package.

Ribbon	Publish > Model Exchange > Reusable
	Assets
	1 200 0 00

### **Check Package Dependencies**

Option	Detail
Package	Displays the name of the related Package.
Version	Displays the latest registered version of the related Package that has links to the selected Package.
GUID	Displays the Global Unique Identifier of the related Package.
Find in Project Browser	Right-click on the 'Package' line and select this option to see if the Package also exists in your model and, if it does, to highlight it in the Browser window.

- If one Package depends on another, and that second Package itself depends on another Package, both the second and third Packages are shown in the 'Dependency' tab
- The 'Dependency' tab will be empty for a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage

### **Package Technologies**

It is possible that the asset Package in the Registry is associated with one or more Technologies, especially if the Package comes from a model developed as an extension or customization of the UML. You can check whether an asset Package has any associated Technologies, and what they are, by viewing the 'Technology' tab of the Reusable Asset Service view.

#### **Access**

Open the Reusable Asset Service window using one of the methods outlined here.

Select a Package, then click on the 'Technology' tab, to display a list of Technologies required to support that Package.

Ribbon	Publish > Model Exchange > Reusable Assets
--------	--

### **Review Technologies**

Option	Detail
--------	--------

Name	Displays the name of the Technology as
Version	Displays the required version of the Technology to support the asset Package, available through the Registry.
ID	Displays the unique identifier of the Technology.
Type	Identifies whether the Technology is system-supplied and built in to Enterprise Architect (such as BPMN 2.0 or ArcGIS), or user-defined.  A user-defined technology can be introduced from an external source or developed by a user within the system.
Registry Status	<ul> <li>Indicates whether the Technology file is:</li> <li>Available - the Technology file is registered in the current Storage, or</li> <li>Unavailable: <ul> <li>The Technology file is not registered in the Storage, or</li> <li>The Technology is a built-in Technology and is already integrated with your system, or must be purchased under license, or</li> </ul> </li> </ul>

	- The Technology is available from a URL and can be downloaded from that URL
Import Technology	<ul> <li>If your local system does not have one of the Available Technologies, you can quickly import it from the Registry.</li> <li>1. Right-click on the Technology name and select the 'Import Technology' option.</li> <li>2. A prompt displays for you to confirm the import to your system; click on the Yes button.</li> <li>3. A message displays to confirm that the Technology has been imported; click on the OK button.</li> </ul>
	You might have to restart Enterprise Architect to activate the Technology.  Other than the remote Technologies, you cannot import a Technology flagged as 'Unavailable'. You can import a remote Technology from its URL site.

- You can also import Available Technologies from the registry as part of the process of importing the asset Package
- If the Storage is password protected, a prompt to enter your password displays (this can be a Read-Only or a Complete Access password) after you confirm that you want to import the Technology; you cannot import the Technology without this password
- The 'Technology' tab will be empty for a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage

### **Storage Files**

The 'Storage Files' tab of the Reusable Asset Service view simply lists the files that have been uploaded to the specified Storage. The files can be of any type, uploaded from any directory on any system connected to the registry. Typically they would be document or graphics files that provide standards, guidelines or design information on a model structure. The tab displays the file name and extension, and a comment on the nature or purpose of the file.

Files held in the Registry are compressed, so to view the contents you download them onto your local system.

#### **Access**

Open the Reusable Asset Service window using one of the methods outlined here.

Select a Package, then click on the 'Storage Files' tab to display a list of files associated with the Package, that are available for download.

Ribbon	Publish > Model Exchange > Reusable	
	Assets	

### Review files in Draft/Complete type Storage

On the 'Storage Files' tab, check the 'Comments' field against each file that interests you.

To view the contents of a file, right-click on the file name and select the 'Import From Registry' option. The 'Save As' browser displays, through which you select the directory into which to copy the file.

Click on the Open button. The file is copied into the selected location, from which you can open it.

# Review files in Learning Center/Reference Data/Source Code Library type Storage

On the 'Storage Files' tab, check the 'Comments' field against each file that interests you.

To import and install a Library file, right-click on the file name and select the 'Import From Registry' option. One of these dialogs will display:

- 'Download Libraries' dialog for a 'Learning Center' type Storage
- 'Import Reference Data' dialog for a 'Reference Data Library' type Storage
- 'Save As' dialog for a 'Source Code Library' type Storage

'Learning Center Library', 'Reference Data Library' and 'Source Code Library' type Storages do not contain any

Assets. Therefore, clicking on the:

- 'Import' button in the Registry Browser will import and install a Library file from the Storage
- 'Delete' button in the Registry Browser will delete all Library files in the Storage

#### **Notes**

• If the Storage is password-protected, the system prompts you to enter a password before you begin importing a file from the Storage; in this case you require either a 'Read-Only' or a 'Complete Access' password

### Compare an Asset to the Model

If you are developing a Package in your model against a standard structure, or using common elements from the Reusable Asset Service, you can check that your model conforms to the standard or incorporates any changes to the common elements, by performing a comparison between the asset Package and your model.

#### **Access**

Open the Reusable Asset Service window using one of the methods outlined here.

Select a Package, then right-click on the Package and choose 'Compare with Package in Model'.

Ribbon	Publish > Model Exchange > Reusable Assets
--------	--

### **Compare Asset Package and Model**

A prompt displays for you to confirm the comparison. Click on the Yes button.

The Baseline Comparison view displays, showing the

element hierarchy in which differences have been detected between the Package in the model and the asset Package in the Registry (as the Baseline).

All facilities of the standard Baseline Comparison are available, including the ability to 'roll back' differences so that the element or Package in the model matches the Registry.

#### **Notes**

• If the Storage is password-protected, the system prompts you to enter a password before you begin comparing information in the Storage and in the model; in this case you require either a Read-Only or a Complete Access password

### Import an Asset into the Model

The Reusable Asset Service provides common or standard information and data that you can import into your local model. The unit that you import is a selected version of the Asset Package; you can also, optionally, import:

- Other Packages on which the selected Asset Package depends, and/or
- Available Technologies that support full use of the model structures in the Asset Package

The Asset Package (with, if selected, any needed Packages) is imported into the currently-selected model Package in the Browser window, unless the Asset Package already exists anywhere else in the Project. In this case, the system locates the existing Package and overwrites it with the imported Asset Package.

#### Access

Open the Reusable Asset Service window, using one of the methods outlined here.

On the 'Registry Browser' tab, either;

- Select an Asset Package and click on the Import button, or
- Right-click on an Asset Package and select the 'Import from Registry' option

D 1.1'.1 > M. 1.1 F .1 > D1.1.
Publish > Model Exchange > Reusable

Ribbon
--------

### **Import Asset Package**

Before selecting an Asset Package to import into your model, click on the 'Version' drop-down arrow and select the appropriate version of the Package to import.

When you select to import an Asset Package into your model, a short menu displays from which you select to import:

- The Package alone or
- The Package with the related Packages on which it is dependent

A prompt then displays for you to confirm the import, and to warn you that if the Package already exists in the model, it will be overwritten by the import. Click on the Yes button to continue, or the No button to cancel the import.

If the Storage is password protected, after you confirm the import a prompt displays for your 'Read-Only' or 'Complete-Access' password; enter this and click on the OK button.

The 'Import from Registry' dialog displays, followed by confirmation that the import of the Package or Packages is complete. Click on the OK button.

### If the Package depends on Technologies

If the Technologies associated with an Asset Package are not already on your system and/or enabled in your model, during the display of the 'Import from Registry' dialog the 'Import Technology From Registry' dialog also displays. Process this dialog as described.

Option	Detail
Name	Displays the name of the Technology as recorded in the Registry.  The checkbox against each name is selected by default. If you want to import one technology but not another, deselect the checkbox of the technology to ignore.
Version	Displays the required version of the Technology to support the Asset Package, available through the Registry.
Registry Status	<ul> <li>Indicates whether the Technology file is:</li> <li>Available - the Technology file is registered in the current Storage, or</li> <li>Unavailable - for one of these reasons: <ul> <li>The Technology file is not registered in the Storage, or</li> <li>The Technology is a built-in</li> </ul> </li> </ul>

	Technology and is already integrated with your system, or must be purchased under license, or - The Technology is available from a URL and can be downloaded from that URL
Model Status	Indicates whether the Technology is already in your model and disabled.  (If the Technology is in your model and enabled, there is no need to import it and it is not listed in the dialog.)
OK	Click on this button to import and/or enable the selected Technology or Technologies in your system.  A status message displays to indicate that the Package and Technologies have been imported and the Technologies enabled. You might have to restart Enterprise Architect for the Technologies to take full effect.  Click on the OK button to clear the message.  In the Browser window, the Package has been added to the model with (if selected) the Packages on which it is dependent.

### **Import Library**

The Reusable Asset Service provides the ability to store Library files that you can import into your local model. The type of Library file available in a Storage will depend on the Storage type. When you import and install a Library from a:

- Learning Center Library storage, it will be available for use on all Enterprise Architect models in this system
- Reference Data Library storage, it will be installed into the current model
- Source Code Library storage, it will be saved in the specified location in the file system

## Library from a Learning Center Library storage. Either:

- Click on the Import button to open the 'Download Libraries' dialog, showing all the Library files in this storage as selected, or
- Right-click on a Library file in the 'Storage Files' tab and select the 'Import from Registry' option to open the 'Download Libraries' dialog showing that specific Library file as selected

#### Library from a Reference Data Library storage. Either:

• Click on the Import button to open the 'Import Reference Data' dialog, showing all the reference data in that Library file as selected, or

• Right-click on a Library file in the 'Storage Files' tab and select the 'Import from Registry' option to open the 'Import Reference Data' dialog, showing all the reference data in that Library file as selected

#### Library from a Source Code Library storage. Either:

- Click on the Import button to open the 'Save As' dialog and select a location in the file system to save the imported Library to, or
- Right-click on a Library file in the 'Storage Files' tab and select the 'Import from Registry' option to open the 'Save As' dialog, then select a location in the file system to save the imported Library to

If the Storage is password protected, a prompt for you to enter your 'Read-Only or 'Complete-Access' password displays. Enter the password and click on the OK button.

#### **Notes**

- You can also import Technologies separately from the Package that is dependent on them, using the 'Technology' tab of the Reusable Asset Service view
- 'Learning Center Library', 'Reference Data Library' and 'Source Code Library' type Storages do not contain any Asset Packages

### **Set Up Registry Password**

As a System Administrator, you can password-protect the Registry server to prevent users from modifying the Registry; that is, restrict users from creating, modifying and deleting Storages. Once you have set password protection, only those users who have a valid Administrator password can modify the Registry.

You can also change the password at regular intervals, for added security.

#### **Access**

Ribbon	Publish > Model Exchange > Reusable
	Assets: Set Administrator Password

#### **Set the Administrator Password**

il
bled if no password exists for the istry server. e server has a current password, type

	it in to this field.
New password	Type in the new Administrator password.
Retype new	Type in the new Administrator password, for confirmation.
OK	Click on this button to set the password and close the dialog.
Cancel	Click on this button to abort the changes and close the dialog.

- To remove password protection from the Registry server, complete the 'Enter old password' field but leave the 'New password' and 'Retype new' fields blank
- If a Storage has a Complete Access password, then you can use either the Administrator password or the Complete Access password to modify the Storage

### **Set Up the Asset Service**

The process of setting up assets and files in the Reusable Asset Service has a number of simple stages, typically:

- Identify the Registry
- Create the Storages, including copying an existing Storage as a template for a new one
- Set password protection on each Storage
- Register the Asset Packages and Storage Files, and update them as necessary

#### **Access**

Ribbon Publish > Model Exchange > Reusal Assets	ole
---	-----

### **Identify Registry**

The Registry server holds the Storages of the Reusable Asset Service. It will have been previously configured by your system administrator, to be accessed through a Cloud Connection. Your system administrator will provide the connection details for you to use.

In the Reusable Asset Service view, click on the button to the right of the 'Registry' field. The 'Cloud Connection' dialog displays.

Using the information provided by your administrator, type in the server name, URL and the name of the model hosting the registry data. If advised by your administrator, also type in the user name and password for the server.

Click on the OK button; the 'Registry' field now shows the server name.

## **Create Storages**

A Storage is a container within the Registry, holding related assets and files. There can be several Storages in the Registry, to support the different areas of work or purposes that your organization might define.

Ste	Action
p	
1	Click on the icon in the Reusable Asset Service toolbar.
2	If necessary, enter the Administration password that enables update access to the Registry. Click on the OK button.  The 'New Storage' dialog displays.

- In the 'Name' field, type a name that indicates the purpose or content of the Storage.
- 4 In the 'Type' field, select:
  - 'Draft' if you intend to make significant changes to the content of the Storage, such as populating it with assets and/or files; you can overwrite existing Packages or files in a Draft Storage
  - 'Complete' if the Storage is ready for use; you cannot overwrite any Packages or files in a Complete Storage, although you can delete Packages and files and add new ones
  - 'Learning Center Library' if the Storage should contain only Enterprise Architect Learning Center Library files this Storage type can be populated only with Library files and not with Asset Packages; you can overwrite existing Library files in a Learning Center Library storage
  - 'Reference Data Library' if the Storage should contain only Enterprise Architect Reference Data Library files this Storage type can be populated only with Library files and not with Asset Packages; you can overwrite existing Library files in a Reference Data Library storage
  - 'Source Code Library' if the Storage should contain only Source Code Library files this Storage type can be populated only with Library files and not with Asset Packages; you can overwrite existing Library files in a Source Code

	Library storage
	You can modify a Storage at a later time, and change this Type setting.
5	If you want to set Storage Access Passwords on this Storage, click on the checkbox against one or both password types, and provide and confirm the 'Complete Access' and/or 'Read-Only Access' passwords.
6	Click on the OK button.  A prompt displays for you to confirm the creation of the Storage, with the type of access you have set on the Storage.
7	Click on the Yes button.  A confirmation message displays; click on the OK button.  The name of the new Storage displays in the 'Storage' field.

#### **Password Protection**

The Registry can be protected by a Registry password, so that only the Administrator can create and modify Storages. If no Registry password is set, a second level of password protection can be applied.

The owner of a Storage can apply password protection to restrict users in processing and modifying the contents of the Storage either intentionally or unintentionally. Password protection can be applied at two levels:

- Complete Access users enter their password and can modify or delete the Storage itself, and within the Storage can register, update and delete Packages and files in the Registry, view Packages and import assets into their models
- Read-Only Access users enter their password and can import assets into their models

You set the 'Complete Access' password before you set the 'Read-Only Access' password.

If password protection is set and a user has no password, they can only view the contents of the Storage. If no password protection is set, all users can freely access and modify the Storage and its contents.

You set the passwords on each Storage as you create that Storage, using the 'New Storage' dialog. Once the Storage has been created, you can change or remove an existing password using the 'Modify Storage Access' dialog, but you cannot add a password.

If a Storage is password protected, the system displays a prompt for the password when the user begins to:

- Change or delete a password on the Storage
- Copy the Storage to create a new Storage
- Delete the Storage

- Register a Package or file in the Storage
- Import a Package, file or Technology from the Storage
- Delete a Package or file from the Storage
- Compare an Asset Package with a Package in the model The system displays the password prompt when any of those operations is performed for the first time after the user:
- Connects to a Registry
- Reloads the Registry Browser
- Selects a Storage in the 'Storage' field in the Reusable Asset Services view

If the user enters the correct password and therefore establishes their credentials, the system does not display a password prompt again for any valid operation that user performs until they:

- Select a different Storage in the 'Storage' field in the Reusable Asset Services view or
- Reload the Registry Browser from the Registry

## **Register Assets and Files**

Whilst a Storage exists and, if the Storage is under password protection, you have the 'Complete Access' password, you can register Packages from a model and files from your system as assets in that Storage. If the Asset Package was developed using one or more MDG Technologies, you can optionally register those technologies in the Storage as well.

See the Register New Assets Help topic.

#### **Copy Storages**

It is possible to copy a Storage as the basis for creating another Storage, for example if you want to use the same set of assets in the context of larger set for a different department, work area or development phase.

Note: It is not possible to change the Type of a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage, nor is it possible to change a 'Draft' or 'Complete' type Storage into a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage.

Action
In the 'Storage' field, select the Storage to be copied.
Click on the icon in the Reusable Asset Service toolbar.
If necessary, enter the Administrator password or your 'Complete Access' password and click on the OK button. The 'Save Storage As' dialog displays.

4	In the 'Name' field, type a name that indicates the purpose or content of the new Storage.
5	<ul> <li>In the Type field, select:</li> <li>'Draft' if you intend to make significant changes to the content of the Storage, such as populating it with assets and/or files; you can overwrite existing Packages or files in a 'Draft' Storage</li> <li>'Complete' if the Storage is ready for use; you cannot overwrite any Packages or files in a 'Complete' Storage, although you can delete Packages and files and add new ones</li> <li>You can modify a Storage at a later time, and change this setting.</li> </ul>
6	If you want to set Storage Access Passwords on this Storage, click on the checkbox against one or both password types, and provide and confirm the 'Complete Access' and/or 'Read-Only Access' passwords.
7	Click on the OK button.  A prompt displays for you to confirm the creation of the Storage, with the type of access you have set on the Storage.
8	Click on the Yes button. A confirmation message displays; click on the OK

button.

The name of the new Storage displays in the 'Storage' field.

## **Change Storage Details**

After you have set up a Storage, you can update it at a later stage to:

- Change the status or Type
- Change one or both of the existing 'Complete Access' and 'Read-Only' Access passwords
- Delete one or both of the passwords

It is not possible to add a password where one has not previously been set.

You cannot change or delete passwords unless you have the 'Complete Access' password yourself.

Note: It is not possible to change the Type of a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage, nor is it possible to change a 'Draft' or 'Complete' type Storage into a 'Learning Center Library', 'Reference Data Library' or 'Source Code Library' type Storage

Ste	Action
p	

1	On the Reusable Asset Service view, in the 'Storage' field click on the drop-down arrow and select the Storage to update.
2	Click on the icon in the Reusable Asset Service view toolbar.
3	If necessary, enter the Administrator password or your 'Complete Access' password and click on the OK button.  The 'Modify Storage Access' dialog displays.
4	<ul> <li>In the 'Type' field, click on the drop-down arrow and select:</li> <li>'Complete' if the Storage has now been set up and is ready for use; you cannot overwrite any Packages or files in the Storage, although you can delete them and add new Packages and files</li> <li>'Draft' if you intend to make significant changes to the content of the Storage; you can overwrite</li> </ul>
5	<ul> <li>existing Packages or files</li> <li>The 'Action' field defaults to 'None', to indicate no changes to the passwords. If you are changing or deleting the passwords, click on the drop-down field and select:</li> <li>'Change Password' to enable both password type fields ready for editing</li> </ul>

	<ul> <li>'Remove Storage Access Password' to simply delete the 'Complete Access' password altogether</li> <li>'Remove Read-Only Access Password' to simply delete the 'Read-Only Access' password altogether</li> </ul>
6	If you have selected the 'Change Password' option, select the appropriate password checkbox or both checkboxes, and type in the new password(s). Re-type the password(s) in the 'Confirm Password' field(s).
7	Click on the OK button to save your changes and close the 'Modify Storage Access' dialog.

## **Delete a Storage**

If a Storage has been created by mistake, or is no longer necessary in the Registry, you can delete it and its entire contents of Package and files in one action.

Ste	Action
p	
1	On the Reusable Asset Service view, in the 'Storage' field click on the drop-down arrow and select the Storage to delete.

2	Click on the icon in the Reusable Asset Service view toolbar.  A prompt displays to confirm the deletion.
	A prompt displays to commit the detection.
3	Click on the Yes button.  If necessary, enter the Adminstrator password or your 'Complete Access' password and click on the OK button.  A message displays to confirm that the Storage has been deleted.
4	Click on the OK button to clear the message.  The Storage and its contents are cleared from the Registry.

# **Register New Assets**

After you have set up your 'Draft' or 'Complete' Storages in the Reusable Asset Service Registry, you can register assets in them. The assets include:

- Packages of modeling structures of your model, shown in the Browser window; these Packages can include diagrams and subordinate Packages
- Any Packages containing model components on which the primary Asset Packages depend
- Any MDG Technologies that you used in developing the Asset Packages, and that you decide to register with the Packages
- Any text or graphics files you want to make available to your corporate community; these files are compressed before being added to the Storage

You register the first three items together. You can register files in the Storage during that same process, or separately.

You can register separate versions of the same Package. If you register a Package that already exists in the Registry under the same version reference, and the Storage has 'Draft' status, the existing version is overwritten. If you register the same Package with a different version number or reference, it is registered separately and users can access both versions of the Package from the Registry.

'Learning Center Library', 'Reference Data Library' and 'Source Code Library' type Storages cannot contain

Packages of modeling structures - they can contain only Library files, which will appear in the 'Storage Files' tab. A Library file is:

- a zipped file containing Enterprise Architect-specific Learning Center files for the 'Learning Center Library' Storage type
- an XML file containing Enterprise Architect-specific reference data XML files for the 'Reference Data Library' Storage type
- a zipped file containing source code files for the 'Source Code Library' Storage type

Once registered, the Library file will be available in the 'Storage Files' tab of the Reusable Asset Service view.

#### **Access**

Ribbon	Publish > Model Exchange > Reusable Assets
--------	--

## Register Package as Asset

Ste	Action
p	

1	In the Reusable Asset Service view, select the appropriate Registry and Storage.
2	In the Browser window, click on the Package to register as an Asset.
3	On the 'Registry Browser' tab, click on the Register button.  If the Storage is password protected, a prompt displays for your 'Complete Access' password. Type this in and click on the OK button.
4	<ul> <li>The 'Register Package(s)' dialog displays, showing the:</li> <li>Name and type of the Storage</li> <li>Name and status of the selected Package (the status at this point being 'Pending')</li> <li>The name, GUID and current version of the selected Package; you can type a different version number or text string if necessary</li> <li>If there is a version of the Package already in the Registry, and the Storage has 'Draft' status, you can either:</li> <li>Overwrite the registered Package with an update of that version, or</li> <li>Add the updated Package as another Asset under a different version number; in this case, the 'Packages to Register' panel shows the version</li> </ul>

	number, registration date and comments on the latest version of the Asset Package You cannot overwrite an existing Package if the Storage has 'Complete' status. In this case, add the Package under a different version number.
5	In the 'Comments' field type a short comment and, in the 'Notes' field, a longer explanation of the Package being registered.
6	Click on the Check Dependency button and resolve the dependencies of the Package.  At the end of this process, the selected Package has the status 'Ready' (for registration).
7	You can, at this point, also register files as assets of the Storage. See Step 4 of the next table, <i>Register File as Asset</i> .  However, if you prefer you can follow the complete procedure separate from registering Packages.
8	Click on the Register button.  A prompt displays to confirm registering the Package. Click on the Yes button.  If the same version of the selected Package already exists in the Registry (if the Storage is a 'Draft') a prompt displays to confirm overwriting it. Click on the Yes button.

A progress dialog displays. If the Package does not have any associated MDG Technologies, a message displays confirming that Package registration is complete. Go to step 10.

If the Package has one or more associated MDG Technologies, the 'Register MDG Technology' dialog displays, listing the Technologies and prompting you to register (OK) or ignore all of them. If you want to register some Technologies but not others, click on those you do not want to register, and click on the Remove button for each one in turn. Click on the OK button or Ignore button.

A message displays confirming that Package and Technology registration is complete.

#### Notes:

- If a remote Technology is removed from registration (that is, the Technology is not registered along with the Package), the registered Package will refer to this Technology at its URL When importing the Package from Registry, the system will import this remote Technology from its URL (if the remote Technology is not already available in the importing model)
- If a remote Technology is registered with the Package being registered, the system will store a copy of the Technology file in the Registry When importing the Package from Registry, the system will import the Technology stored in the

	Registry and will not import it from its URL (if the remote Technology is not already available in the importing model)
10	Click on the OK button.  The 'Registry Browser' tab is updated with the newly-added details of the Package and any dependent Packages. You can review the details on the tabs on the lower half of the Reusable Asset Service view.

# **Register File as Asset**

Ste p	Action
1	In the Reusable Asset Service view, select the appropriate Registry and Storage.
2	On the 'Registry Browser' tab, click on the Register button.  If the Storage is password-protected, a prompt displays for your 'Complete Access' password. Type this in and click on the OK button.  The 'Register Package(s)' dialog displays.

3	If any Packages are listed in the 'Packages to Register' panel, and you do not want to re-register them, clear the checkbox against each Package name.
4	Click on the Additional Files button. The 'Select Additional Files' dialog displays.
5	Click on the Add button.  A 'Select' screen displays, on which you browse for and click on the required file. You can only select one file at a time on this browser.
6	Click on the Open button. The 'Add Comment' dialog displays.
7	Type a brief comment on the nature or purpose of the file in the Registry, and click on the OK button. Focus returns to the 'Select Additional Files' dialog, which now lists the selected file.
8	Repeat steps 5-7 for each Asset file to register.  When you have finished, click on the OK button.  The 'Register Package(s)' dialog redisplays.
9	Click on the Register button. A prompt displays to confirm registration of the files.

10	Click on the Yes button.  A 'Progress' dialog displays while the files are registered, followed by a message confirming that the (Package and) File registration is complete.
11	Click on the OK button to clear the message, and to return focus to the Reusable Asset Service view.  You can review the files on the 'Storage Files' tab in the lower half of the view.

# **Register Learning Center Library**

Ste	Action
p	
1	In the Reusable Asset Service view, select the appropriate Registry and 'Learning Center Library' Storage.
2	On the 'Registry Browser' tab, click on the Register button.  If the Storage is password protected, a prompt displays for your 'Complete Access' password. Type this in and click on the OK button.

3	The 'Register Learning Center Library' dialog displays.  Click on the button next to the 'File' field and select the Library file.
	Type in a short comment on the Library being registered, in the 'Comments' field.
4	Click on the Register button.  A prompt displays to confirm registering the Library file. Click on the Yes button.  If the same Library file already exists in the Registry, a prompt displays to confirm overwriting it. Click on the Yes button.
	A progress dialog displays followed by a message confirming that Library registration is complete.
5	Click on the OK button.  The 'Storage Files' tab in the lower half of the Reusable Asset Server view is updated with the newly-added Library file.

# **Register Reference Data Library**

Ste	Action
p	

1 In the Reusable Asset Service view, select the appropriate Registry and 'Reference Data Library' Storage. 2 On the 'Registry Browser' tab, click on the Register button. If the Storage is password protected, a prompt displays for your 'Complete Access' password. Type this in and click on the OK button. The 'Register Reference Data Library' dialog 3 displays. Press the button next to the 'File' field and select: • From File System – to select an existing Reference Data XML file from the file system • From Model – to open the 'Export Reference Data' dialog for selecting categories that will be registered as the Reference Data Library once the Register button is clicked and a name is entered in the 'Enter Reference Data File Name 'dialog Type in a short comment for the Library being registered in the 'Comments' field. Click on the Register button. 4 A prompt displays to confirm registering the Library file. Click on the Yes button. If the same Library file already exists in the

	Registry, a prompt displays to confirm overwriting it. Click on the Yes button.  A progress dialog displays followed by a message
	confirming that Library registration is complete.
5	Click on the OK button.
	The 'Storage Files' tab in the lower half of the
	Reusable Asset Server view is updated with the
	newly-added Library file.

# **Register Source Code Library**

Ste p	Action
F	
1	In the Reusable Asset Service view, select the appropriate Registry and 'Source Code Library' Storage.
2	On the 'Registry Browser' tab, click on the Register button.  If the Storage is password protected, a prompt displays for your 'Complete Access' password. Type this in and click on the OK button.

3	The 'Register Source Code Library' dialog displays.
	Select the Library file by pressing the button next
	to the 'File' field.
	Type in a short comment for the Library being
	registered, in the 'Comments' field.
4	Click on the Register button.
	A prompt displays to confirm registering the Library
	file. Click on the Yes button.
	If the same Library file already exists in the Registry
	a prompt displays to confirm overwriting it. Click on
	the Yes button.
	A progress dialog displays, followed by a message
	confirming that Library registration is complete.
5	Click on the OK button.
	The 'Storage Files' tab in the lower half of the
	Reusable Asset Server view is updated with the
	newly-added Library file.

# **Check Package Dependencies**

As you register a Package in the Reusable Asset Service, the system provides a check on whether that Package is dependent on any external content; that is, whether it links to any modeling component held in Packages other than its own child Packages. You can perform three types of dependency check:

- Complete, which will consider Package A to be dependent on Package B if Package A contains any element, attribute, operation, operation parameter, diagram or connector (or their Tagged Values) that references elements in Package B
- Normative, which is the same as a Complete Dependency Check except that it will not treat as a dependency for Package A any element from Package B that is added as a link on a diagram in Package A
- Package Dependency/Import, where only those Packages that are the target of a Dependency/Package Import connector from Package A will be treated as dependent Packages for Package A

You perform this dependency check as an integral part of the Asset Registration process (specifically, at step 6 of the Register Package as Asset process). The check automatically identifies, firstly, the Packages directly needed by the Asset Package, and then any Packages needed by those initial Packages, and so on until the needed Packages are not dependent on any other. In practice, such dependency chains are likely to be quite short. If you know that the original Asset Package is dependent on two other Packages, one of which is subordinate to the other, you can simplify the process further by selecting the Parent or Ancestor Package first and thus avoiding the extra steps of selecting the two Packages separately.

#### **Access**

Open the Reusable Asset Service window, using one of the methods outlined here.

• In the Reusable Asset Service window, click on the 'Register' button

Ribbon	Publish > Model Exchange > Reusable	
	Assets	

## **Check Package Dependencies**

Ste	Action
p	
1	Select the appropriate Registry, Storage and version of the model Package to register, and provide any


appropriate comments or notes.

2 Click on the Check Dependency button.

If there are no Packages on which the Asset Package depends, the system sets that Package to 'Ready'. Go to step 6.

The 'Select Needed Package: <dependent package name>' dialog displays, showing the model hierarchy containing the Packages needed by the Asset Package. Each needed Package has a selected checkbox against it.

If you know that a needed Package is a child or grandchild of another needed Package, click on the checkbox next to the 'higher' Package name so that the child is validated as part of the parent. In this example, if the Asset Package has dependencies on both External factors and Location, click on the 'External factors' checkbox to register both dependencies as External factors.



If the needed Package is already registered in the Registry, it is indicated by a globe icon:



In this case, select the 'Use latest version of selected

package in Registry (if available)' checkbox to link to the registered version. For such Packages, no further dependency check is performed and, on the 'Register Package(s)' dialog, the Package's Status is set to 'Ready'.

- 3 Click on the OK button.
  - The 'Register Package(s)' dialog updates to show the initial 'Asset Package status' as 'Ready', and to list the needed Packages each with the status of 'Pending'.
- Click on the Check Dependency button again.

  If there are no Packages on which the needed Package depends, the system sets that Package to 'Ready' and sets the focus on the next Pending Package. If there are no more Pending Packages, go to step 6.

If the needed Package is dependent on other Packages, the 'Select Needed Package: <dependent package name>' dialog displays again, showing the model hierarchy containing those Packages, each with a selected checkbox next to it. As in step 2, you can select a 'higher' Package if appropriate.

5 Click on the OK button.

The 'Register Package(s)' dialog updates to show the first needed Package status as 'Ready', and to list any further needed Packages with the status of 'Pending.

If there are further needed Packages in the chain, repeat step 4. The system automatically identifies them and lists them for validation as in step 5.

Otherwise the system sets the final needed Package status to Ready and you can continue to register files and MDG Technologies.

#### **Notes**

- A Package with status Pending cannot be registered; only Packages with status Ready can be registered
- If you are certain that there are no parent-child relationships between the needed Packages, you can work through these steps quickly by just clicking on the Check Dependency button and OK button alternately until all Packages in the Package to Register list have the status Ready
- The system does not allow you to register an Asset Package that has dependencies on its own parent or grandparent Package; such dependencies would cause the Asset Package to be registered twice - by itself and as part of the parent Package - creating the risk of differences developing between the two instances

# **Update an Asset**

Over time, you might need to revise the contents of the Registry. Such updates can include:

- Registering additional Asset Packages and files
- · Registering a new version of an Asset Package
- Registering a new edition of a Storage file
- Registering new Libraries
- Deleting an Asset Package
- Deleting a Storage file
- Deleting a Library
- Changing the details of a Storage
- Deleting an entire Storage and the assets and files within it

#### **Access**

Ribbon	Publish > Model Exchange > Reusable
	Assets > Registry Browser

## **Update Tasks**

Task	Detail
Register new Asset Packages and Storage files	You can add further Asset Packages and files to a Storage at any time.
Register a new version of an Asset Package	You register a new version of an Asset Package as if it were a new Asset. In the 'Current Version' field on the 'Register Package(s)' dialog, you type a different number or reference to that assigned to the currently-registered Asset.  You can overwrite an existing Asset Package under the same version number only if the Storage has 'Draft' status. If the Storage has 'Complete' status, you cannot overwrite the existing Asset Package under the same version number. To replace the current version, you must delete the Asset from the Storage and register the Package again.
Delete Asset Package from Storage	Click on the Package name in the 'Registry Browser' tab and either:  Click on the Delete button or Right-click and select the 'Delete From Registry' menu option  In either case a short submenu displays,

prompting you to select to delete:

- The Asset Package only, or
- The Asset Package and the Packages on which it is directly or indirectly dependant

When you select the appropriate option, a prompt displays for you to confirm the deletion.

Click on the Yes button. A message displays to confirm that the Package has been deleted from the Registry, and the name of the Package is removed from the 'Registry Browser' tab.

If the Storage is password-protected, the system prompts you to enter a 'Complete Access' password before it begins deleting the Package(s).

If any of the registered Packages depend on the Package being deleted, the system displays the names of these Packages and prompts for confirmation before deleting each Package.

Register a new version of a Storage File You register a new version of a Storage file as if it were a new file under a different file name.

You can overwrite an existing file under the same file name only if the Storage has

	'Draft' status. If the Storage has 'Complete' status, you cannot overwrite the existing file. To replace the current version, you must delete the file from the Storage and register the file again.
Delete Storage Files from Storage	On the 'Storage Files' tab, right-click on the file name and select the 'Delete From Registry' option. A prompt displays for you to confirm the deletion.  Click on the Yes button. A status message confirms the deletion, the file is removed from the Registry and the file name is removed from the 'Storage Files' tab.  If the Storage is password-protected, the system prompts you to enter a 'Complete Access' password before it begins deleting the file.
Register a new Library File	You can add further Library files to a Storage at any time.  When you register a Library file, the file name and location will be used as the unique identifier for the file. You can overwrite this Library file in the Registry by registering a file with the same name and from the same file system location.

Delete Library Files from Storage	To delete all Library files in Storage, click on the Delete button in the 'Registry Browser' tab.  To delete a particular Library file, right-click on the Library file name in the 'Storage Files' tab and select the 'Delete From Registry' option.  A prompt displays for you to confirm the deletion. Click on the Yes button. A status message confirms the deletion, the Library file(s) is removed from the Registry and the Library file(s) name is removed from the 'Storage Files' tab.  If the Storage is password-protected, the system prompts you to enter a 'Complete Access' password before it begins deleting the Library file.
Change Storage Details	This task is as documented for setting up the Registry. Note that whilst you can copy a Storage as a new Storage, you cannot transfer assets directly between existing Storages.
Delete a Storage and its contents	This task is as documented for setting up the Registry. Note that whilst you can copy a Storage as a new Storage, you cannot transfer assets directly between existing Storages.

Refresh
Registry
Browser

If there is a possibility that another user has updated the Registry while you have had it open, click on the icon in the Reusable Asset Service toolbar to refresh your display from the latest updates to the Registry.

# **Pro Cloud Server Troubleshooting**

#### **Browser Test**

For a simple check that the Pro Cloud Server is operating on the specified Ports defined in the configuration file, you can enter this address into a web browser:

```
col>://<machineName>:<port>
```

For example, using the default settings on the machine with Pro Cloud Server installed:

http://localhost:804/

Or

https://sparxcloud.com

If the port is enabled this message is returned:

Sparx Systems Pro Cloud Server vX.X.XX

Congratulations, your server is now ready to host your models. Connect through the

configuration client to add or remove models.

If this message is not displayed, confirm the server name and port, check for other services listening on the specified port, check the server log file for error messages, check any firewalls between the client and the server to confirm there is connectivity and the relevant port(s) are open.

# **Errors shown in Enterprise Architect System Output**

Error Message	Meaning
Http Status Code: 503 Service Unavailable	<ul> <li>Indicates that the Pro Cloud Service is not running on the Server.</li> <li>Check you have the correct Server Name and Port</li> <li>Check that the 'Sparx Systems Professional Cloud' Service is currently running on the server.</li> </ul>
HTTP Status 401 Access Denied	Indicates a failure to authenticate with the server.  With the built-in web server, this error will occur if an invalid username or password was provided, or no username or password were provided.
HTTP Status 403	Indicates an attempt to access a model that is marked on the server as 'Require authenticated and secure connection'.  This might indicate that you are connecting using an <i>http</i> protocol instead of <i>https</i> , or that the port you are using is not providing authentication to the model

	you are connecting to. Check that you are using https. Check with the system administrator that the security authentication option is pointing to a model with security enabled.
HTTP Status 500 Unable to connect to service	<ul> <li>The connection is not being accepted.</li> <li>Check the server name</li> <li>Check the firewall settings on the client and server</li> <li>Check the ports the server is listening on</li> </ul>
The database manager for this database was shut down	Enterprise Architect established a connection to a Pro Cloud Server, and requested to connect to a known repository, but the repository is currently disabled.  Ask your system administrator to check the 'Enabled' option for the database manager in question.
There is no database manager configured for the	Enterprise Architect established a connection to a Pro Cloud Server, but the model name requested does not match any defined database on the server.

requested repository	When accessing the model using the Enterprise Architect Cloud Connection screen, ensure that the Model Name entered matches the Alias which is shown in the Pro Cloud ServerConfiguration Client.
Unable to connect to Database	Enterprise Architect established a connection to a Pro Cloud Server and requested to connect to a known repository; however, when the server attempted to open a connection to the database using the supplied details, it failed.  Note: Whenever this error occurs, a Warning-level message that contains more detailed information will be written to the Pro Cloud Server logs.  If the repository is:  If Using ODBC, ask your System Administrator to check that an ODBC connection is defined as a System DSN (and not a User DSN) on the server, that all connection parameters are correct, and that the database username and password have been saved into the ODBC DSN or the connection string  Oracle, ask your System Administrator to verify that the user name and

password were saved with the connection string and that all other options in the connection are correct

- SQL Server connecting via OLE DB and Windows authentication, ask your System Administrator to verify that the user name the Pro Cloud Server service is running and has been granted permission to the SQL Server database (at a minimum it will need the roles db\_datareader and db\_datawriter) and that all other options in the connection are correct
- SQL Server connecting via OLE DB and SQLServer authentication, ask your System Administrator to verify that the defined user name has been granted permission to the SQL Server database (at a minimum it will need the roles db\_datareader and db\_datawriter), that the option to save the password with the connection string was enabled, and that all other options in the connection are correct

12007 - The server name or address could not be

Indicates the server name (or IP address) is incorrect.

- Check that the server name is correct.
- Attempt the Browser Test described

resolved	above.
12029 - A connection with the server could not be established	<ul> <li>This could indicate that the Pro Cloud Server is not installed, the Service is not running, or an incorrect Port was entered.</li> <li>Confirm the Pro Cloud Server is installed.</li> <li>Check that the 'Sparx Systems Professional Cloud' Service is running.</li> <li>Check that you entered a valid Port (I.e. It should match one defined in the Configuration Client).</li> <li>Attempt the Browser Test described above.</li> </ul>
After Reinstall Enterprise Architect no longer works	Your environment was working correctly, then you updated to the latest version of the Pro Cloud Server and now Enterprise Architect clients are not able to connect to your Cloud models.  During the reinstall process the Pro Cloud Server installer actually uninstalls the original version and then installs the new one. As a result of this the Firewall exception that is automatically added by the installer is removed and re-created. The problem with this is if someone manually adjusted the Firewall exception (after the original install) any manually

changes are lost when the installer re-creates the Firewall exception. One method of stopping this from occurring in the future is to create a completely new firewall exception (with a different name) that is a copy of the one created by the installer, and make any manual changes to that exception.

# **Reading Server Logs**

As mentioned earlier the Sparx Systems Pro Cloud Server is a Windows Services application and as such it needs to conform to some basic rules. When it comes to troubleshooting the most important rule for Windows Services is that they can be run independently of user input/interaction and as such do not contain screens/GUI of any kind. For this reason the Sparx Systems Pro Cloud Server writes any potential message to Log files.

The Pro Cloud Server configuration file contains a number of settings that control where, how many and how large log files can be. By default the Pro Cloud Server will save all log files to a \Logs\ folder under \Services\ (C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\Logs), and it will keep up to 3 files. A new file will be created whenever the Cloud Service is started or whenever the maximum file size if reached. Filename

'SparxCloudServicesLog-1.log' will always be the most recent log file and each time a new file is created the older ones are renamed by increasing the number. ie SparxCloudServicesLog-2.log is renamed to SparxCloudServicesLog-3.log.

The configuration file also contains a setting that controls the level of logging that is performs, see the logging related options in 'Extended Server Properties' for more details. When troubleshooting, it is recommended that the Pro Cloud Server LOG\_LEVEL property be set to the highest level, SYSTEM.

Each log entry will consist of the Time, Log Level and Message, if an error occurs the Message will normally contain a description of the problem and from this the appropriate action can be undertaken.

Log Message	Explanation
Log File	Each time new Log file is created the Pro

Header	Cloud Server will write out a summary of the main settings, this information is particular useful if you are requesting support from Sparx Systems.
Started database managers	When a Pro Cloud Server is initially started, and the Log Level is set to INFO (or lower) it will log out a summary of each configured model which includes the connection string of the model.  [INFO]: Added database manager - ConnectionStr: 'eaexample Connect=Provider=MSDASQL.1;  If the Log level is lower than INFO, additional log entries will be written for each model, for example:  [SYSTEM]: SUCCESS Started database manager firebird:anonymous@eaexample
House keeping	The Pro Cloud Server performs regular 'house keeping' tasks, the frequency of which is controlled by the AUDIT_TIME_PERIOD setting in the Pro Cloud Server configuration file.  When the log level is set to INFO, each time house keeping is performed the Pro Cloud Server will log out a summary of connections for each defined database

manager and report how many are currently available, the maximum number used concurrent and total number of uses since the last audit.

[AUDIT]
firebird:anonymous@eaexample |
Free: 0 | Max Active: 3 | Acquisitions:
192 |

Normally these entries can be ignored as they are purely reference information only.

### Open port list

When a Pro Cloud Server is initially started, and the Log Level is set to SYSTEM, it will log out a success message for each configured port, which includes the management port (803) and any http/https ports, you should see a line such as:

[SYSTEM] SUCCESS Bound and listening on port 804.

If the log file is missing any lines, or if the message doesn't read 'SUCCESS' this might indicate a problem with the server port.

A common error here is:

Unable to create secure server on port

443.

Possible causes of this are:

- Certificate/Private Key file not found at C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\server.pem
- The server.pem file does not contain a valid certificate and private key
- Certificate Authority file not found or invalid at C:\Program Files (x86)\Sparx Systems\Pro Cloud Server\Service\cacert.pem

Unable to connect to database

During general operations, the Pro Cloud Server will write entries to its log file, which include any failed attempts to open a model. This will generally not occur until a user attempts to connect to the database. Errors that can occur here are:

REQUEST\_CONNECT FAIL. Error (5): Unable to connect to database

This means that the server attempted to open a connect but it failed. If you see this message, review the list of potential reasons outlined in the Errors shown in Enterprise Architect System Output table.

# **Change Management**



As a repository is developed it will become the data store for valuable organizational information assets, and it is imperative that this data is protected and maintained. Enterprise Architect has sophisticated tools to ensure the information is protected, including full integration with all the leading Version Control Systems, Baselines that are snapshots of your model that can be taken at important milestones, and Auditing that can track the finest changes to a model. A Project Transfer function helps you to make backups of models without involving information technology personnel. There are also Model Validation and Project Integrity Checkers to ensure the repository is maintained with a clean bill of health, and a powerful role based Security System to ensure users can collaborate easily.

### **Facilities**

Facility	Detail
Version Control of Packages	<ul><li>Enterprise Architect Model Version</li><li>Control helps you to:</li><li>Coordinate sharing of Packages</li></ul>

	between users, with either read-only access or update access, ensuring that work on different areas of the model is coordinated and synchronous rather than conflicting  Save and retrieve a history of changes to Packages  To use Version Control in Enterprise Architect, you require a third-party source-code control application such as:  Subversion  CVS  MS Team Foundation Server (TFS), or  Any other Version Control product that complies with the Microsoft Common Source Code Control standard
Tracking Changes	Enterprise Architect provides two separate but complementary facilities for tracking changes to data across the project:  • Auditing of model changes  • Baselining and differencing to capture and roll back changes
Project Data Transfer	Enterprise Architect enables you to transfer project data between project data repositories either for:

- Sections of the project (XMI and CSV) or
- The whole project, row by row, table by table (in the Corporate, Unified and Ultimate editions of Enterprise Architect)

### **Version Control**

Within Enterprise Architect, you can manage changes to and revisions of your projects by placing individual model Packages, view nodes or root nodes under Version Control. This provides numerous key facilities, including:

- Saving a history of changes to Packages
- The ability to retrieve previous revisions of Packages
- Propagating model updates between team members
- Coordinating the sharing of Packages between team members

You apply Version Control through a third-party source-code control application that manages access to and stores revisions of the controlled Packages. Once the Version Control software has been installed and configured, you must define a Version Control Configuration within your project. You can then use Version Control to manage changes to the Packages of your model.

#### **Notes**

- Sparx Systems strongly urge you not to manipulate Version Controlled Package files outside of Enterprise Architect; it is possible to leave the Package files in a state that Enterprise Architect cannot recognize
- Database replication should not be combined with Version Controlled Packages

• If the Packages under Version Control contain any alternative images and those images are subject to frequent change, you can set the 'Export alternate images' option on the 'Preferences' dialog to export the images to the Version Control repository when you check in the Packages; if the images are not subject to frequent change, do not select this option and instead use 'Export/Import Reference Data' to manage alternative images

### Introduction

Enterprise Architect's Version Control integration provides several key facilities, including:

- Saving a history of changes made to your model's Packages
- Retrieving previous revisions of Packages
- Propagating model updates between team members
- Coordinating the sharing of Packages between team members

The steps involved in setting up a Version Control environment and applying Version Control to an Enterprise Architect project that is to be accessed by a number of users, are summarized in the Help topic <u>Applying Version Control</u> in a Team Environment.

There are a number of factors to consider when setting up and using Version Control in your model development.

#### **Factors to consider**

Factor	Detail
System Requirements and Configuratio	You apply Version Control through a third-party source-code control application that manages access to and stores revisions of the controlled

n	Packages.
	Typically the configuration consists of:
	<ul> <li>A server component that manages a Version Control repository, and</li> </ul>
	<ul> <li>Client components on the workstations, that manage local working copies of controlled files</li> </ul>
	Enterprise Architect uses the client component to communicate with the server. A Version Control client must be installed on every machine where you run Enterprise Architect and want to access your Version Control system.
Version Control Usage	There are two main ways in which projects can be deployed:  Centralized Shared Model  Distributed Private Models  Version control is employed in the same way for both scenarios; however, when using Private Model deployment you have the additional facility of propagating model updates throughout the team.  Version Control can also be used to share standard Packages between different projects.
Team	Consider the process of setting up a

Deployment	Version Control environment and applying Version Control to a project to be accessed by a number of users.
Version Control Basics	Enterprise Architect enforces serialized editing of Version Controlled Packages, using the lock-modify-unlock mode of operation.
Applying Version Control to Models	Using Version Control consists of placing individual model Packages under Version Control, rather than Version Controlling the project as a whole.
Version Control and Project Reference Data	To share changes in reference data between users in a version-controlled project deployed as multiple private models, you periodically export the reference data from the model where the changes were made, and import it into the other models maintained by the team.
Offline Version Control	You can prevent the system from attempting to make any Version Control connections by choosing to Work Offline before loading a model.  If Enterprise Architect is unable to connect a Version Control Configuration for any reason, it displays warning

messages to notify you and provides 'offline' Version Control functionality for all Packages associated with the failed connection.

#### **Notes**

 Packages under Version Control are identified in the Browser window by icons that indicate the current status of the Package

# **Version Control Usage**

The Version Control facility can be used in many different ways, although these roughly fall into one of four types of use as discussed here.

## **Usage**

Type	Details
Single Shared model	Users share a model stored in a central project file or DBMS repository. In this configuration you can view changes to other users' Packages without explicitly having to check them out, by simply refreshing your view of the model.  Version control is used to:  Archive successive versions of your work to date  Maintain Package revision history  Recover from unwanted changes or accidental deletions, through an 'undo' facility  Regulate access to Packages
Multiple Private	One model is created by a single user who configures it for Version Control.

models	The model file is then distributed to other users, with each user storing their own private copy of the model.
	Version Control is used to:
	<ul> <li>Propagate changes to the model, throughout the team</li> </ul>
	<ul> <li>Archive successive versions of your work to date</li> </ul>
	<ul> <li>Maintain Package revision history</li> </ul>
	<ul> <li>Recover from unwanted changes or accidental deletions, through an 'undo' facility</li> </ul>
	Regulate access to Packages
Shared Packages	<ul><li>Individual users create separate models but share one or more Packages:</li><li>Users share Packages through Version Control</li></ul>
Standard Packages	A company might have a standard set of read-only Packages that are broadly shared:
	<ul> <li>Individual users retrieve Packages with the Get Package menu option</li> </ul>

### **Version Control of Model Data**

When applying Version Control in Enterprise Architect, you place individual model Packages under Version Control, and not the project as a whole.

All Enterprise Architect models are stored in databases - even the .eap file is an MS Jet database. In simple terms, the project file is a single entity of binary data. Being binary data, the project file would require the use of the lock-modify-unlock model of Version Control, which would mean that only a single user at a time could work on any given (Version Controlled) model. Therefore, it is not practical to apply Version Control to the database (.eap file) as a whole; this can also create problems for you in that:

- Most Version Control systems mark their controlled files as read only, unless they are specifically checked-out to you
- The .eap file is an MS Jet database, and Enterprise Architect must be able to open this file for read/write access when you load your model; if the model is read-only, the system displays an error message and fails to load the model

# **Version Controlling Packages in your Model**

To overcome these limitations, Enterprise Architect exports discrete units of the model - the Packages - as XMI Package

files, and it is these XMI files, not the project file, that are placed under Version Control. The XMI file format used by Enterprise Architect dictates that they too be treated as binary files - therefore it is not possible to merge the XMI files either; however, by splitting the model into much smaller parts, many users can work on separate parts of the model simultaneously.

# **Version Controlled Nested Packages**

Version Controlled nested Packages result in much smaller XMI files being exported, as the parent Packages' XMI files do not contain any content for the Version Controlled child Packages.

Version Control of nested Packages, together with a model structure of small individual Packages, provides greater scope for multiple users to work concurrently, as individual users are locking much smaller parts of the model.

### **Version Control and Reference Data**

Reference data is data that is used across a model or project; it is not Package-specific. Version Control operates at Package level, and therefore does not capture changes in reference data. Where Version Control is used in a multiple private model set up, changes in reference data are not brought into the model when Packages are updated from Version Control.

In a Shared Model environment, all users are accessing the same project reference data. Changes in reference data can be shared between users in a Version Controlled project deployed as multiple private models, by periodically exporting the reference data from the model where the changes were made, and importing it into the other models maintained by the team.

Reference data is exported and imported as an XMI file, which contains whatever types of reference data you want to transfer. You can place your project reference data under Version Control by exporting the data as an XMI file and apply Version Control to that file using your Version Control software external to Enterprise Architect.

# **Version Controlling Packages**

Enterprise Architect implements Version Control of your model by exporting Package data from the project database to XMI Package files, which are placed under Version Control in the source-code control application. The XMI file format cannot be merged in the same way as ordinary text files can be merged, which is why Enterprise Architect must enforce serialized editing of Version Controlled Packages, as discussed here.

# The Lock-Modify-Unlock Solution

Many Version Control systems use a lock-modify-unlock model to address the problem of different authors in a shared source overwriting each other's work. In this model, the Version Control repository allows only one person to change a file at a time, and access is managed using locks. Harry must lock a file before he can begin making changes to it. If Harry has locked a file, Sally cannot also lock it, and therefore cannot make any changes to that file. All she can do is read the file, and wait for Harry to finish his changes and release the lock. After Harry unlocks the file, Sally can take her turn in locking and editing the file.

# The Copy-Modify-Merge Solution

Subversion, CVS and a number of other Version Control systems use a copy-modify-merge model as an alternative to locking. In this model, each user's client contacts the project repository and creates a personal working copy - a local reflection of the repository's files and directories. Users then work simultaneously and independently, modifying their private copies. In due course, the private copies are merged together into a new, final version. The Version Control system often assists with the merging, but ultimately a person is responsible for making it happen correctly.

# When Locking is Necessary

While the lock-modify-unlock model is generally considered a hindrance to collaboration, there are still times when locking is necessary.

The copy-modify-merge model is based on the assumption that files are contextually merge-able: that is, that the files in the repository are line-based text files (such as program source code). However, for files with binary formats, such as artwork or sound, it is often impossible to merge conflicting changes. In these situations, it really is necessary for users to take strict turns in changing the file. Without serialized access, some users end up wasting time on changes that are ultimately overwritten.

# Applying Version Control in a Team Environment

This is a summary of the process of setting up a Version Control environment and applying Version Control to a project to be accessed by a number of users.

#### **Version Control - Process Overview**

Ste	Action
p	
1	Install your Version Control product.
2	Create a Version Control repository.
3	Create a Version Control project to be used with your Enterprise Architect project.
4	Check-out a working copy of the Version Control project (a module, project or folder within the Version Control system) into a local folder.  You must do this for every team member that is accessing the Version Controlled Packages, whether you are using a single shared model or each team member stores his own private copy of the model.

- Before attempting to access the new Version Control environment from within Enterprise Architect, you should first verify that it functions correctly when used outside of Enterprise Architect.
- Within Enterprise Architect, define a Version Control configuration to provide access to the working copy files.

The name of the Version Control configuration must be the same across all machines throughout a team. That is, all Version Control access to a given Package must be through Version Control configurations with the same name, across all models and all users.

The easiest way to perform this step (throughout the team) is to have one user set up Version Control on the model and then share that model with the rest of the team.

- In Shared Model deployment, all users connect to a single instance of the model database, so the model is shared automatically
- In Private Model deployment, it is easiest to distribute copies of the original model (after Version Control has been set up) to all other members of the team

Whenever you open a model (Private or Shared) that uses a Version Control configuration that is not yet defined on your workstation, a prompt displays to

	complete the definition for that configuration. This typically means specifying the local working copy directory and perhaps choosing the Version Control project associated with this Enterprise Architect project.  Once this has been done, the Version Controlled Packages that already exist in the model are ready for use.
7	Configure Packages within the Enterprise Architect model for Version Control. That is, apply Version Control to individual Packages.
8	Check-out and check-in Packages as required.

#### **Notes**

• It is possible to use multiple Version Control Configurations within the same model; different Packages can still use different Version Control Configurations within the model, as long as any given Package is always accessed via the same Version Control Configuration

# **Version Control Nested Packages**

When you save a Package to the Version Control system, only stub information is exported for any nested Packages. This protects information in a nested Package from being inadvertently over-written by a top level Package.

## **Operations on Nested Packages**

Operation	Detail
Checking Out	When you check out a Package, you do not modify or delete nested Packages; only the top level Package is modified.  As a consequence of this behavior, if you check out or get a Version Controlled Package with nested Packages that are not already in your model, you see stubs in the model for the nested Packages only.
Get All Latest	If you select the 'Get All Latest' option from the Version Control menu, any new stubs are populated from the Version Control system.
Importing	You can populate a large and complex

Models	model, by 'getting' only the root Packages, then using 'Get All Latest' to recursively iterate through the attached and nested Packages.
	This is a powerful and efficient means of managing your project and simplifies handling very large models, even in a distributed environment.
	The 'Import a Model Branch' option combines the procedure steps into a single operation.

#### **Notes**

• It is recommended that, when sharing a Version Controlled model, you do not mix versions of Enterprise Architect later than version 4.5 with earlier versions; if this is necessary it is best to go to the 'Version Control Settings' dialog and deselect the 'Save nested version controlled packages to stubs only' checkbox, setting Enterprise Architect to the pre-version 4.5 behavior (for the current model only)

## **Add Connectors To Locked Elements**

Generally, when working in a diagram containing locked elements, you cannot add a connector to a locked element. However, this depends on the lock status of the source and target elements (or more precisely, the lock status of the parent Packages of the source and target elements, when the source and target element are held in different Packages). There are scenarios in which a connector can be created on a locked element.

#### **Lock Scenarios**

<b>Element Status</b>	Add Connectors
Source unlocked, target unlocked	Yes, any kind of connector can be added
Source unlocked, target locked	Yes, except for Composition connectors
Source locked, target	No, except for Composition connectors

unlocked	
Source locked, target locked	No, prohibited for all connectors

#### **Notes**

- A connector can be added if its source is unlocked you are modifying what the source can see
- The exception is Composition connectors, where the target (the parent) must be unlocked you are modifying the parent by adding children

## **Browser Window Indicators**

Packages under Version Control are identified in the Browser window by icons that indicate the current status of the Package.

#### **Indicators**

Icon	Indicates that
<b>⊗</b>	This Package is Version Controlled and not checked out to you.  You cannot edit the Package (until you check out the Package yourself).
8 <u></u>	This Package is Version Controlled and checked out to you. You can edit the Package.
<b>8</b>	This Package is Version Controlled, but you checked it out whilst not connected to the Version Control server.  You can edit the Package but there could be version conflicts when you check the Package in again.
<b></b>	This Package is controlled and is

represented by an XMI file on disk, but it is not under Version Control.
You can edit this Package.

### **Offline Version Control**

When loading a model that uses Version Control, Enterprise Architect normally initializes a connection to the Version Control system for each Version Control configuration defined in the model. If Enterprise Architect is unable to connect a Version Control configuration for any reason, it displays warning messages to notify you and provides offline Version Control functionality for all Packages associated with the failed connection.

You can prevent Enterprise Architect from starting to make any Version Control connections, by selecting to work offline before loading your model.

#### **Access**

Ribbon Configure > Version Control > Work Offline	ork
---	-----

# **Working Offline**

Concept	Discussion

## Choosing to Work Offline

Selecting to work offline is useful if you know beforehand that Enterprise Architect cannot connect to your Version Control system. For example: If you are working on a laptop computer that is disconnected from your network, on an Enterprise Architect model that uses a large number of Version Control configurations, you can select to work offline before you load the model to avoid all the error messages that the system would normally display as each Version Control connection attempt failed.

You can switch between working offline and working online at any time, either before or after a model is loaded, by toggling the 'Work Offline' menu option. Enterprise Architect disconnects or reconnects Version Control (depending on the connection availability) according to your selection.

Using
Version
Control
Whilst
Disconnected
From the
Version

Enterprise Architect 'remembers' the status of a model's Version Controlled Packages. Packages that were checked out to you prior to disconnecting from the server are still shown as checked out to you, even though you are no longer connected to the server. You can still edit

#### Control Server

these Packages as you normally would. Packages that were not checked out to you prior to disconnecting from the server are shown as Version Controlled and locked. You cannot edit these Packages until you check them out.

## Offline Check Out

You can 'check-out' and edit a Version Controlled Package even when your machine is disconnected from the Version Control server. In this example, the colored 'figure 8' icon for DFD indicates that you have checked it out whilst off line.



(The gray 'figure 8' icon shown against Logical View indicates that you have checked out a Version Controlled Package on line.)

You should be aware that the Version Control system, and therefore other users, have no way of knowing that you have 'checked-out' a Package whilst offline. It is not possible to merge changes to an XMI file that result from two users editing the same Package at the same

time. If an offline checkout leads to two people editing the same Package at the same time, when the changes are brought back online the first-saved set of changes is lost.

Checking In a Package That Was Checked Out Offline

Once you reconnect your system to the Version Control server, if the Package you checked out offline is not currently checked out by another user, you can check in that Package. However, before Enterprise Architect checks in the Package, it compares the local working copy of the Package file with the latest revision in the repository. (These Package files remain unchanged in your work area until Enterprise Architect exports the Package again before checking in.) If the repository version remains unchanged from when you last updated your local copy, Enterprise Architect exports and checks in your Package without further prompting.

On the other hand, if the repository now contains a file that has changed since you last updated your local copy, checking in your Package would overwrite those changes. Enterprise Architect displays a message warning you of the pending data loss and giving you the opportunity to

abort the check in. At this point, you must decide whether to discard your own changes, using the 'Undo Check Out' command, or continue with your check in and overwrite the changes that have been committed to the repository since you last updated your local copy from the repository.

You can use the 'File Properties' command to determine who checked in the last changes to this Package. This might help you to discover what changes have been uploaded and decide whose changes take precedence.

# Update Before You Disconnect

Whenever you are connected to the Version Control server, you are always working with the latest version of a Package. This is because you cannot modify a Package until you check it out from Version Control, and checking it out loads the latest revision from the repository into your model.

This cannot happen when you are disconnected from the Version Control server. You are working on whatever versions you have on your machine, dating back to the last time you updated your local copy of each Version

Controlled Package. So, if you are planning to work on a model whilst disconnected from Version Control, it is a very good idea to make sure that you have the latest versions of all Packages before you disconnect. The 'Get All Latest' option makes this a simple task.

## **Version Control Branching**

Currently, Enterprise Architect does not support Version Control Branching.

Work-arounds to achieve similar results might be possible for certain version-control products; contact Sparx Support for advice.

#### **Contacts**

<b>User Type</b>	Contact via
Registered users	https://sparxsystems.com/registered/reg_s upport.html
Trial users	support@sparxsystems.com

## **Version Control Product Setup**

To control and maintain the different revisions of your project Packages, Enterprise Architect uses third-party Version Control products. Once your Version Control product is installed and a suitable environment has been created, Enterprise Architect can use that environment to control your project's Packages.

Typically, Version Control products consist of:

- A server component
- A client component

Enterprise Architect integrates with the Version Control client components for Subversion, CVS and MS Team Foundation Server command line clients, as well as for products having API clients that comply with the MS SCCI specification.

### **Version Control System Components**

Component	Detail
Version Control Server	The server component maintains the controlled files in their many revisions, in a central repository.  The server component is usually located

	on a server machine that is accessible to all team members who are using Version Control.
Server Configuration	<ul> <li>The steps for configuring a Version Control server are, broadly:</li> <li>Install the software</li> <li>Create a repository</li> <li>Create Version Control projects (or modules or folders for use with specific projects)</li> <li>Configure user IDs and passwords</li> <li>For details on configuring any particular Version Control server, consult the appropriate documentation provided with the Version Control product.</li> </ul>
Version Control Client	The client component manages the working copies of the controlled files, submitting files to or retrieving files from the server as required.  A Version Control client must be installed on every machine on which you run Enterprise Architect and want to access your Version Control system.
Client Configuratio	The steps for configuring a Version Control client are, broadly:

 $\mathbf{n}$ 

- Install the software
- Create a new directory for use as a local working copy folder
- Log in to the Version Control server
- Associate the working copy folder with its corresponding server repository folder

For details on setting up a product-specific Version Control environment for use with Enterprise Architect, click on the appropriate link in the next column.

## **System Requirements**

Enterprise Architect is a Windows-based application and requires a Windows-based Version Control client for integration. It is independent of the Version Control server component and the platform on which that runs.

### **Version Control Product Requirements**

Product	Detail
Subversion	Subversion is free, open source software.  Subversion server components are available to run on a wide range of different hardware and operating systems.  Enterprise Architect is not affected by your choice of server components, but requires Subversion's Windows-based command line client for integration.  There are many graphical user interface clients available for use with Subversion, such as TortoiseSVN; this type of client cannot be used directly for integration with Enterprise Architect, but can be very useful in preparing a working Subversion environment for use by Enterprise Architect.

Binary Packages are available for download from:

http://subversion.apache.org/packages.
 html

Subversion documentation is available from:

http://svnbook.red-bean.com/nightly/en/index.html

#### Concurrent Versions System (CVS)

CVS is free, open source software.

CVS server components are available to run on a wide range of different hardware and operating systems.

Enterprise Architect is not affected by your choice of server components, but requires CVS's Windows-based command line client for integration.

There are many graphical user interface clients available for use with CVS, such as TortoiseCVS; this type of client cannot be used directly for integration with Enterprise Architect, but can be very useful in preparing a working CVS environment for use by Enterprise Architect.

The software is available for download from:

	<ul> <li>http://www.nongnu.org/cvs/</li> <li>CVS documentation is available from:</li> <li>http://cvsbook.red-bean.com/cvsbook.html</li> </ul>
Microsoft Team Foundation Server	Enterprise Architect is able to use either the:  Command line client for TFS, or  MS TFS-SCC client  Your choice of client affects how you specify your Version Control Configuration.
	MS TFS-SCC clients are available for download from Microsoft's web pages. (Run an Internet search for 'TFS MSSCCI'.)
Common Source Code Control (SCC)-compa tible products	Any Version Control product that provides a client that complies with the Microsoft Common Source Code Control standard, version 1.1 or higher, can be integrated with Enterprise Architect.  These products are SCC-compatible and are known to successfully integrate with Enterprise Architect:  Accurev  ClearCase

- . MS Visual Source Safe
- MS TFS-SCC
- MKS Source Integrity
- Perforce
- Source Offsite
- Snapshot CM

Products that do not appear in this list should still integrate successfully with Enterprise Architect, if there is a client available for that product that complies with the MS SCC API specification.

#### **Create a Subversion Environment**

You can use Subversion as a Version Control provider for Enterprise Architect. The first step in doing this is for a Subversion administrator to install and configure the appropriate software. A number of basic tasks are performed in creating an operational Subversion environment, and useful tools are available for performing some of these tasks.

## **Tasks in Creating a Subversion Environment**

Task	Detail
Install server components	Executable files for Subversion can be obtained from the Apache Software Foundation.  Subversion server components are available to run on a wide range of different hardware and operating systems; Enterprise Architect is not affected by your choice of server components.  VisualSVN is a package that can greatly simplify the installation, configuration and management of your Subversion server.

Create a repository	Please consult the official Subversion documentation.
Create Subversion users	Please consult the official Subversion documentation.
Create a new repository sub-tree	It is good practice to create a new repository sub-tree in Subversion for each new Enterprise Architect model being added to Version Control with Subversion. Users should create a new local working copy from the sub-tree to be used with that model.  TortoiseSVN can greatly simplify the process of creating new repository sub-trees.
Install client components	Executable files for Subversion can be obtained from the Apache Software Foundation.
Create a working copy folder	A working copy folder must exist on each users' machine, for Enterprise Architect to use when exporting and importing the Version Controlled Package files. It is this folder that is specified as the Local Project Path, when defining your Version Control Configurations.

The working copy folder is the 'sandbox' where you modify the controlled files. The working copy folder is usually associated with a folder that exists within the Version Control repository. In Subversion, to create a local working copy you perform an initial check-out of a folder from the Subversion repository; this downloads a copy of the folder and its contents, to create your local working copy.

TortoiseSVN can greatly simplify the initial check out of a working copy folder.

Setting up Subversion under Wine/CrossO ver The process of setting up and using Subversion with Enterprise Architect under Wine is almost identical to the process when running natively under Windows, apart from minor differences in installing the Subversion client and performing the initial check out of the working copy folder.

#### **Notes**

• Enterprise Architect relies on exclusive file locking when

applying Version Control to its Packages; file locking was not introduced into Subversion until version 1.2, therefore Enterprise Architect does not work with Subversion releases earlier than Subversion 1.2

• Enterprise Architect can only communicate with the Subversion server using the Subversion command line client syn.exe

## **Create a new Repository Sub-tree**

When you set up Subversion as your Version Control tool, it is good practice to create a new repository sub-tree in Subversion for each new Enterprise Architect model. The sub-tree can be used to control the Package files for your model.

# Create a new sub-tree in the Subversion Repository

Ste	Action
p	
1	Use Windows Explorer to create a temporary directory on your PC file system, to be imported into the Subversion repository as a new repository sub-tree. The directory would have this structure:
2	Open a Windows command prompt, navigate to <i>tempDir</i> and issue the Subversion command <i>import</i> .  For example:  C:\Documents and Settings\user> cd \tempDir  C:\tempDir> svn import .  https://host.example.com:8443/repos/ message "Repository Initialization"

On your PC, delete the temporary directory structure (tempDir) and all its contents.

#### **Notes**

- After the import is finished, the original tree is not converted into a Subversion working copy; you should delete the temporary structure and check out a fresh working copy of the tree
- The process can also be performed using TortoiseSVN's Repository Browser, which provides commands for simply creating new folders directly in the repository

## **Create a Local Working Copy**

In order to use Subversion to provide Version Control of the Packages in a model, you need to prepare a functional SVN working copy folder that can be accessed through an Enterprise Architect Version Control configuration within that model.

## Create a Subversion working copy folder

Ste p	Action
1	Choose or create a suitable directory on your system in which to create your Subversion working copy.
2	Open a command prompt window and navigate to the directory you have selected. For example:  C:\> mkdir mySVNWorkSpace  C:\> mkdir mySVNWorkSpace/myEAModelName  C:\> cd mySVNWorkSpace/myEAModelName
3	Perform the initial check out from the Subversion repository, specifying the repository folder and local working copy folder, as well as your user name and password. For example:

C:\> svn checkout

"https://myserver:8443/svn/repos folder

"C:\mySVNWorkSpace/myEAModelName"

- --username myUserName
- --password myPassword

(By specifying your Subversion username and password, you ensure that they are correctly cached by Subversion and available for use by Enterprise Architect.)

If you specify the HTTPS protocol when performing the initial Subversion check out, a prompt displays to accept a security certificate; in this instance, press the P key to permanently accept the certificate.

The nominated local folder is configured as a Subversion working copy folder.

Any files already existing in the repository folder are downloaded to the working copy folder as working copy files.

4 Verify that your Subversion environment functions correctly.

#### **Notes**

• It is important that Subversion caches your username and

password, so that it never has to prompt for user input; a check-out operation might not request authentication, and if it does not you should perform an action that does request authentication, such as adding and committing a dummy test file

• The process can also be performed using TortoiseSVN's Checkout command (which provides options to browse when specifying both your repository folder and your local folder); when prompted for authentication details by TortoiseSVN, make sure you place a check against the 'Save Authentication Data' option

## Verify the SVN Workspace

After creating the Subversion local working copy to hold the working copies of your Package files, you can verify that it functions correctly before attempting to use it with Enterprise Architect. You need to be able to add files to Subversion, lock the files and commit changes to those files.

# Verify correct operation of a Subversion working copy folder

Ste	Action
p	
1	Use Windows to open a command prompt window.
2	Select the directory you specified as the working copy, in the Subversion checkout command when preparing the SVN workspace. For example:
	C:\> cd mySVNWorkSpace
3	Create a test file, such as <i>Test.txt</i> , containing the text <i>Subversion Test</i> . For example:
	C:\> echo Subversion Test > Test.txt
4	Execute each of these Subversion commands:

- svn add Test.txt
- svn commit -m"Commit comment" Test.txt
- svn update Test.txt
- svn lock Test.txt
- Use your preferred editor to modify the file and save the changes
- svn commit -m"Second commit comment" Test.txt The commands should execute without any errors and without prompting the user for any extra input.

#### **Notes**

• Your environment must be set up such that you can perform these operations without ever being prompted for user ID or password; for further information, please see the Caching Client Credentials topic in the official Subversion documentation

#### **Subversion Under Wine-Crossover**

If you want to set up and use Subversion with Enterprise Architect under Wine, the process is almost identical to the process for setting up and using the systems under Windows. When running Enterprise Architect under Wine or CrossOver, you still use a Windows-based Subversion command line client.

There are some minor differences in the way you prepare the Subversion working environment, specifically in the way you install your Subversion client and the way you check out a working copy folder from the Subversion repository.

### **System Requirements**

Sparx Systems has tested the use of Enterprise Architect with Subversion under Wine 1.2, on macOS 10.4 and 10.6.2, and on Ubuntu 10.04. All tests were passed. When using Wine 1.2 on the Ubuntu 9.10 platform, Sparx Systems was able to use the svn: and file: protocols to communicate with the SVN server; but not the https: protocol.

## **Installing a Subversion Client**

Wine is able to install applications from either a Windows .exe file, or a .msi installer file.

Place the installer for your Windows Subversion client in a convenient location on the native file system, then open a Wine console window from within Enterprise Architect and run the installer from within the Wine console. Your Subversion installation can then access the same C: drive and folders that Enterprise Architect is accessing.

## Preparing a Subversion Environment Under Wine

Under Wine, you can install Subversion from either a Windows .exe file, or a .msi file. By performing your Subversion installation and initial check out from a Wine console window opened from within Enterprise Architect, you have access to the same C: drive and folders that Enterprise Architect is accessing.

## Set up Subversion for use with Enterprise Architect, running under Wine

Ste p	Action
1	Start Enterprise Architect.
	You do not have to load a project at this point.
2	From the 'Start' ribbon, select 'Desktop > Preferences > Keyboards and Toolbars > Tools: [2]'
	A new, blank entry is opened on the 'Tools' tab of the 'Customize' dialog.
3	Define the new menu item entry:
	• In the newly-opened 'Menu contents' field, type

	the name 'Wine Console'
	• In the 'Command' field, type 'wineconsole'
	• In the 'Arguments' field, type 'cmd'
	• Leave the 'Initial directory' field blank
4	Click on the Close button.
	The 'Customize' dialog closes.
5	Select the ribbon option: 'Configure > User Tools > Wine Console'.
	A Wine console window opens.
6	Type 'C:' and press the Enter key.
	The Wine console switches to the C: drive.
7	Issue the command to install your Subversion client. For example:
	C:\>/Installers/Subversion-client-1.9.5.win32.exe
	To install from a .msi file, use Wine's msiexec utility. For example:
	C:\>msiexec /i "Installers\Slik-Subversion-1.9.7-win32.msi"
	Installation of the Subversion command line client begins.
8	Create a folder to serve as the working copy folder to be used by Enterprise Architect. For example:

## C:\>mkdir C:\VC workspaces\SVN workcopy 9 Issue the command to perform the initial checkout from the Subversion repository, specifying the repository folder, working copy folder, username and password. For example: C:\>svn checkout "https://myServer:8443/svn/repos folder" "C:\VC workspaces\SVN workcopy" --username myUserName --password myPassword (After specifying your Subversion username and password, they are correctly cached by Subversion and are available for use by Enterprise Architect.) If the HTTPS protocol is specified when performing the initial Subversion check out, you are prompted to accept a security certificate; in this instance, press the P key to permanently accept the certificate. The nominated local folder is configured as a Subversion working copy folder. Any files already existing in the repository folder are downloaded to the working copy folder as working copy files. Type 'Exit' and press the Enter key. 10 The Wine console window closes. You are now ready to load a project in Enterprise Architect and apply Version Control to it, using the normal Windows-based procedures.

#### **Notes**

• You should copy the installer for your Windows Subversion client to a convenient location on the native file system, so that you can easily refer to it from within the Wine console window in step 7

#### **TortoiseSVN**

TortoiseSVN is a Windows shell extension for Subversion; it provides icon overlays in Windows Explorer that are useful as a tool for observing the status of your Subversion controlled files. You can also use it to create your repository sub-trees and check out local working copies from within Windows Explorer, using simple menu commands.

You can download TortoiseSVN from <a href="http://tortoisesvn.net/downloads.html">http://tortoisesvn.net/downloads.html</a>.

#### **Notes**

• Enterprise Architect can only communicate with the Subversion server using the Subversion command line client syn.exe

#### **Create a TFS Environment**

You can use Microsoft Team Foundation Server (TFS) as a Version Control provider for Enterprise Architect. The first step in doing this is for a TFS administrator to install and configure the TFS server and client applications. A number of basic tasks are performed in creating an operational TFS environment.

### **Tasks in Creating a TFS Environment**

Task	Detail
Obtain and install TFS	Enterprise Architect uses the TFS command line client to integrate TFS Version Control.  The TFS command line client is normally available as part of your Visual Studio installation.
Choose a TFS project	It is good practice to create a new TFS project, or least a new Source Control Folder within a project, for each Enterprise Architect project being added to Version Control with TFS.  If you have a single Enterprise Architect project that contains many different

models (for example, a DBMS hosted project with multiple model root nodes), you might choose to create a new TFS project for each separate model.

For further information, please consult your TFS product documentation.

## Create a TFS workspace

A working copy folder must exist on each users' machine, for Enterprise Architect to use when exporting and importing the Version Controlled Package files. It is this folder that is specified as the Local Project Path, when defining your Version Control Configurations.

The working copy folder is the 'sandbox' where you modify the controlled files. The working copy folder is usually associated with a folder that exists within the Version Control repository. In TFS, the TFS workspace is used to map a local working folder on your PC to a Source Control Folder within a TFS project. TFS 2012 and VS 2012 (and later versions) feature a new type of workspace called 'local' workspaces. Do not attempt to use TFS 'local' workspaces with Enterprise Architect. You must use only 'server' workspaces for Enterprise Architect Version Control, as 'local'

workspaces do not support the application of checkout locks to files. Enterprise Architect relies on the presence of checkout locks to ensure that Packages can only be checked out exclusively and that a given Package is not already checked-out in some other project (for instance, in a Private Model deployment). This is necessary because it is not practical to merge the XMI Package files that Enterprise Architect uses for Version Control.

A single TFS workspace can map many different local folders, each one to a separate Source Control Folder. In this case, TFS can take a long time to work through and update the files in all of those folders, and the system might appear to 'freeze' whilst it waits for TFS to hand back program control.

You can avoid this if you keep your Version Controlled Package files in a folder that is separate from other artifacts, such as source code files, creating a separate work space to use just for your Package files, or creating and mapping a separate folder for Package files within an existing workspace.

Configure exclusive check-outs	The XMI format files used for the Version Control of Enterprise Architect's Packages can not be merged as if they were ordinary text files. Therefore, Enterprise Architect must enforce serialized editing of its Version
	Controlled Packages. As a consequence, it is important that TFS is configured to use 'exclusive checkouts' for XML files.
Verify the TFS Workspace	Enterprise Architect uses the TFS command line client to checkin and checkout files from the TFS repository. After creating the TFS workspace, it is important to verify that the command line client can be used to add, check-in and check-out files residing in the working copy folder that is mapped through this workspace.

#### **Notes**

- TFS can also be used with an SCC client; the MS TFS-SCC client is available for download from Microsoft's web site
- MDG Integration for Visual Studio 2005 or 2008

enhances TFS support by providing access to, for example, work items and bugs within both Enterprise Architect and the MDG Integration product

### **TFS Workspaces**

In order to use TFS to provide Version Control of the Packages in a model, you prepare a functional TFS workspace that can be accessed through an Enterprise Architect Version Control configuration within that model. You use the TFS workspace to map a local working folder on your PC to a Source Control Folder within a TFS project repository.

It is assumed that have TFS 2013 open and a TFS Team Project already exists for you to use in Version Control of the Packages of your Enterprise Architect project. You can create the TFS workspace through MS Visual Studio.

TFS 2013 and later versions support the use of Local workspaces. However, Local workspaces do not support the application of checkout locks. For this reason, Sparx Systems strongly advises against the use of Local workspaces when Version Controlling your Enterprise Architect Package files. Using Local workspaces carries a high risk of merge conflicts when checking in, which would almost certainly result in loss of data or a corrupted model database.

## Map a local folder to a TFS Source Control Folder

p	
1	Connect to your TFS server.  From the TFS main menu, choose 'View   Team Explorer'.  In the Team Explorer toolbar, click on the Connect to Team Projects button (fourth from left, with a power plug icon).  The 'Team Explorer Connect' page displays.
2	Click on the link 'Select Team Projects' The 'Connect to Team Foundation Server' dialog displays.
3	Click on the appropriate Team Foundation Server, Team Project Collection and Team Project, then click on the Connect button.
4	Click on the Home page of the Team Explorer, and then on the Source Control Explorer button.  The Source Control Explorer view displays.
5	In the Source Control Explorer, click on the drop-down arrow in the 'Workspace' field in the toolbar, then click on 'Workspaces' at the bottom of the list.  The 'Manage Workspaces' dialog displays.

6	Click on the Add button.
	The 'Add Workspace' dialog displays.
7	Click on the Advanced button. A number of new fields display on the dialog.
8	Type in an appropriate name for the new workspace and, if required, type in a comment.
9	Set the 'Location' field to 'Server'. This setting is important.
	This setting is not available in TFS 2010 and earlier releases, where all workspaces are Server based.
10	Click in the Source Control Folder column, then click on the Browse button to select a Source Control Folder.
	Select the Source Control folder (in the Team Project) to use for controlling Enterprise Architect Packages.
11	Click on the Browse button in the 'Local Folder' column and create a new local folder.
	This is the working copy folder into which Enterprise Architect exports the Package files.
12	Click on the OK button. The new workspace is created and saved.

	The 'Add Workspace' dialog closes.
13	Click on the OK button. The 'Manage Workspaces' dialog closes.

### **Notes**

• The local folder referenced in step 11 is the Working Copy Path that should be specified when defining an Enterprise Architect Version Control Configuration to use this TFS workspace

### **TFS Exclusive Check Outs**

The XMI format files used for the Version Control of Enterprise Architect's Packages can not be merged as ordinary text files can. Therefore Enterprise Architect must enforce serialized editing of its Version Controlled Packages, and it is important that Team Foundation Server is configured to use 'exclusive checkouts' for XML files. Otherwise, TFS can return file statuses that make it look as if the Package file is not checked-out by another user when indeed it is.

You set exclusive checkouts in the TFS workspace through MS Visual Studio.

# Configure TFS to enforce exclusive check outs for XML files

Ste	Action
p	
1	Using Visual Studio, from the main menu select 'View   Team Explorer'.
2	In the 'Team Explorer' pane, right-click on the TFS Server name that is controlling the Enterprise Architect Package files, then from the context menu select 'Team Foundation Server Settings   Source

	Control File Types'.
3	Select the entry for XML files (or create an entry if necessary) then click on the Edit button.
4	Deselect the 'Enable file merging and multiple check out' checkbox.

### **Verify the TFS Workspace**

Enterprise Architect will be using the TFS command line client to commit file updates from the local working copy folder into the TFS repository. After creating the TFS workspace that maps your local working copy folder to a TFS repository folder, it is good practice to verify that the TFS workspace functions correctly before attempting to use it with Enterprise Architect. You need to be able to add files to TFS, place a check-out lock on the files and check-in changes to those files.

### Verify correct operation of a TFS Workspace

Ste p	Action
r	
1	Use Windows to open a command prompt window.
2	Select the directory you specified as the local working copy folder when creating the TFS workspace.
	For example:
	C:\> cd myTFSWorkingCopyFolder
3	Create a test file, such as <i>Test.xml</i> , containing the text ' <i>my TFS Test</i> '. For example:

C:\> echo my TFS Test > Test.xml

(The filename extension '.xml' is used because the TFS server should have been configured to allow exclusive checkouts for XML files.)

- 4 Using the command line client, execute each of these TFS commands:
  - tf.exe add Test.xml
  - tf.exe checkin Test.xml /override:"Manual check in." /comment:"a message"
  - tf.exe checkout /lock:checkout Test.xml
    Use your preferred editor to modify the file and save the changes.
  - tf.exe checkin Test.xml /override:"Manual check in." /comment:"a message"
  - tf.exe get . /recursive

### **Notes**

- All of the commands in step 4 should execute without any errors; in particular, you should be able to apply a checkout lock when checking out the file
- If the checkout command reports any errors, you might have to reconfigure the TFS workspace as a server based workspace, or you might have to configure the TFS

Server to use 'exclusive checkouts' for XML files

### **Create a CVS Environment**

You can use Concurrent Versions System (CVS) as a Version Control provider for Enterprise Architect. The first step in doing this is for a CVS administrator to install and configure the appropriate software. A number of basic tasks are performed in creating an operational CVS environment, and useful tools are available for performing some of these tasks.

### **Tasks in Creating a CVS Environment**

Task	Detail
Install server components	Executable files for CVS can be obtained from March Hare Software.  CVS server components are available to run on a wide range of different hardware and operating systems; Enterprise Architect is not affected by your choice of server components.
Create a repository	Please consult the official CVS documentation.
Create CVS users	Please consult the official CVS documentation.

Create a new repository module	It is recommended good practice to create a new repository module in CVS for each new Enterprise Architect model being added to Version Control with CVS.  Users should create a new local working copy folder from the module to be used with that model.  A repository module represents a project, or a set of related files in the repository.  TortoiseCVS can greatly simplify the process of creating new repository sub-trees.
Install client components	Executable files for CVS can be obtained from March Hare Software.  Enterprise Architect is a Windows based application - it requires a Windows based CVS command line client for integration.
Create a working copy folder	A working copy folder must exist on each users' machine, for Enterprise Architect to use when exporting and importing the Version Controlled Package files. It is this folder that is specified as the Local Project Path, when defining your Version Control Configurations.  The working copy folder is the 'sandbox' where you modify the controlled files.

The working copy folder is usually associated with a folder that exists within the Version Control repository. In CVS, to create a local working copy you perform an initial check-out of a folder from the CVS repository; this downloads a copy of the folder and its contents, to create your local working copy. TortoiseCVS can greatly simplify the initial check out of a working copy folder. The process of setting up and using CVS Setting up CVS under with Enterprise Architect under Wine is almost identical to the process when Wine/CrossO running natively under Windows, apart ver from minor differences in installing the CVS client and performing the initial checkout of the working copy folder.

### **Notes**

• If you do not already use CVS for Version Control, you should consider using Subversion instead; Subversion's client-server protocols provide a broader range of possibilities for connecting to remote servers, with easier set up of secure connections

• TortoiseCVS is a Windows shell extension; Enterprise Architect cannot use TortoiseCVS as its client, it must use the CVS command line client

### Prepare a CVS Local Workspace

In order to use CVS to provide Version Control of the Packages in a model, you need to prepare a functional CVS working copy folder that can be accessed through an Enterprise Architect Version Control configuration within that model.

### **Prepare a CVS Working Copy Folder**

Ste p	Action
1	Ask your System Administrator to install CVS and create a remote repository, with a module that you can use to control your Enterprise Architect Package files.
	Your administrator must create a username and password for you before you can make a connection.
2	Select or create a suitable directory to use as your CVS working copy directory.
3	Open a command prompt window and navigate to your CVS working copy directory. For example:  C:\> mkdir myCVSWorkSpace  C:\> cd myCVSWorkSpace

4 Log in to the remote CVS repository. For example: C:\myCVSWorkSpace> cvs -d:pserver:myUserID@ServerName:/reposPath login Replace myUserID with your CVS username, replace ServerName with the name of your CVS server and replace reposPath with the path to the repository on the server. A prompt for a password displays. 5 Enter your password. You are logged in to the CVS server. Perform the initial checkout of the CVS repository 6 module, into the local working copy directory. For example: C:\myCVSWorkSpace> cvs -d:pserver:myUserID@ServerName:/reposPath checkout moduleName (Replace moduleName with the name of the repository module that you want to check out.) A subdirectory is created in your current working directory, with the same name as the module being checked out. Any files already existing in the repository module are downloaded to the working copy folder as working copy files.

7 Verify that your CVS environment functions correctly.

### **Notes**

• Much of the process can also be performed (more simply) using the TortoiseCVS command 'Make New Module'

### Verify the CVS Workspace

After creating the CVS local working copy to hold the working copies of your Package files, you can verify that it functions correctly before attempting to use it with Enterprise Architect. You need to be able to add files to CVS, and commit changes to those files. You also need to be able to register as an editor of the file and retrieve the list of currently registered editors.

# Verify correct operation of a CVS working copy folder

Ste	Action
p	
1	Use Windows to open a command prompt window.
2	Select the directory you specified as the working copy in the cvs checkout command, when preparing the CVS workspace. For example:  C:\> cd myCVSWorkSpace
3	Create a test file, such as <i>Test.txt</i> , containing the text <i>CVS Test</i> . For example:  C:\> echo CVS Test > Test.txt
3	CVS Test. For example:

4	Execute these CVS commands:
	<ul> <li>cvs add Test.txt</li> </ul>
	<ul> <li>cvs commit -m"Commit comment" Test.txt</li> </ul>
	<ul> <li>cvs update Test.txt</li> </ul>
	• cvs edit Test.txt
	• cvs editors Test.txt
	The commands should execute without any errors and without prompting the user for any extra input.
	The editors command should produce output that resembles this:
	Test1.txt myUserID Tue Aug 9 10:08:43 2009 GMT myComputer
	C:\myCVSWorkSpace\moduleName
5	Take note of the userID that follows the filename.  Enterprise Architect must find and use this user ID when you create your Version Control configuration.

### **Notes**

• Your environment must be set up such that you can perform these operations without ever being prompted for input, such as user ID or password

### **TortoiseCVS**

TortoiseCVS is a Windows shell extension for CVS; it provides icon overlays in Windows Explorer that are useful as a tool for observing the status of your CVS controlled files. You can also use it to create your repository modules and check out local working copies from within Windows Explorer using simple menu commands.

You can download TortoiseCVS from: <a href="http://www.tortoisecvs.org">http://www.tortoisecvs.org</a>.

### **Notes**

• Enterprise Architect must use the CVS command line client to communicate with the CVS server; it cannot use TortoiseCVS

### **Create an SCC Environment**

You can use a Microsoft Common Source Code Control (SCC) compatible product as a Version Control provider for Enterprise Architect. The first step in doing this is for an administrator to install and configure the server and client applications. A number of basic tasks are performed in creating an operational SCC-based environment.

### Tasks in Creating an SCC Environment

Task	Detail
Install and configure your chosen Version Control product	A Version Control server component is typically installed on a dedicated server machine. All Enterprise Architect users who require access to Version Control must be able to connect to the server machine.  After installing the Version Control software, the administrator should also create Version Control user IDs for all users who require access to Version Control.  For further information, consult the product documentation for your particular Version Control product.

Create a new SCC project	It is good practice to create a new SCC Version Control project, or least a new folder within a project, for each Enterprise Architect project being added to Version Control with SCC. If you have a single Enterprise Architect project that contains many different models (for example, a DBMS hosted project with multiple model root nodes), you might choose to create a new SCC Version Control project for each separate model. For further information, consult the product documentation for your particular Version Control product.
Configure your SCC project to support exclusive check-outs for .XML files	The XMI-format files used for the Version Control of Enterprise Architect Packages can not be merged in the same way as ordinary text files can. Therefore, Enterprise Architect must enforce serialized editing of its Version Controlled Packages. As a consequence, it is important that your Version Control application is configured to use 'exclusive checkouts' for XML files.
Create a local	A working copy folder must exist on each

### working copy folder

users' machine, for Enterprise Architect to use when exporting and importing the Version Controlled Package files. It is this folder that is specified as the Local Project Path, when defining your Version Control Configurations.

The working copy folder is the 'sandbox' where you modify the controlled files. The working copy folder is usually associated with a folder that exists within the Version Control repository. Your Version Control product provides some means by which you associate a working copy folder with a repository folder. For further information, consult the documentation for your particular Version Control product.

### **Notes**

• When installing the client component software on users' PCs, check that the SCC client is also installed, as it might not be a part of the default installation

# **Upgrade at Enterprise Architect Version 4.5, Under SCC Version Control**

If you are working in Enterprise Architect release 4.5 or later and you open an SCC Version Controlled project that was created under a release earlier than 4.5, you must identify the SCC connection with a new unique ID. You can assign a name to the existing SCC configuration or associate the project with another configuration that has previously been assigned a unique ID.

By having a unique ID for each Version Control configuration, you can assign a configuration quickly and efficiently using configurations that have been created previously for other Version Controlled repositories. This enables you to configure the many Packages to use an existing Version Control repository; this can apply to Packages created for more than just one model enabling a great deal of flexibility.

# Upgrade an existing SCC Version Controlled project created before release 4.5, in Enterprise Architect release 4.5 or later

Ste	Action
p	

1	Open the project that has an SCC Version Control configuration created in Enterprise Architect earlier than version 4.5.  The 'Select or Create Unique ID for Version Control' dialog automatically displays.
2	On the dialog, either create an ID for an existing configuration or choose a previously created one from the 'Unique ID' drop-down list.
3	The existing SCC configuration is the initial value, represented by SCC-XXXXX; this number is not especially meaningful, therefore it is recommended that the configuration be given a meaningful name.
4	You can associate the Version Controlled Package with a previously-defined configuration by selecting an existing configuration from the 'Unique ID' drop-down list (if one exists).
5	After you have assigned the unique ID, click on the OK button to load the model.

### **Version Control Set Up**

Once you or an Administrator have installed and configured the Version Control product software, to start using Version Control you must first define a Version Control configuration within your project in Enterprise Architect, to be used to control the Packages in the project. You can define any number of Version Control configurations in a single model, but any given Package is associated with only one configuration.

### **Access**

Ribbon	Configure > Version Control > Project-VC
Context	Right-click on Package > Package
Menu	Control > Version Control Settings

### **Define Version Control Configuration**

Ste	Action
p	

1	On the 'Version Control Settings' dialog, click on the New button.
2	In the 'Unique ID' field, type a suitable configuration name.
3	Select the Type of Version Control product you are connecting to, by clicking on the corresponding radio button.
4	At this point, the middle section of the dialog changes to display a collection of fields specific to the type of Version Control configuration you are defining.  Enter details relating to the Version Control workspace that this configuration is to use.
5	Click on the Save button. The new configuration is added to the Defined Configurations list.
6	If you want to create another Version Control configuration, return to step 1.  When you have finished defining your Version Control configurations, click on the Close button.

### **Notes**

- Version Control Configuration details are stored in the user's Windows Registry settings, but each project stores a list of the configurations it uses, so that Version Control connections can be initialized as the project is being loaded
- If you are using the Corporate or extended editions of Enterprise Architect with security enabled, the administrator must also set up access permissions to configure and use Version Control

### Re-use an Existing Configuration

Once a Version Control configuration has been defined for use in one project, it is possible to re-use that configuration in other projects to provide access to:

- An already existing Version Control environment (a working copy directory and its associated repository that is already in use)
- Version Controlled Packages that were created (and Version Controlled) in another project

### **Access**

Ribbon	Configure > Version Control > Project-VC
Context Menu	Browser window   right-click on Package   Package Control   Version Control Settings

### Select existing configuration

Ste	Action
-----	--------

p	
1	On the 'Version Control Settings' dialog, click on the New button.  The various fields on the dialog are cleared, ready for data entry.
2	In the 'Unique ID' field, click on the drop-down arrow and select one of the previously-defined Version Control configurations.  The details of the selected configuration are displayed in the dialog.
3	Click on the Save button.  The configuration details are saved and are ready for use in the current project.

### **Version Control Settings**

Defining Version Control settings within Enterprise Architect should only be performed after you have successfully created the Version Control environment that you intend to use to control your Package files. If you have not yet done so, please refer to the Help topic *Applying Version Control in a Team Environment* for a summary of what is required.

To set up a Version Control configuration on your model, or update an existing Version Control configuration, you define a number of settings that control how the status of your model is communicated to your Version Control system. You define these settings using the 'Version Control Settings' dialog.

### **Access**

Ribbon	Configure > Version Control > Project-VC
Context	Right-click on Package > Package
Menu	Control > Version Control Settings

### **Configuration Options**

Option	Action
This model is private	Select to specify that this model database is to be accessed by just a single user (Private Model).  Leave unselected (the default) or deselect to specify that the database is to be accessed by multiple concurrent users (Shared Model).  If in doubt, use the default setting.
Save nested Version Controlled Packages to stubs only	Select to specify that the exported XMI file for a Version Controlled Package will contain Package stubs (place holders) for nested Version Controlled child Packages (recommended).  Deselect to specify that the exported XMI file will contain the full content of nested Version Controlled child Packages.
For all packages, create placeholders for external references	Select to force all XMI 1.1 imports across the model to exclude incoming relationships and instead create external references.  If the 'Create placeholders for missing External References during XMI 1.1/2.1

	Import' checkbox is not selected in the XML Specifications options for a user, this field overrides that setting.
Unique ID	Specify a name that uniquely identifies the configuration. Either:
	Type a name to identify a new configuration, or
	<ul> <li>Click on the drop-down arrow and select the name of a configuration previously defined in a different project (if any exist)</li> </ul>
Type	Click on the appropriate radio button for the type of Version Control system you are associating with this configuration.  The middle section of the dialog changes to display a collection of fields relating to the type of Version Control configuration
	you are defining. Set the type to SCC for:
	MS Visual Source Safe
	• Rational Clear Case
	<ul><li>Perforce</li><li>AccuRev</li></ul>
	<ul> <li>Any other SCC-compatible clients</li> </ul>
	For any other product that you are using, select the type that matches the product -

	CVS, Subversion or TFS.
New	Click on this button to clear the fields and create a new Version Control configuration.
Save	Click on this button to save the details of a new or updated configuration.
Delete	Click on an entry in the Defined Configurations list and click this button to remove the definition of the selected configuration from this model.
Defined Configurations	Review a list of configurations that are in use in the current model.
In future, do not prompt for incomplete configuration s	Select to specify that the user is not prompted to complete the definition of configurations that are not fully specified (the default).  Deselect to prompt the user to complete configurations that are not fully defined.
Close	Close the 'Version Control Settings' dialog.
Help	Display this Help topic.

### **Notes**

- It is important that, for any given Version Controlled Package file, any user accessing that file from any model uses Version Control configurations having the same Unique ID
- When you first open a model that was created by another user and that uses Version Control, the Version Control configuration(s) used by that model do not yet exist in your Windows registry settings; you have to complete the definitions of those configurations before you can use Version Control in that project
- If User Security is enabled, you must have 'Configure Version Control' permission to set up Version Control options for the current model
- It is possible to use multiple Version Control configurations in the same model

### **SCC Settings**

When you are setting up your Version Control configurations on the 'Version Control Settings' dialog, and you set the configuration type to 'SCC', the dialog presents a set of fields specific to SCC-based configurations. You can then define details such as:

- The working copy folder to be used with the configuration
- The details necessary to connect to the SCC Version Control system

You set the Version Control configuration type to SCC for version Control providers such as:

- MS Visual Source Safe
- Rational Clear Case
- Perforce
- AccuRev
- Any other SCC-compatible clients

### Access

Ribbon	Configure > Version Control > Project-VC : Type: SCC
Context	Right-click on Package > Package
Menu	Control > Version Control Settings:

Type: SCC

### **Settings**

Option	Action
Local Project Path	Displays the full path of the folder that contains the local (working) copies of the XMI Package files.  This field is read-only; its value can only be set through use of the Select Path button.
Select Path	Click on this button to choose the Local Project Path, by opening a file browser dialog and navigating through the file system to the appropriate folder.  • After you choose the appropriate folder path, the 'Select SCC Provider' dialog displays, listing all SCC providers that are installed on the current workstation; choose the SCC provider to use and click on the OK button  • At this point, the SCC client opens its own dialog to prompt you for information; SCC products implement

	this functionality in varied ways, but typically you are prompted to log in to the Version Control system, then prompted to choose the SCC project to use and possibly a (server) folder contained within that project  • At the conclusion of this process, all of the SCC details should be filled in; you can then save the definition by clicking on the Save button on the 'Version Control Settings' dialog
Current User	Displays the user name used to log on to the Version Control system that is accessed through this configuration.  This field is read-only; the value it displays is retrieved from the SCC client.
SCC Provider	Displays the name of the SCC provider.  This field is read-only; the value it displays is retrieved from the SCC client.
SCC Project	Displays the name of the SCC Project that this configuration attaches to. This field is read-only; the value it displays is retrieved from the SCC client.

• You define the SCC-specific details as part of the broader process of setting up a Version Control Configuration on the 'Version Control Settings' dialog

# **CVS Settings**

When you are setting up your Version Control configurations on the 'Version Control Settings' dialog, and you set the configuration type to CVS, the dialog presents a set of fields specific to CVS-based configurations. You can then define details such as:

- The working copy folder to be used with the configuration
- The path to the CVS command line client

#### **Access**

Ribbon	Configure > Version Control > Project-VC : Type: CVS
Context Menu	Right-click on Package > Package Control > Version Control Settings: Type: CVS

## Settings

Option	Action

Working Copy Path	Displays the full path of the folder that contains the local (working) copies of the XMI Package files.  This field is read-only; its value can only be set through use of the Select Path button.
Select Path	Click on this button to choose the working copy path, by opening a file browser dialog and navigating through the file system to the appropriate folder.
Current User	This field is read-only; its value is retrieved from a file named CVS\Root, located in the folder selected using the Select Path button.
CVS Exe Path	Displays the full path of the CVS command line client executable file.  This field is read-only; its value can only be set through use of the Select Path button.
Select Path	Click on this button to specify the path to the CVS command line client, by opening a file browser dialog and navigating through the file system to locate the appropriate file.

VC
Time-Out
Value

Specify the amount of time that Enterprise Architect waits for a CVS command to complete; if the command does not complete within the allowed time, the system displays a Time-out error message, detailing the command that failed to complete.

This single time-out value is applied to all Version Control Configurations (of types SVN, TFS and CVS) that the user accesses from this workstation.

- When connecting to a remote CVS repository, the 'Current User' field should display the user name used to log into that repository; if this does not happen, it indicates that Enterprise Architect cannot extract the user name from the file ...\WorkingCopyPath\CVS\Root and the configuration does not work correctly
- You define the CVS-specific details as part of the broader process of setting up a Version Control configuration on the 'Version Control Settings' dialog

# **SVN Settings**

When you are setting up your Version Control configurations on the 'Version Control Settings' dialog, and you set the configuration type to 'Subversion', the dialog presents a set of fields specific to Subversion-based configurations. You can then define details such as:

- The working copy folder to be used with the configuration
- The path to the Subversion command line client

#### **Access**

Ribbon	Configure > Version Control > Project-VC : Type: Subversion
Context Menu	Right-click on Package > Package Control > Version Control Settings: Type: Subversion

## Settings

Option	Action

Working Copy Path	Displays the full path of the folder that contains the local (working) copies of the XMI Package files.  This field is read-only; its value can only be set through use of the Select Path button.
Select Path	Click on this button to choose the Working Copy Path, by opening a file browser dialog and navigating through the file system to the appropriate folder.
Subversion Exe Path	Displays the full path of the Subversion command line client executable file.  This field is read-only; its value can only be set through use of the associated Select Path button.
Select Path	Click on this button to specify the path to the Subversion command line client, by opening a file browser dialog and navigating through the file system to locate the appropriate file.
VC Time-Out Value	Specify the amount of time that Enterprise Architect should wait for a Subversion command to complete; if the command does not complete within the allowed time, the system displays a

Time-out error message, detailing the command that failed to complete.

This single time-out value is applied to all Version Control Configurations (of types SVN, TFS and CVS) that the user accesses from this workstation.

#### **Notes**

• You define the Subversion-specific details as part of the broader process of setting up a Version Control configuration on the 'Version Control Settings' dialog

# **TFS Settings**

When you are setting up your Version Control configurations on the 'Version Control Settings' dialog, and you set the configuration type to 'TFS', the dialog presents a set of fields specific to TFS-based configurations. You can then define details such as:

- The working copy folder to be used with the configuration
- The user name and password to log in to the TFS server
- The path to the TFS command line client

#### **Access**

Ribbon	Configure > Version Control > Project-VC: Type: TFS
Context Menu	Right-click on Package > Package Control > Version Control Settings: Type: TFS

## **Settings**

Option Action	
---------------	--

Working Copy Path	Displays the full path of the folder that contains the local (working) copies of the XMI Package files.  This field is read-only; its value can only be set through use of the associated Select Path button.
Select Path	Click on this button to choose the Working Copy Path. The file browser dialog opens, through which you navigate through the file system to the appropriate folder.
Server Name	Displays the name of the TFS Server that is associated with the working copy folder specified in the 'Working Copy Path' field.  This field is read-only; Enterprise Architect retrieves the value it displays by querying the TFS client.
Workspace Name	Displays the name of the TFS Workspace that is associated with the working copy folder specified in the 'Working Copy Path' field.  This field is read-only; Enterprise Architect retrieves the value it displays by querying the TFS client.

User Name	Type in the user name with which to log into the TFS Server.
Password	Type in the password with which to log into the TFS Server.
Display Name	TFS 2013 and later releases use a Display Name to report on who owns a checkout lock on a file. TFS 2010 uses AccountID when reporting lock owners and so does not require a Display Name.  If using TFS 2013, type in your TFS Display Name as shown in the User column of the Visual Studio Source Control Explorer when you checkout a file.
Checkout Locks Required	This checkbox defaults to selected.  TFS 2013 supports the use of Local workspaces, but these do not support checkout locks. If you want to use TFS Local workspaces (not recommended), you must deselect this checkbox.  Otherwise, leave the checkbox selected. It is recommended that all workspaces used for Version Controlling Enterprise Architect Package files are set as 'Server' workspaces.

TFS Exe Path	Displays the full path of the TFS command line client executable file.  This field is read-only; its value can only be set through use of the associated Select Path button.
Select Path	Click on this button to specify the path to the TFS command line client.  The file browser dialog opens, through which you navigate through the file system to the appropriate folder.
VC Time-Out Value	Type in the number of seconds that Enterprise Architect should wait for a TFS command to complete; if a command does not complete within this allowed time, the system displays a Time-out error message, detailing the command that failed to complete. This single time-out value is applied to all Version Control configurations (of types SVN, TFS and CVS) that the user accesses from this workstation.

- If you automatically log in to TFS through a path external to Enterprise Architect (for example, through MS Integrated Security), you can leave the 'User Name' and 'Password' fields blank
- If the 'Password' field is blank, Enterprise Architect retrieves your Windows username and uses that value when determining whether a Package file is checked out to you or to another user
- TFS Version Control can also be accessed using the TFS MSSCCI client; to make use of the TFS MSSCCI client, please define an SCC based Version Control configuration
- You define the TFS-specific details as part of the broader process of setting up a Version Control configuration on the 'Version Control Settings' dialog

## **Use Version Control**

Once your Version Control product is installed and you have created a suitable environment, Enterprise Architect can make use of that environment to control the Packages in your project. Version Control provides a range of facilities, as outlined in this table.

## **Facilities**

Facility	Detail
Define Version Control Settings	Version Control Configurations are used by Enterprise Architect to communicate with your Version Control system.  You define one or more Version Control configurations in your project and then use those configurations to control the Packages in your project.
Configure a Package	To put a Package under Version Control you mark the Package as a controlled Package, specify the Version Control configuration to control it, and associate an XMI file with the Package.
Check In a	Checks in all Packages involved in a

Model Branch	particular unit of work, as a single operation.  Checking-in updates the reference version of a Package or group of Packages in the model.
Check Out a Model Branch	Checks out all Packages within a selected model branch as a single operation, so that you can update modeling objects within them.
Check In a Package	Checks in the Package currently selected in the Browser window.  Checking-in updates the reference version of a Package or group of Packages in the model.
Check Out a Package	Checks out the Version Controlled Package currently selected in the Browser window, so that you can update modeling objects within it.
Undo Check Out of a Package	Reverses the check-out of a Package, discarding any modifications that have been made by restoring the Package content to the latest revision held in Version Control.
Import a	Retrieves Packages from Version Control

Package From Version Control	that have been created by other users, or by you in another model, and imports them into your current model.
Apply Version Control to a Model Branch	Applies Version Control to all Packages within the selected model branch, in a single operation.  In this context, a model branch is a Package in the Browser window, and all of the Packages contained within it.
Export a Version Controlled Model Branch	Exports Version Control information about the root Package of a model branch, that is used to simplify the process of exporting and importing a hierarchy of Packages from one model to another.
Import a Model Branch From Version Control	Uses Enterprise Architect's Model Branch files, of which there are few, to retrieve information about the root Package file and to import the model branch.  Model branch files can simplify the process of exporting and importing a hierarchy of Packages from one model to another.
View	Displays the change history of Version

Package Revision History	Controlled Packages. You can also check out a prior revision of the Package for editing, effectively rolling-back to a prior revision of the Package.
Validate Package Configuratio ns	You can test the validity of the Version Control settings associated with each Version Controlled Package within your current model.
Resynchroniz e the Status of Version Controlled Packages	Re-synchronizes the Version Control status of Packages within your project with the status reported by your Version Control provider.

- Database replication should not be combined with Version Controlled Packages
- If the Packages under Version Control contain any alternative images, you can export the images to the Version Control repository when you check in the Packages, by setting the 'Export alternate images' option on the 'Preferences' dialog

# **Configure Controlled Package**

Once your Version Control application is set up and you have Version Control configurations in place, you can place the individual Packages in your model under Version Control. To put a Package under Version Control, you:

- Flag the Package as a controlled Package
- Specify the Version Control configuration to control it and
- Associate an XMI file with the Package

You can then export and import the Package data to and from the file and issue commands to the Version Control system.

## Access

Ribbon	Configure > Version Control > Package-VC
Keyboard Shortcuts	Ctrl+Alt+P

## **Apply Version Control to a single Package**

Ste p	Action
1	Click on the 'Control Package' checkbox to select it, indicating that this Package is to be controlled.
2	Click on the 'Version Control' drop-down arrow and select the Version Control configuration to be used to control this Package.
3	<ul> <li>The 'XMI Filename' field displays a default filename for the Package export file, based on the Package name.</li> <li>Optionally, modify the filename. Either:</li> <li>Type a new name, or</li> <li>Click on the button to open a file selection dialog</li> <li>The target file must be located within the working copy folder of the selected Version Control configuration, or one of its sub-folders.</li> </ul>
4	The 'Version ID' field defaults to '1.0'. Optionally, change this to a different version number.
5	The 'Owner' field defaults to your user name. Optionally, type or select the name of the user who

	actually owns the Package.
6	Click on the OK button. The 'Add Package to Version Control' dialog displays.
7	Optionally, clear the 'Keep checked out' checkbox.  After applying Version Control, the Package either remains checked-out for editing, or is checked-in and locked against editing, depending on this setting.
8	Click on the OK button. The 'Add Comment' dialog displays.
9	Optionally, add any further comments to the default comment.  Enterprise Architect provides a default comment that includes the current date & time.
10	Click on the OK button.  The current Package is exported to the nominated XMI file, which is then committed to Version Control. The Package icon in the Browser window is updated to reflect the Package's Version Control status.

• If you are using the Corporate or extended editions of Enterprise Architect with security enabled, these features are only available to users who have been granted permission to configure and use Version Control

# **Apply Version Control To Branches**

It is possible to apply Version Control to all Packages within a selected model branch, in a single operation. In this context, a model branch is a Package that is currently selected in the Browser window, and all of the Packages contained within it.

## **Access**

Context Menu Package Control   Add Branch to Version Control		i i
--	--	-----

# Apply Version Control to all Packages within a selected model branch

Ste	Action
p	
1	On the 'Apply VC to Branch' dialog, click on the
	drop-down arrow in the 'Version Control
	Configuration' field and select the configuration to

	use.
2	Optionally, tick the checkbox 'Export as Model Branch'.
	Once the Version Control operation is complete a Model Branch file (.EAB file) is created for this branch.
3	Click on the OK button.  The system creates a number of sub-folders within the Version Control working copy folder, then exports all of the Packages within the selected model branch. The system generates filenames for the XMI files, based on the Package GUIDs.

- The Version Control configuration to be used in this operation must be defined within the model before selecting this command
- When invoked on the model root node, this command applies Version Control to every Package within the model

# **Package Version Control Options**

When you have set up a Package for Version Control, you gain access to a range of Version Control operations that can be performed on that Package, such as:

- Open the dialog for working with baselines of the Package
- Check-in and check-out single Packages or a selected hierarchy of Packages
- Update Packages to the latest revision from the Version Control repository
- Inspect the revision history or properties of the XMI file associated with a Package
- Revert a Package to a previous revision
- Compare the current model content of a Package, against the latest revision of the Package in Version Control
- Import and export hierarchies of Packages (model branches) to and from the model, through the Version Control system
- Synchronize the status of a Package, with the Version Control system

#### Access

Context	Right-click on Version Controlled

Menu	Package > Package Control
------	---------------------------

# **Options**

Option	Action
Check In Branch	Check-in Packages contained in the currently selected model branch (that is, the selected Package and all of its child Packages).  The 'Select Packages to Check In' dialog lists all Version Controlled Packages within that branch that are checked out to you; you can then select Packages in the displayed list, to be submitted for check-in.
	You can also choose to keep the Packages checked-out after committing a new revision to Version Control.
Check Out Branch	Recursively check out all Packages contained within the currently selected model branch (that is, the selected Package and all of its child Packages) that are Version Controlled and checked-in.

Check In	Commit a new revision of the currently selected Package to the Version Control repository and lock the Package against further editing.  Only available for Packages that you have checked-out yourself.
Check Out	Synchronize the currently selected Package with the latest revision from the Version Control repository and unlock the Package to allow editing. Only available for Packages that are not already checked-out (and whose associated Package file is not checked-out).
Undo Check Out	Restore the selected Package to the latest revision in the Version Control repository and lock the Package against further editing.
Put Latest	Commit a new revision of the currently selected Package to the Version Control system, while keeping the Package checked-out.  This is equivalent to checking a Package in and immediately checking it back out again.

	Only available for Packages that you have checked-out yourself.
Get Latest	Synchronize the currently selected Package with the latest revision from the Version Control repository.  Available only for Packages that are checked in.
Get All Latest	Updates all of the Version Controlled Packages in the project, to the latest revision retrieved from Version Control. Only updates Packages that are currently checked in.  Once the latest revisions are retrieved, the system scans all the controlled Packages and fixes any missing cross-references by comparing the Package with its XMI 1.1 file.  If the cross-reference information in the XMI does not match the model, the system updates the model with the information from the XMI and records this update in the System Output window. You can roll back such updates by selecting the entry in the System Output window and using the context menu option 'Rollback Update' (or 'Rollback Selected Updates' if multiple entries are

## selected).

- Closing the model clears the entries in the System Output window
- An entry in the System Output window is also cleared as and when you roll-back the update for it

## Scan XMI and Reconcile Model

Scan the Package XMI files associated with each of the project's controlled Packages and restore any diagram objects or cross-references that are detected as missing from the project.

This function is useful in team environments where each user maintains their own private copy of the model database (that is, multiple private project files) and model updates are propagated through the use of controlled Packages. It provides no benefit when the model is hosted in a single shared database that is accessed by all team members.

Each controlled Package is compared with its associated XMI file and, if the cross-reference information in the model does not match the XMI, the system updates the model with the information from the XMI and records the update in the System Output window.

You can roll back such updates by

right-clicking on the entry in the System Output window and selecting the 'Rollback Update' option (or 'Rollback Selected Updates' if multiple entries are selected).

Closing the model clears the entries in the System Output window; an entry in the window is also cleared as and when you roll-back the update for it.

This functionality is invoked automatically as part of the 'Get All Latest' operation.

When working in an environment that uses a Private Model deployment and your model contains a significant number of cross-Package references, it is recommended that you invoke 'Scan XMI and Reconcile Model' from time to time, following the re-importation of controlled Packages - for example, after using 'Get Latest' to update a number of Packages - or after performing a number of Package check-outs.

- As a general rule, avoid running 'Scan XMI and Reconcile Model' while you have uncommitted changes in your model; generally, you:
  - Check-out a number of Packages
  - Invoke 'Scan XMI and Reconcile

	Model'  - Make your modifications  - Commit any outstanding changes before you check-out more Packages and run 'Scan XMI and Reconcile Model' again
File Properties	Display Version Control properties pertaining to the XMI export file associated with the currently selected Package; this also identifies who has checked out the Package.
File History	Display change history information for the currently selected Package.  Revert to or check-out a prior revision of the Package.
Compare with Controlled Version	Compare the currently selected Package with the latest revision of its associated XMI file retrieved from Version Control.
Add Branch to Version Control	Apply Version Control to all Packages within a selected model branch, in a single operation.  In this context, a model branch is a Package that is currently selected in the Browser window, and all of the Packages

	contained within it.
Export as Model Branch	Export a newly created model branch from your own private copy of a model.
Import a Model Branch	Retrieve a model branch and import it into either the source model or another model.
Get Package	Access Packages in the Version Control repository that are not currently available in your model.
Re-synch Status With VC Provider	Update the Version Control status value recorded for the selected Package in the project to match the value reported by the Version Control provider, without performing an XMI import or export.  Use this function when the Package's Version Control status recorded in your project is out of synchrony with the Version Control status reported by your Version Control provider.
Version Control Settings	Display the 'Version Control Settings' dialog.

- You set up Version Control using options from the project 'Version Control' submenu
- If the selected Package is not under Version Control, a different set of options is available
- If a Version Control configuration has not been defined for the model, no options for using Version Control are available, only the options for configuring Version Control

# **Check Out a Package**

When you need to work on a Version Controlled Package, you check it out. The local XMI file associated with the Package is then checked-out from Version Control. No other user can check out the Package to make changes to it until it has been checked in again.

#### Access

Context	Right-click on Package > Package
Menu	Control > Check Out
Keyboard Shortcuts	Ctrl+Alt+L

## **Check out a single Package**

The Package file is imported into your model, and the 'Package' icon is updated to reflect the change in the Package's Version Control status.

When working in a Private Model, if the system detects that the Package content in the model is already up to date with the latest revision of the Package file retrieved from Version Control, then the 'Import Package' dialog displays first. This dialog is not displayed for a Shared Model.

These options are available:

- Force Reload From XMI reload the Package from XMI regardless of whether it is up to date or not
- Accept current Package select to skip the process of re-importing the Package from XMI
- Refresh model view select to refresh the Browser window and diagrams, by reloading the Package content from the project database
- Always use these settings when selected, if you subsequently check out a Package that is found to be up to date, the same settings are applied again without displaying the dialog

- If you check out a Version Controlled Package whilst offline, the 'Package' icon has a red figure 8 in front of it
- If you have selected the 'Always use these settings' checkbox and you want to reconfigure the 'Import Package' dialog, press the Ctrl key whilst you select the 'Package Control | Check Out' context menu option; the dialog displays and you can change the settings

# **Undo Check Out of a Package**

If you check out a Package and then decide not to proceed, you can undo the check-out and discard any modifications that have been made, by restoring the Package content to the latest revision held in Version Control. The Package returns to a checked-in state and subsequently can be checked out by any user, including yourself if, for example, you need to reverse incorrect changes before checking the Package out and starting again.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Undo Check Out

## Undo check out of a selected Package

A confirmation dialog displays; click on the OK button.

The latest revision of the Package is retrieved from Version Control and re-imported into your model. The icon against the Package in the Browser window is updated to reflect the change in the Package's Version Control status.

## Check In a Package

When you have finished working on the contents of a Package under Version Control, and you want to return it to the model for other users to see, you check it in.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Check In
Keyboard Shortcuts	Ctrl+Alt+S

## **Check in a single Package**

Ste	Action
p	
1	The selected Package is exported and the 'Add Comment' dialog displays. A default comment is provided that contains the current date and time.  Optionally, modify the default check-in comment

2 Click OK.

The Package file is checked-in to Version Control and the Package icon is updated to reflect the change in Version Control status.

### **Check Out a Model Branch**

If you need to check out a number of related Packages involved in a particular unit of work, to update the contents, you can do so in a single operation by checking out the whole model branch that contains them.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Check Out Branch

## Check out a sub-tree of model Packages

Ste	Action
p	
1	The selected root-node Package and all of its contained sub-Packages are recursively checked out. Any Packages that cannot be checked-out are listed in a message box, with a brief description of the problem; for example: <i>The Package is already checked out by user 'Fred'</i> .

When Project Security is enabled in Lock to Edit mode, Enterprise Architect prompts you to apply a User Lock throughout the selected model branch before proceeding.

### **Check In a Model Branch**

If you need to check in a number of related Packages involved in a particular unit of work, and that you have updated, you can do so in a single operation by checking in the whole model branch that contains them. You can also commit new revisions of the affected Packages as you complete milestones, whilst keeping the Packages checked-out for further editing.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Check In Branch

## Check in Packages from within a model branch

Ste	Action
p	
1	The 'Select Packages to Check-in' dialog lists all
	Version Controlled and checked-out Packages within

the selected model branch. By default, the entire list is selected. Optionally: · Click an individual Package to select just that Package · Ctrl+click on an individual Package to add or remove it from the selection Shift+click on a range of Packages to select them • Click on the All button to select all listed Packages • Click on the None button to clear the selection 2 Optionally, you can commit into Version Control a new revision of all selected Packages, while keeping those Packages checked out for further editing. To do this, select the 'Keep packages checked-out after committing new revision' checkbox. 3 Click on the OK button. The 'Add Comment' dialog displays. A default comment is provided that contains the current date and time. This comment is applied to all Packages that are checked in. 4 Optionally, modify the default check-in comment. 5 Click on the OK button. The selected Packages are exported and checked-in. The Package icons are updated to reflect any change

in Version Control status. If you opted to keep Packages checked out, there is no change in status.

# Update to the Latest Revision of Selected Package

When you are part of a team working in a Distributed Model environment, you will want to periodically update your model with the changes that other team members have committed into Version Control. You can transfer the other users' updates from Version Control into the selected Package in the Browser window.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Get Latest

### **Update Package to latest revision**

The local XMI file associated with the Package is updated to the latest revision from Version Control. The XMI file is imported into your model database, updating the Package in your model.

When working in a Private Model, if the system detects that the Package content in the model is already up to date with the latest revision of the Package file retrieved from Version Control, then the 'Import Package' dialog displays first. This dialog is not displayed for a Shared Model.

These options are available:

- 'Force Reload From XMI' reload the Package from XMI regardless of whether it is up to date or not
- 'Accept current Package' select to skip the process of re-importing the Package from XMI
- 'Refresh model view' select to refresh the Browser window and diagrams, by reloading the Package content from the project database
- 'Always use these settings' when selected, if you subsequently check out a Package that is found to be up to date, the same settings are applied again without displaying the dialog

#### **Notes**

- The 'Get Latest' command is disabled for any Package that is checked-out (to anybody) in the currently loaded project
- When using a Shared Model environment, where all users are connected to a single model database, you should reload the Package from the database, rather than using the 'Get Latest' command
- If you have selected the 'Always use these settings' checkbox and you want to reconfigure the 'Import

Package' dialog, press the Ctrl key whilst you select the 'Package Control | Get Latest' context menu option; the dialog displays and you can change the settings

# Update to the Latest Revision of All Packages

When you are part of a team working in a Distributed Model environment, you will want to periodically update your model with the changes that other team members have committed into Version Control. You can transfer the other users' updates to all Version Controlled Packages into the currently loaded project.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Get All Latest

## Update all Packages in project to latest revision retrieved from Version Control

All the local XMI files for all the Version Control configurations used in the project are updated to the latest revision from Version Control. The system then scans the Packages in the model, to determine which ones are up to date and which are not, compared to the latest revisions of

the associated Package files.

A prompt displays, providing these import options for Packages that are up to date:

- Import changed files only
- Always import
- Prompt for each file

Click on the OK button. The Version Controlled Packages in your project are updated according to the option you selected; if you chose the 'Prompt for each file' option, a prompt displays to confirm import of each file.

#### **Notes**

- There is no need to re-import Packages that are already up to date re-importing Packages first deletes them from the project and then re-imports them from the XMI file, which is time consuming as well as unnecessary; we strongly recommend using the default option 'Import changed files only'
- The 'Get All Latest' command does not update any Package that is checked-out (to anybody) in the currently loaded project; otherwise, any changes not yet committed to Version Control would be discarded
- When using a Shared Model environment, where all users are connected to a single model database, the information in the model database is always the same as, or ahead of, what is committed into Version Control; in this situation,

the Get All Latest command will simply refresh your view of the model database, by reloading diagrams or reloading Package content in the Browser window

## **Include Other Users' Packages**


Other users might be developing Packages in their own models that you could use in your model, or you might have other models containing Packages that you want to use in the current model. Unless you are sharing an SQL database or project file, those Packages are not automatically available to you. However, if the Packages have been placed into Version Control, you can import them into your model as children of one of your model's Packages.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Get Package

# Import Packages from Version Control into current model

Ste	Action
p	
1	On the 'Get Shared File' dialog, click on the



#### **Notes**

- You must have access to the Package files through the Version Control system and you must define a Version Control configuration through which to access those files
- The Version Control configuration must use the same unique ID that was originally used to add the Package to Version Control
- XMI Package files associated with Packages that are already part of your project, are NOT included in the list of files available for import

## **Export Controlled Model Branch**

Applying Version Control to a model can result in many XMI files being placed under Version Control. It might then be hard to locate and import the file corresponding to the root of a particular model branch. Using Model Branch Files (.eab files) overcomes this problem by making it easier to export and import Package hierarchies from one model to another.

You could export a newly created model branch from your own private copy of a model so that, for example:

- Another user can import that branch into their own private copy of the same model
- It can be imported for inclusion as a common branch in a number of different models

#### **Access**

Context	Right-click on Package > Package
Menu	Control > Export as Model Branch

# Create a Model Branch File to represent a Package hierarchy stored in Version Control

Ste p	Action
P	
1	On the 'Export as Model Branch' dialog, in the 'EAB Filename' field, type a name for your Model Branch File.
	Alternatively, click on the button and browse for the file location.
	Note that the Package name is supplied as a default.
2	Click on the OK button.
	A branch file is created to represent the selected
	Package. The branch file is committed to Version
	Control using the same Version Control
	configuration that controls the Package you selected.

#### **Notes**

- You can specify any file name, including sub-folder names, as long as the file is contained in or below the working folder of your Version Control configuration
- The facility is only enabled for Packages that are already under Version Control

## **Import Controlled Model Branch**

Applying Version Control to a model can result in many XMI files being placed under Version Control. It could then be hard to locate and import the file corresponding to the root of a particular model branch, if you want to:

- Retrieve a model branch created by another user in a private copy of a model, to import it into your own private copy of the same model
- Retrieve a model branch that is common in many models, for inclusion in a new model

Model Branch Files overcome this problem by simplifying the retrieval of Package hierarchies for use in other models. You use Enterprise Architect's Model Branch Files, of which there are few, to retrieve information about the root Package file - such as the name and type of the Version Control configuration for the selected Package, and the relative filename of the Version Controlled XMI file associated with the Package. The system then uses this information to import the branch into your model.

### **Prerequisites**

Before you begin, you must have:

- An operational Version Control environment that can be accessed by Enterprise Architect, and
- All of the Version Controlled Package files and the model

branch file associated with the model branch to import, in a valid and accessible working copy folder

#### **Access**

Context Menu	Right-click on target Package for import > Package Control > Import a Model Branch
-----------------	--

## **Import a Model Branch**

Ste p	Action
1	<ul> <li>On the 'Import VC Model Branch' dialog, either:</li> <li>Use the lower portion of the dialog to select a model branch file (this is the simpler option if the associated Version Control configuration has already been saved in the current model; continue to step 2)</li> <li>OR</li> <li>Click on the Find a Model Branch (.EAB) file</li> </ul>
	button (this option is useful when you have not yet

	defined the Version Control configuration that is associated with the model branch to be imported; see the <i>Manually Locating Model Branch Files</i> topic)
2	Click on the drop-down arrow in the 'Select a Version Control Configuration' field and select a configuration.  A list of .eab files controlled by that configuration is displayed in the 'Select a Model Branch (.EAB) file' list.
3	Select the Model Branch File you need, then click on the OK button.  The system imports the root Package specified in the Model Branch File and recursively imports and populates all the sub-Packages contained in the root Package.

#### **Notes**

• The Import a Model Branch command is only enabled for Packages that you (the current user) are able to edit, as the imported model branch is inserted into the model under your selected Package

## **Manually Locating Model Branch Files**

When importing a Model Branch File from Version Control, you might not have the associated Version Control configuration saved in the model that is receiving the import. In this situation, it is simpler to manually browse the file system to locate the Model Branch File (.eab) and let Enterprise Architect derive the details of the configuration from the branch file you select.

### **Prerequisites**

Before you begin, you must have:

- An operational Version Control environment that can be accessed by Enterprise Architect, and
- All of the Version Controlled Package files and the model branch file associated with the model branch to import, in a valid and accessible working copy folder

#### Access

Context	Right-click on target Package for import
Menu	> Package Control > Import a Model
	Branch: Find a Model Branch (.EAB)

file

### **Locate the Model Branch File**

Ste p	Action
1	Access the 'Import VC Model Branch' dialog, then browse for and select the Model Branch File that represents the model branch to import.
2	Click on the Open button.  If the Version Control configuration referenced by the file is fully defined within the current model, the import commences at this point.  Otherwise, Enterprise Architect displays a dialog prompting you to complete the required configuration.
3	Click 'Yes' to proceed with completing the definition of the Version Control configuration.  The 'Version Control Settings' dialog is displayed.
4	Complete the definition of the configuration.  (Typically this involves simply specifying the

	working copy folder.)
5	Click on the Save button.  The configuration details are saved.  The import of the model branch proceeds.

#### **Notes**

• The Import a Model Branch command is only enabled for Packages that you (the current user) are able to edit, as the imported model branch is inserted into the model under your selected Package

## **Review Package History**

It is possible to review the change history of Version Controlled Packages by examining previous revisions. If necessary, you can check out one of these earlier revisions of a Package for editing, effectively rolling-back to that prior revision of the Package.

#### **Access**

Context	Right-click on Package > Package
Menu	Control > File History

# Review change history of a version-controlled Package

Ste	Action
p	
1	For Version Control environments using Subversion,
	CVS or TFS command line clients, the 'File Version
	History' dialog displays.
	Click on a revision number in the 'Revisions' field, to

select that revision and view its log entry.

For Version Control environments using SCC based clients, your particular product opens its own 'File Version History' dialog.

- On the 'File Version History' dialog, you can optionally click on either:
  - Check Out the selected revision of the Package file is retrieved from Version Control and imported into your model as a Package that is checked out for editing; you can subsequently check in this revision as a new HEAD revision, effectively allowing you to revert the Package to a prior revision or
  - Retrieve the selected revision of the Package file is retrieved from Version Control and imported into your model, but the Package remains flagged as checked-in and cannot be modified; subsequently checking out the Package updates it to the latest revision before it is unlocked for editing

#### **Notes**

· If the selected Package was already checked out in the

current model, the Retrieve and Check Out buttons are disabled

- If the selected Package contains any sub-Package that is already checked-out in the current model, a warning will be displayed and the retrieval or check-out will not go ahead
- If you check out a prior revision of a Package, but do not want to commit it as a new revision, right-click on the Package and select Package Control | Undo Check Out

## **Review Package History - SCC Client**

It is possible to review the change history of Version Controlled Packages by examining previous revisions. If necessary, you can check out one of these earlier revisions of a Package for editing, effectively rolling-back to that prior revision of the Package. The process for reviewing the change history of Packages configured for Version Control with an SCC client (including products such as Visual Source Safe, TFS-SCC, ClearCase, Perforce, AccuRev and MKS Source Integrity) differs from that for Subversion, CVS or TFS command line clients.

#### **Access**

Context Menu	Right-click on Package > Package Control > File History
IVICIIU	Condoi / The History

# Review change history of a version-controlled Package (SCC client)

Ste	Action
p	

- 1 The change history mechanism offered by the third party SCC provider displays.
  - To import a prior revision of the Package into your model, use the 'SCC History' dialog to retrieve the revision, then close the dialog.
- The SCC client notifies Enterprise Architect that a different revision has been retrieved. A prompt then displays, asking whether you want to check-out the prior revision.
- 3 Optionally, click on either:
  - Yes, to check out the prior revision the selected revision of the Package file is retrieved from Version Control and imported into your model as a Package that is checked out for editing; you can subsequently check in this revision as a new HEAD revision, effectively reverting the Package to the prior revision
     OR
  - No, to import the prior revision as read-only the selected revision of the Package file is retrieved from Version Control and imported into your model, but the Package remains flagged as checked-in and cannot be modified; subsequently checking out the Package updates it to the latest revision before it is unlocked for editing

#### **Notes**

- If the selected Package was already checked out in the current model, the system does not proceed with retrieving a prior revision
- If you check out a prior revision of the Package, but do not want to commit it as a new revision, right-click on the Package and select 'Package Control | Undo Check Out'

### **Retrieve Prior Revision - SCC Client**

Depending on your Version Control product, retrieving a prior revision of a controlled Package can involve a number of prompts regarding overwriting the current local copy.

This example details retrieval of a prior revision from a TFS-SCC Version Control configuration.

#### Access

Context	Right-click on Package > Package
Menu	Control > File History

# Example Procedure - retrieve prior revision, TFS-SCC client

Ste	Action
p	
1	Display the 'TFS File History' dialog.
2	Clials on the Cat levetton
2	Click on the Get button.
	The TFS-SCC client displays the 'Resolve Conflicts'

	dialog.
	This dialog offers the 'Automerge All XML Package files' option. DO NOT select this option.
	It is important to prevent any merging of Enterprise Architect's XML Package files.
3	Click on the Resolve button.
	The TFS-SCC client displays the 'Resolve writeable file conflict' dialog.
4	Select the 'Overwrite local file/folder' option.
	The existing working copy of the Package file is overwritten by the prior revision retrieved from Version Control.
5	Click the OK button.
	The TFS-SCC client redisplays the 'Resolve writeable file conflict' dialog; it should now show no conflicts.
6	Click on the Close button.
	The TFS-SCC client redisplays the 'File History' dialog.
7	Click on the Close button.
	Enterprise Architect displays a prompt, asking whether to check-out the prior revision.

#### 8 Click on the:

- Yes button to check-out the prior revision
- No button to retrieve a read-only version of the Package, that is NOT checked-out and is NOT editable

## **Validate Package Configurations**

Having defined the Version Control settings for your current model, you can test the validity of those settings associated with each Version Controlled Package within the model.

#### **Access**

D'1.1	
Ribbon	Configure > Version Control > Check
	Configuration

### **Validate Version Control settings**

Ste	Action
p	
1	The validation process scans the model database and verifies that the Version Control configuration associated with each Version Controlled Package is fully specified in the current model. It also queries the corresponding Version Control provider to find the status of the Package file associated with each Version Controlled Package.

	The results of the validation process are sent to the System Output window.
2	Open the 'Version Control Settings' dialog to complete the definition of any invalid or missing Version Control configurations.
3	Click on an error message in the System Output window to highlight the corresponding Package in the Browser window.
4	Right-click a Package node and select 'Package Control   Configure Package' to open the 'Package Control Options' dialog.  Correct any problems with the Version Control details for the Package.  Correct any problems with the Package's associated XMI file.

# Resynchronize the Status of Version Controlled Packages

It is possible to update the Version Control status of Packages within your project to re-synchronize with the status reported by your Version Control provider. This can be useful if you are creating copies of your project, where checking in a Package from one copy of the model leaves the Package in the second copy of the model with an out-of-date Version Control status.

For a given Package, the re-synchronization process queries the corresponding Version Control provider to find the status of the Package file associated with the Version Controlled Package. If necessary, the process then updates the Package flags within the model database, to synchronize the Package status recorded in the model with the value reported by the Version Control provider.

#### **Access**

Ribbon	Configure > Version Control > Re-Synch Status (applies to all Packages in model)
Context Menu	Right-click on Package > Package Control > Re-synch Status With VC Provider (applies to single Package only)

## **Resynchronize Version Control status**

Ste	Action
p	
1	The results of the re-synchronization process are sent to the System Output window.
2	Double-click on any result message to select, in the Browser window, the corresponding Package.

- This process does not cause any Package data to be either exported from your model to the associated Package file, or imported from a Package file into your model's Package data
- If a Package has been checked-out and modified with Enterprise Architect, but your Version Control provider reports the Package file as checked-in, running this process marks the Package within Enterprise Architect as being checked-in, without exporting and committing the

- pending changes; subsequently checking-out the Package imports the latest revision of the Package file from Version Control, effectively discarding the uncommitted modifications from the model
- Similarly, if a Package file is checked-out to you in your local working copy folder, but not in the Enterprise Architect model, running this process marks the Package within the model as checked-out, but it does not import the associated Package file from the Version Control system; consequently, it is possible to check-in a Package from Enterprise Architect that is potentially out of date, compared to the latest revision of the Package file within the Version Control system

## **Tracking Changes**

If you want to track changes to data across your project, you can use two separate but complementary facilities - Auditing and Baselines.

#### **Facilities**

Facility	Detail
Auditing of model changes	Auditing is a project-level feature, available in the Corporate, Unified and Ultimate editions, that enables you to record model changes in Enterprise Architect.  By enabling this feature, model administrators can view a range of information regarding changes, such as:  Who changed an element  How many elements they changed  When they changed the data  What the previous values were, and  What type of elements they changed
Baselining and	The Enterprise Architect Corporate, Unified and Ultimate editions provide a

differencing to capture and roll back changes facility to 'baseline 'or snapshot a model branch in XMI format at a particular point in time, and store it within the model in compressed format.

More than one baseline can be stored against a single Enterprise Architect Package; using baselines, you can compare Packages at the current and earlier stages of development, using the Compare (Diff) utility.

The Compare utility is available in the Professional, Corporate, Unified and Ultimate editions of Enterprise Architect; it enables you to compare the current model with:

- A Baseline
- An exported Enterprise Architect XMI file on disk
- A version-controlled Enterprise Architect XMI file on disk

## **Auditing**

Auditing is a project-level feature that model administrators can use to record model changes in Enterprise Architect. After switching Auditing on, you can view information on changes such as:

- Who changed an element
- How many elements they changed
- When they changed the data
- What the previous values were, and
- What type of elements they changed

Auditing does not record changes to:

- Document Templates
- Model Documents
- Baselines or
- Profiles

We provide a Quickstart procedure to help you enable Auditing and see it in action, from which point you can explore a number of set-up options and display features.

#### **Features**

Feature	Detail
The Audit	To view what has been recorded by the

View	audit, use the Audit View, which provides an interface to everything recorded by Auditing.  If security is enabled, you must have Audit View permission to display data in the Audit View.
Model Views	You can also obtain a snapshot of selected items in the model, using the Model View facility.  In the Corporate, Unified or Ultimate editions of Enterprise Architect, you can use this facility to automatically generate a snapshot at intervals and, if there are changes in the items collected by the defined search, to trigger a notification to you of such changes.  This helps you to monitor workflow and other events of concern to you.
Document Report	You can generate a document report that includes the audit history information for the selected element or Package, by choosing the basic + audit template.
Audit History	Using Auditing, you can track changes to an element or connector over time.  However, enabling Auditing also enables an 'Audit History' tab in the System

	Output window, which summarizes all changes made to the selected element or connector.
Performance Issues	By enabling Auditing on a project, you increase the time taken for most actions. For most modeling tasks, this increase is insignificant; however, there are some instances where the difference is more substantial.

- The Auditing facility is available in the Corporate, Unified and Ultimate editions
- Warning If your site runs separate editions of Enterprise Architect, when Auditing is turned on in a project any Professional edition users are locked out of the project; to restore access, turn Auditing off in the project from the Corporate, Unified or Ultimate edition instance of Enterprise Architect

## **Auditing Quickstart**

It is very simple to enable Auditing and see it in action.

#### **Access**

Ribbon	Configure > Model > Audit : Audit Settings
--------	--

## **Enable Auditing**

Ste	Action
p	
1	In the 'Audit View', click on the Audit Settings button. The 'Audit Settings' dialog displays.
2	Select the 'Enable Auditing' checkbox.
3	Click on the OK button to close the 'Audit Settings' dialog.

4	Close the 'Audit View' dialog.
5	Change and save your project.  Add a new Package  Add a new Class  Add a new connector  Change the name of an element  Delete an element
6	Open the Audit View again and click on the Refresh (or Load) button to display a record of the changes you have made.

## **Auditing Settings**

Using the 'Audit Settings' dialog, you can change what is recorded by the Auditing facility and:

- Define the areas of processing in Enterprise Architect to audit
- Administer your audit records
- Indicate the kind of model objects for which changes are to be recorded
- Configure Auditing to record changes to only certain types of elements

#### **Access**

Ribbon	Configure > Model > Audit : Audit Settings
--------	--

## **Configure Settings**

Option	Action
Enable	Select this checkbox to turn the Auditing

Auditing	facility on.
Audit XMI Import	Select this checkbox to record changes arising from XMI importing in the audit. As Version Control uses XMI, you must select this option to record changes from checking out Packages.
Audit XMI Export	Select this checkbox to record changes arising from XMI exporting in the audit. As Version Control uses XMI, you must select this option to record changes from checking out Packages.
Audit Reverse Engineering	Select this checkbox to record changes arising from reverse engineering in the audit.
Use Database Timestamp	Select this checkbox to use the database server's timestamp instead of each user's local timestamp; this improves security. This option is not available for project files.
Clear Logs	Click on this button to permanently delete all log data from the current project; use the Save Logs button first, to save the audit records outside the project.  The system prompts you to specify

	<ul> <li>whether to clear items logged over a specific period of time.</li> <li>Click on the No button to clear all log items currently held in the database</li> <li>Click on the Yes button to display the 'Time Filter' dialog, on which you select a standard time period or define your own</li> <li>This function can be accessed through the Automation Interface.</li> </ul>
Save Logs	Click on this button to save a copy of the logged audit items currently held in the project. These items remain in the project; you can use the Clear Logs button to remove them.  The system prompts you to specify whether to save items logged over a
	<ul> <li>Specific period of time.</li> <li>Click on the No button to save all log items currently held in the database</li> <li>Click on the Yes button to display the 'Time Filter' dialog, on which you select a standard time period or define your own</li> <li>This function can be accessed through the Automation Interface.</li> </ul>

Load Logs	Click on this button to load a previously saved set of logs back into the project. A browser displays through which you select the log file to reload.  If the same record exists in both project and log file, that record is not reloaded.
Core	Select this radio button to record changes to elements (including attributes and operations), Packages, connectors and some model-level information.
Standard	Select this radio button to record the same changes as for the Core option, plus changes to some of the 'housekeeping' data for diagrams - Name, Author, Version, Stereotype, Notes and Date Modified.  You can check for changes to diagram content and structure using the Baseline facility for reviewing visual changes to diagrams.
Extended	Select this radio button to record the same changes as for the 'Standard' option, plus changes to project security.
Debug	Select this radio button to record the same changes as for the 'Extended' option

	plus changes to any database tables. Some of the auditing information will not be visible unless the Audit View mode is set to 'Raw'.
Maintenance	Select this radio button to audit changes to maintenance elements only; that is:  Package (element) Requirement Feature Use Case Actor Note Issue and Change
Core Structural	Select this radio button to audit changes to maintenance elements plus certain structural elements; that is:  Package (structure)  Class  Interface Signal  Node Component  Artifact Part

	• Port and
	• Device
All	Select this radio button to audit changes to all types of element.
Custom	Select this radio button to audit changes to element types that you specify.  The Customize button is made available; click on this button to display a list of element types, and select the checkbox against each element type to include in the audit (or click on the Select All button to select every element type).  Click on the OK button to save the selection.

- As the number of records increases, the performance of the Audit View reduces; it is recommended that audit records that are not regularly required are saved to file, then cleared from the project, to help ensure high performance
- Connectors are audited when they are connected to an element that is included in the Audit Options

• If security is enabled, you must have Audit View permission to turn Auditing on, and Audit Settings permission to change the audit settings

## The Audit View

The Audit View provides an interface to the information that has been recorded by auditing.

#### **Access**

Ribbon	Configure > Model > Audit
--------	---------------------------

#### **Sections of the Audit View**

The Audit View is divided into three main areas:

Section	Description
View controls	The view controls provide a variety of settings for controlling auditing and the display of audit records.
Audit tree	The audit tree displays the log items that have been recorded by auditing.  What is displayed in the tree is affected by the view controls, such as:  • Sorting

- Filter (by time)
- Mode
- Auditing settings (what was actually recorded)

If synchronizing with the Browser window, it is also affected by the Package, diagram or element you have selected.



#### In the audit tree:

- The green tick indicates a creation
- The yellow pencil indicates an edit
- The red cross indicates a deletion

Right-clicking an element in the audit tree (such as MyClass) displays a context menu that enables you to locate the selected element in:


- The Browser window
- Any diagrams in which it exists

## Record display

The record display is in two parts: the identity of the selected change, and the actual change made.

The data in the record display is determined by the view controls and mode and, if synchronizing with the Browser window, by the Package, diagram or element you have selected.

#### **Identity**



The identity of a change consists of:


- The Windows username of the user that made the change; if security is enabled, the name is of the format WindowsUsername(SecurityUser)
- When the change was made
- The path of the change; for example: Class Class1 - Attribute Att1 -Attribute Constraint Constraint

#### **Changes**

Changes are displayed in a table format, showing the:

- Property (or data item) name
- Its original value before the change and
- Its value after the change

If you double-click on an item in the list of changes (or right-click and select the 'Show Differences' option) the Difference window displays:



#### **Notes**

• If security is enabled, you must have Audit View permission to display data in the Audit View

## **Audit View Controls**

The Audit View controls provide a variety of settings for controlling auditing and the display of audit records.

## **Options**

Option	Action
Load or Refresh	Click to reload the Audit Tree, updated with any new audit results.
Search	Click to search through log items for a particular area - you can search by Name, Type or GUID.
	The items are loaded and filtered with the current Sort By, Time Filter and Mode settings.
	If you refresh the Audit View, you must run the search again.
Audit Settings	Click to open the 'Audit Settings' dialog.
Sort-by	Select the appropriate radio button for the required display setting:  Type - changes are grouped under

	element type (such as Class or Requirement), and then grouped under the changed element  Class Elements  MyClass  2007-03-13 10:38:55 2007-03-13 10:39:04
	User - changes are grouped under user name, each with the number of changes for that user
	Under each user name, changes are grouped as for the Type sort  Admin (3)  Class Elements  MyClass  MyClass  2007-03-13 10:46:06 2007-03-13 10:46:15
Filter By Date/Time	Select to enable the Filter Settings button, to filter the audit results by time period. Changes that occur outside the selected filter period are not shown in the Audit View.
Filter Settings	<ul> <li>Click to display the 'Time Filter' dialog, to set the filter time period:</li> <li>Today - to display changes occurring today</li> <li>Previous Hour - to display changes</li> </ul>

	<ul> <li>Previous 24 Hours - to display changes occurring in the last 24 hours</li> <li>Previous Week - to display changes occurring in the last 7 days</li> <li>Previous 30 Days - to display changes occurring in the last 30 days</li> <li>Previous Year - to display changes occurring in the last 365 days</li> <li>Custom - to define your own time period, using the From and To fields</li> <li>The six pre-configured time periods automatically update when you click on the Refresh button; custom periods are static and do not automatically update.</li> <li>If you have set a filter period, and you deselect the 'Filter By Date/Time' checkbox, the period remains set; the custom time period, too, is retained so that you can re-use it or modify it later if required.</li> </ul>
Status Text	<ul><li>Read to see which:</li><li>Mode has been selected and</li><li>Time filter is being applied to the data</li></ul>
Mode	Click to display a menu of options to change the mode of the Audit View.

#### Select:

- 'Standard' to automatically synchronize with the Browser window; where changes have been made, the Audit View reflects your selection from the Browser window - if you click on:
  - An element, the Audit View displays the history for that element
  - A Package, the Audit View displays the history for that Package and its immediate children (but not the contents of nested Packages)
  - A diagram, the Audit View displays the history for that diagram and

its contents (which could be drawn from a wide area of the Project Browser)

- 'Advanced' to load large sets of log items independent of the Browser window; in this mode, a special Audit Settings group can be displayed in the Audit Tree, which records:
  - When Auditing has been enabled and disabled
    - Who made the change
    - The date and time of the change
    - Changes to the Audit Settings

- When Audit Operations are executed
- Security changes (which can be browsed in the same way as other changes)
- 'Deleted' to display only deleted records, but otherwise data is shown as in 'Advanced' mode; records can be sorted by element type or by user as required
- 'Raw' to display all audit records in chronological order without sorting, enabling you to see a progression of changes; this can be especially useful in determining date-time inconsistencies

Any search and filtering you define still apply, enabling you to view all of today's changes in order, or all changes for a particular element in order, or both

Additional database information is displayed; this additional information might be insignificant or only in machine-readable format

## **Audit History Tab**

When Auditing is turned on, an 'Audit History' tab is enabled in the System Output window. The tab shows a history of changes to whichever element or connector you have selected in the:

- Current diagram
- Browser window
- Audit View, or
- Package Browser

As you select different elements or connectors, the 'Audit History' tab automatically updates to reflect your current selection. For each change made to the element or connector, the tab shows:

- Who made the change
- · When the change was made
- Where the change was made
- The value of the characteristic before the change
- The value of the characteristic after the change

#### Access

Ribbon	Start > Desktop > Design > System Output > Audit History
	Output > Audit History

- To see this tab, you must have the Audit View open; the tab continues to display if you subsequently close the Audit View
- If security is enabled, you must have Audit View permission to display data on the 'Audit History' tab

## **Auditing Performance Issues**

Enabling auditing on a project increases the time taken for most actions.

For most modeling tasks, this increase is insignificant; however, there are some situations where the difference is more substantial.

## **Operation Delays**

Operation	Detail
Large Deletions	Deleting large Packages or Package structures, or large numbers of elements, takes significantly longer with auditing on.  You might disable auditing before performing such a deletion.
XMI Imports	Importing XMI takes longer with auditing enabled.  A project-level option is provided for disabling auditing of XMI Imports.
Reverse Engineering	Reverse engineering code takes longer with auditing enabled.  A project-level option is provided for

	disabling auditing of reverse engineering.
Replication	You cannot remove replication from a model with Auditing enabled.  If you have to remove replication, disable Auditing and - if prompted to do so - allow Enterprise Architect to roll back the database version; you can then remove replication.

## **Audit View Performance Issues**

The Audit View can cause slow performance, generally because of the volume of records it has to process.

## **Considerations and Responses**

Consideratio n	Detail
Navigating the Browser window Within Auditing is Slow	Try setting the time filter to a period in the immediate past, such as 'Today', 'Previous 24 Hours' or 'Previous Week'; this time period updates each time you open or refresh the Audit View.  Save log items outside the project with the Save Logs button; if you then clear the logs you have just saved, the load time of the Audit View is reduced.  You can reload logs into the project at any time, using the Load Logs button.
The Audit View is Slow in Loading and Changing	Try setting the time filter to a period in the immediate past, such as 'Today', 'Previous 24 Hours' or 'Previous Week'; this time period updates each time you open or refresh the Audit View.

Modes	Save log items outside the project with the Save Logs button; if you then clear the logs you have just saved, the load time of the Audit View is reduced.  You can reload logs into the project at any time, using the Load Logs button.
Navigating the Audit Tree is Slow	Close the 'Audit History' tab in the System Output window

## **Package Baselines**

Enterprise Architect includes tools to help you manage and review changes to your models over time. These tools apply the concepts of Baselines, Differencing and Merges.

You use Baselines, Differencing and Merges essentially to compare two snapshots of a specific part of your project, to capture the differences between them and either roll back or incorporate selected changes or all changes.

#### **Baselines**

Enterprise Architect provides a facility to create a Baseline or 'snapshot' of the contents of a selected Package and its child Packages at a particular point in time; this enables you to later compare that branch of the model at that time with the current state of the branch.

Baselines are stored in the same XML format as is used for Version Control, but are stored within the project in compressed format.

You can also have parallel copies of parts of your model for team development, and create Baselines within each copy to merge changes into the project master.

## **Differencing**

Differencing (Diff, or Compare) helps you to explore the differences between:

- The current state of a specific part of your project, and
- Previous or parallel versions captured in a Baseline or an XMI 1.1 file on disk

## Merges

Once Differencing is complete, you can merge information from the Baseline into the current project; it is not possible to go the other way.

#### You can:

- Merge information manually, change by change
- Merge information automatically by electing to merge in all changes in one batch procedure
- Revert completely to the original Baseline by importing the stored XMI directly
- Merge information and elements from a Baseline in a different project, making it possible to keep multiple versions of a single model in synch

The merge options are available through the toolbar, context menus and the keyboard on the 'Compare Utility' tab, which shows the results of a comparison.

## Visual differences in diagrams

Changes to a model might include:

- Adding or removing elements and connectors on a diagram, or
- Changing the position of elements or the overall layout of a diagram

You might believe that a diagram has changed, and select to compare it with a baseline using a ribbon option.

Alternatively, you might perform a baseline comparison on a Package or a model and select from the comparison output any diagrams that are flagged as changed.

- Package Baseline facilities are available in the Corporate, Unified and Ultimate editions of Enterprise Architect
- The Enterprise Architect Corporate, Unified and Ultimate editions provide another facility, Auditing, which you can switch on to perform continuous monitoring of changes across the project; you can dovetail your use of each facility to meet the range of your change management requirements
- If a Package under Version Control forms part of a Baseline, and that Package is checked in to the model, you cannot merge the original data from the Baseline into that Package
- You can also obtain a snapshot of selected items in the

model, using the Model Views facility; this facility enables you to automatically generate the snapshot at intervals and, if there are changes in the items collected by the defined search, to trigger a notification to you of such changes, which enables you to monitor workflow and other events of concern to you

• If security is enabled you must have 'Baselines - Manage' permission to create, import and delete Baselines, and 'Baselines - Restore' permission to merge data from a Baseline; security permissions are not required to select an existing Baseline and perform a comparison with the model

### **Baselines**

Enterprise Architect provides a facility to 'Baseline' (snapshot) a model branch at a particular point in time for later comparison with the current Package state.

### **Baselines**

Baseline comparison is most useful for determining the changes made to the model during development compared to some Baseline saved at a crucial point - for example the completion of a phase or version iteration.

More than one Baseline can be stored against a single Enterprise Architect Package.

Baselines are particularly useful during requirements management to check for changes, additions and deletions that have occurred since the start of the current work phase; knowing how a model has changed is an important part of managing change and the overall development process.

Baselines are stored within the model in compressed XML format; you can save a Baseline to an external XML file for storage or archive, or for distributing to other users working on models derived from a master project.

Baselines are generally used in conjunction with the Compare utility.

### **Scenario**

A typical scenario for using Baselines would be:

- Create the base model branch to a sufficient point to create a Baseline (checkpoint); create and store the Baseline as Version 0.1a
- As work continues on development, managers and developers can check the current model branch against the Baseline for important modifications, additions and deletions; the Compare utility can be invoked from the Baseline dialog to check the current model branch against the stored version
- As required, minor Baselines can be created to check recent progress; these 'temporary Baselines' are useful for managing change when a lot of work is being done and it is important to only see what has changed in, for example, the last 24 hours

At sign-off or the move to a new version/phase, a major Baseline can be created to capture the new state of the model.

Minor Baselines created earlier can be deleted if required to save space

### **Considerations**

Baselines are based on the GUID or unique ID of a

### particular Package:

- Enterprise Architect checks for that ID as the root element within the XML document being used as a Baseline
- When you export a Package to XML, the Package you export is the root element; likewise when you create a Baseline, the current Package is the root Package of the XML Baseline
- When you save information in a Version Control system, the current Version Controlled Package is again the root Package of the document
- It is not useful to create a Baseline by importing an XMI Package file created by Version Controlling a Package that itself contains Version Controlled child Packages; that type of XMI Package file contains stubs for the child Packages, not full information on the child Packages and elements
- If a Package under Version Control forms part of a Baseline, and that Package is checked in to the model, you cannot merge the original data from the Baseline into that Package

XML files must be in the same format used by the Baseline engine - currently the UML 1.3 XMI 1.1 format (plus Enterprise Architect extensions), which contains all the information necessary to reconstruct a UML model, even a UML 2.x model

#### **Notes**

- The Baseline facility is available in the Corporate, Unified and Ultimate editions of Enterprise Architect
- The Compare utility is available in the Professional edition of Enterprise Architect, as well as in the Corporate and extended editions

## **Manage Baselines**

Enterprise Architect provides a range of facilities for working with and managing Baselines.

#### Access

Ribbon	Design > Model > Manage > Manage Baselines
Keyboard Shortcuts	Ctrl+Alt+B

## **Baseline Management**

Create, select and process Baselines using the 'Package Baselines' dialog.

Option	Action
Current Baselines For Package: <name></name>	Review the Baselines for the current model branch, listed by version reference with the highest alphabetical/numerical value at the top.

	If an entry is longer than the display area, a horizontal scroll bar displays at the bottom of the panel; use this to scroll to the text that is not shown.
Show Differences	Run the Compare utility on the selected Baseline and the current model branch or diagram, to display the differences between the two.
Restore to Baseline	Completely restore the model branch from the selected Baseline.
New Baseline	Create a new Baseline.
Delete Selected	Delete the selected Baseline.
Load Other Baselines	<ul> <li>Display a drop-down menu that enables you to load Baselines from another model, in either a project file or a DBMS repository.</li> <li>For project files, a browser displays; locate the required project file</li> <li>For DBMS repositories, the Windows 'Data Link Properties' dialog displays;</li> </ul>
	select the data provider and click on the OK button to display the 'Select Data

	Source' dialog, from which you select the required project
	In either case, the <i>Connected To:</i> message at the bottom of the 'Package Baselines' dialog changes to the name of the alternative model.
	To return the dialog to the original project, select the third option on the drop down list: 'Load From Selected Package'.
Import File	Import an XML 1.1 file from the file system as a new Baseline for this current model branch.
Export File	Export the selected Baseline to an XML file on disk.
Compare Model to File	Compare the selected model branch with an XML 1.1 file on disk; a browser displays, which you use to locate the file.
Options	Set filters to make the comparison more specific.

### **Notes**

• Package Baseline facilities are available in the Corporate, Unified and Ultimate editions of Enterprise Architect

### **Create Baselines**

This topic details the basics of creating new Baselines of Model Packages.

#### Access

Select a Package in the Browser window, then open the 'Baselines' dialog using one of the methods outlined here. In the 'Baselines' dialog, click on the New Baseline button.

Ribbon	Design > Model > Manage > Manage Baselines : New Baseline
Keyboard Shortcuts	Ctrl+Alt+B : New Baseline

### Create a new baseline

Field	Action
Name	Display the Package name of the currently selected model branch.

Version	Type a unique version reference for this Baseline, which can consist of any alphanumeric characters.  The 'Package Baselines' dialog sorts the Baselines according to the value of this field.
Include Sub-packages	Include the entire sub-Package hierarchy of this branch in the Baseline; this option defaults to selected.  If you deselect the checkbox, only the immediate contents (XMI stubs) of the Package are included in the Baseline.
Note	Edit the default current time and date to any other value.  The field is a single-line entry, for display on the 'Package Baselines' dialog (a one-line-per-entry list).
OK	Click to create a new Baseline and return to the 'Package Baselines' dialog.

### **Notes**

• Package Baseline facilities are available in the Corporate,

## Unified and Ultimate editions of Enterprise Architect

# The Compare Utility (Diff)

Enterprise Architect has a comprehensive and powerful built in Compare (diff) utility, which enables you to:

- Explore what has changed within a model over time
- Explore how previous versions of a model branch differ from what is currently in the model
- Perform a full model comparison by exporting all of Model A to XMI, then using 'Compare Model to File' from within the current model (Model B)

Comparing and checking model development at various points in the process is an important aspect of managing change and development, monitoring what is being modified and ensuring the development and design process is on track.

Using the Compare Utility you can:

- Compare a model branch in Enterprise Architect with a Baseline created using the Baseline functionality (Corporate, Unified and Ultimate editions)
- Compare a model branch in Enterprise Architect with a Baseline stored in a different model
- Compare a model branch in Enterprise Architect with an XML 1.1 file on disk created previously using the Enterprise Architect XML export facility (user selects file)
- Compare a model branch in Enterprise Architect with the current version-controlled XMI 1.1 file on disk as created

when using Version Control in Enterprise Architect (file automatically selected)

#### **Access**

Select a Package in the Browser window, then open the 'Baselines' dialog using one of the methods outlined here. In the 'Baselines' dialog, click on the Show Differences button.

Ribbon	Publish > Model Exchange > Package Control > Compare Package to XMI
Keyboard Shortcuts	Ctrl+Alt+B: Show Differences

### **Differencing With Baselines**

As a Baseline is stored within a model and contains all the information, elements and connections for a Package at a point in time, it can be used within Enterprise Architect to track changes to model elements over time.

The Differencing engine first builds a representation of the current Package in memory, based on what is currently in the model.

It then compares this with the stored Baseline, highlighting changes, new elements, missing elements and elements that have been moved to other Packages.

It is possible to filter the resultant output to display only one particular kind of change: for example, additions to the model.

If a Baseline has been created to ignore child Package content, a comparison between that Baseline and the model does not include any child Package content in the model. See the Example comparison.

### **Notes**

- This utility is available in the Professional, Corporate, Unified and Ultimate editions of Enterprise Architect
- You cannot compare the current model with an XMI 2.1 file; the utility can only compare with an XMI 1.1 file

## **Compare Options**

You use the 'Compare Options' dialog to refine the output of the Compare utility when it compares the current model with a Baseline.

To display the dialog, either:

- Click on the Options button on the 'Package Baselines' dialog, or
- Click on the 'Compare Options' icon on the 'Compare Utility' tab toolbar

If the 'Compare Utility' tab shows the results of a Baseline comparison, when you click on the OK button the display refreshes to refine the information according to the options you have selected.

### **Options**

Option	Action
Always Expand to Differences	Always display the list of elements fully expanded to show changes.  If you deselect the checkbox, when the 'Compare Utility' tab is first opened it lists the Package contents to element level, and you expand each element as required to show the changed items.

	For large branches of the model, it is better to leave the checkbox unselected.
Show Elements that are	<ul> <li>List elements that:</li> <li>Have been changed since the Baseline was created</li> <li>Are in the Baseline only (that is, have been deleted from the model since the Baseline was created)</li> <li>Are in the model only (that is, have been created since the Baseline was created)</li> <li>Have not changed since the Baseline was created (you might generally leave this checkbox unselected)</li> </ul>
Suppress these Changes	<ul> <li>Exclude:</li> <li>Changes to diagrams</li> <li>Changes to the 'Date Modified' field for an item</li> <li>Changes to the 'Date Created' field for an item</li> <li>Child items of a deleted item</li> <li>Changes to advanced properties (defaults to selected)</li> </ul>
Baseline Diagram	Select the checkbox to always open the first parent Package for which there is a

Compare	Baseline, when you select the diagram for
Options	comparison from the Browser window.

### **Notes**

• Package Baseline facilities are available in the Corporate, Unified and Ultimate editions of Enterprise Architect

# **Check Visual Changes to Diagrams**

The Baseline Diagram Compare feature is a quick and easy way to visually compare a current diagram with an earlier version from a saved Baseline, and highlight any elements in the diagram that have been added, deleted, resized or moved.

You can then review these changes and optionally roll back each change if needed to its previous state from the Baseline.

The changes are identified on the 'Baseline Diagram Compare' dialog and on the diagram itself. If the diagram is not already open, the compare feature also opens the diagram.


#### Access

Ribbon	Layout > Diagram > Options > Compare to Baseline (on an open diagram)
	Design > Diagram > Manage > Compare to Baseline

## **Processing**

In two of these access paths, you perform a comparison of a Package and Baseline, and then select the diagram from the results on the 'Baseline Comparison' dialog to display the 'Baseline Diagram Compare' dialog. Refer to the *Results* section and the *Options* table.

In the other access paths, you first select the diagram to check, and then might have the option of selecting the Package from which to use a Baseline, on the 'Load Baselines from Package' dialog.



This dialog displays if you have NOT selected the:

- 'Always open first parent with a Baseline' checkbox on the dialog itself or
- 'Baseline Diagram Compare Options' checkbox on the 'Compare Options' dialog

(Selecting or clearing one of these checkboxes resets the other one as well.)

When you create a Baseline, it can be for a Package that contains one or more levels of child Package, and you might create Baselines for the Package(s) at each level. If the diagram you are checking is at a lower level in the hierarchy, there might therefore be a number of Baselines that contain information on the diagram, perhaps taken at different times and capturing different changes to the diagram. The 'Load Baselines from Package' dialog provides the facility to compare the diagram with one of a broader range of Baselines than just those from the diagram's immediate parent.

Click on the Package, and click on the OK button. In this case, **or** if the dialog did not display at all (the checkboxes were selected), the 'Baselines dialog displays.

Click on the required Baseline and on the Show Differences button. The 'Baseline Diagram Compare' dialog displays. Refer to the *Results* section and the *Options* table.

### Results

The 'Baseline Diagram Compare' dialog shows the elements that have been changed on the diagram, and what kind of change was made ('Status' field).



As you select elements on the dialog, images are shown on the diagram itself to indicate where the changed element was and what kind of change it underwent.

### **Options**

Option	Detail
Select (click on) name of element	<ul> <li>The 'Status' column indicates whether the element has been:</li> <li>Moved or re-sized (Changed)</li> <li>Deleted from the diagram (Baseline only)</li> <li>Added to the diagram since the Baseline was captured (Model only), or</li> <li>Deleted from its parent external</li> </ul>

Package, and there is no record in the current Baseline (because the Baseline is only for the current diagram's parent Package)


This diagram-linked element has been deleted from the model. The element might be found in a different baseline either in a parent Package baseline or a different Package baseline outside of the current Package. If the external referenced element is restored to the model, the visual comparison will be able to resolve the missing diagram object in the current baseline.

When an item is selected, the corresponding element on the diagram is highlighted as shown:

• Deleted from the diagram




• Added to the diagram



	• Resized or moved to a new position
	Order Screen Tests
	A deleted external element on the diagram
	[external reference]
	The highlighted element on the diagram is marked with a colored dot, as shown, to indicate that it is in focus.
Position the diagram to show the selected element	To scroll the diagram so that you can see the original (Baseline) position of an element, double-click on the item in the list.  To scroll the diagram so that you can see
	the current (model) position of the element, press and hold Ctrl while you double-click on the item.
Leave the changes in	Ensure that the checkbox against the item is not selected.
the item as	Click on the OK button.

they are	
Roll the changes back to the Baseline position	Click on the checkbox against each required item (or click on the Check All button to select every item).  The 'Action' column displays the action required to roll each element's relationship to the diagram back to the Baseline relationship, and on the diagram the selected elements are represented as shown:  This deleted element will be restored  Req-Load Stress3  This added element will be removed  This resized/repositioned element will be put back in its original position

• This element from another Package, deleted from the diagram, cannot be restored from this Baseline



The comparison automatically shows a blue direction arrow for each reposition or resize that has been checked. For a heavily edited diagram this might be confusing. However, you can hide the arrow for all elements except the one currently in focus; to do this:

- Deselect the 'Visually link new and old position for checked items' checkbox
   To roll back the changes for all items for which a checkbox is selected:
- Click on the Apply button


#### **Notes**

• Diagram Baseline facilities are available in the Corporate, Unified and Ultimate editions of Enterprise Architect

## **Example Comparison**

This diagram shows the result of a comparison between a Package (Log in/out Use Cases) in the current project and that Package in a Baseline captured at an earlier date.

The results of the comparison are displayed on the 'Baseline Comparison' tab.



### **Review Changes**

Aspect	Description
Interpretation	A hierarchy of model elements is displayed in the left-hand pane.  From the triangle-based icons and the highlighted lines on the report, it is clearly visible which items in the hierarchy have, since the Baseline was

#### captured, been:

- Changed
- Deleted from the model (in the Baseline only)
- Added to the model (in the Model only) or
- Switched to different Packages (changes in the Parent Package property)

If you click on an item in the left hand pane, the right-hand pane displays a table of properties showing the values of those properties in the current model and in the Baseline.

For each property where there is a difference between the model and the Baseline, the row is highlighted.


The 'Compare Utility' tab enables you to perform operations (such as merging or rolling back changes) on the reported information, using the toolbar, context menu and keyboard.

### Increase Level of Detail

The right panel of the 'Compare Utility' tab might, for some fields, display only part of the value.

It might also not be immediately obvious what a change is.

In either case, you can double-click on the property to display full details and to highlight the exact differences; this example shows the highlighted changes to the 'Name' property.



### **Notes**

• The Compare utility is available in the Professional, Corporate, Unified and Ultimate editions of Enterprise Architect

# **Baseline Comparison Tab Options**

The 'Baseline Comparison' tab enables you to perform operations on the reported information, using the toolbar, context menu, 'Merge' dialog and certain keyboard keys.



- The toolbar is at the top of the left-hand panel; the icons operate either on the comparison as a whole or on the currently-selected item in the left hand panel of the 'Baseline Comparison' tab
- Each item in the hierarchy has a context menu, which you display by right-clicking on the item; the options displayed depend on the level of the item in the hierarchy
- The 'Merge' dialog enables you to specify which changes to roll back in the model from the baseline
- You can use a selection of keyboard keys to move up and down the hierarchy, or to roll back changes

## **Toolbar Options**

Option	Action
Refresh	Re-run the comparison to refresh the current display.
Merge To	Merge the values of the currently-selected item in the Baseline

Model	back into the model.
Next Change	Highlight the next changed item (this skips Moved items).
Previous Change	Highlight the previously-changed item.
Expand All	Fully expand the selected item.
Collapse All	Collapse the changed items in the selected item.
Expand To Changed Items	Expand the selected item to show changed items only (in the event that you have selected to also show unchanged items in the comparison).
Find in Project Browser	Highlight the item in the Browser window.
Log To XML	Log the changes to an XML file.  A browser displays, on which you specify the file name and location.
Compare Options	Display the 'Compare Options' dialog.

Manage Package Baselines	Display the 'Package Baselines' dialog.
Help	Display the Help topic <i>Package Baselines</i> .

# **Context Menu Options**

Option	Action
Merge from Baseline Add from Baseline	Restore the item in the model to the Baseline state, or restore a deleted item from the Baseline.
Delete from Model	Remove a recently-created item from the model.
Merge From Baseline (with Options)	(For the root node of the hierarchy on the 'Compare Utility' tab.) Display the 'Merge' dialog, which you can use to specify options for rolling back the whole model branch to the Baseline state.

Refresh	(Object-level items.)
	Re-run the comparison to refresh the current display.
Find in Project Browser	Locate and highlight the item in the Browser window.
Open Baseline Diagram Compare	(For a diagram listed in the comparison.) Display the Baseline Diagram Compare window, showing differences in diagram content and layout.
Expand All	Fully expand the selected item.
Expand To Changed Items	Expand the selected item to show changed items only.
Collapse All	Collapse the changed items in the selected item.
Log To XML	Log the changes to an XML file.  A browser displays, on which you specify the file name and location.
Compare Options	Display the 'Compare Options' dialog.

# **Merge Dialog Options**

Option	Action
Changed	Restore all changed items in the model branch to the Baseline state.
In Baseline Only	Restore all deleted items to the model branch from the Baseline.
In Model Only	Remove all recently-created items from the model branch.
Moved	Restore all moved items to their original locations, as identified in the Baseline.
Full Restore from XMI	Completely restore the model branch to the version held in the Baseline XMI 1.1 file, (using the 'XMI Import' function). (This option automatically selects all the other options)

## **Keyboard Keys**

- Ctrl+ ↓ expand and highlight the next changed item
- Ctrl+ ↑ expand and highlight the previous changed item
- Ctrl+ ← undo the changes for a selected item (roll back to the Baseline values)

## **Compare Projects**

A number of operations can make changes to your project that you either want to monitor carefully or not have at all. Such events include:

- Recovering from a database crash
- Restoring a backup
- Performing a Project Data Transfer
- · Importing from XMI, and
- Deleting model elements

You might have made a copy of the original project or the purpose of the operation is to generate a copy, in which case you can compare the size and row counts of the 'before' and 'after' copies as a convenient 'sanity check'. The copies can be on different platforms; you have options to:

- · Compare a project file to another project file
- Compare a project file to a DBMS-based repository
- Compare two DBMS repositories

The comparison examines the number of project rows in each database, producing a report indicating the total records in each and the difference in record count between the two. If discrepancies are found, you must investigate further manually. The comparison does not examine the actual data in the tables.

#### Access


Ribbon Configure > Model > Integrity > Project Compare	Ribbon	Configure > Model > Integrity > Project Compare
--	--------	---

# **Compare two projects**

Ste	Action
p	
1	On the 'Project Compare' dialog, select the radio button for the database types of the two projects you want to compare:  • File to File  • DBMS to File  • DBMS
2	In the 'Source Project' and 'Target Project' fields, type the name or connection string for the source and target projects to compare.
3	Click on the Compare Projects button.  The results of the comparison display in the panel at the bottom of the dialog.

4 If you want to print the results of the comparison, click on the Print List button.

## **Project Maintenance**



The repository is an important data store that must be maintained to ensure that it is running efficiently and that the information it contains has integrity. Enterprise Architect has built-in features that allow you to keep the repository in good health. These include tools to maintain the database itself, such as Repair and Compact functions (for file based repositories), and a series of tools to manage the data and models, such as model validation and data integrity checks. Reference data can be imported and exported from the repository, and can be shared between repositories, ensuring consistency. The Browser window allows repositories to be refactored easily by dragging and dropping Packages, elements, features and diagrams to new locations. The Element Discussion and Team Library features allow the model to be critically analyzed and reviewed.

#### **Facilities**

Facility Detail	
Check the	If you have a failed XMI import, network

integrity of the data in a project	crash or other unforeseen event that could disrupt the integrity of information in the model, it is recommended that you run a Project Integrity Check.
Reset Auto Increment Columns in Tables	XMI Import/Export can affect the table auto increment column values and push them towards their maximum allowed value; you can re-sequence the columns to avoid this problem.
Upgrade an old project to enable use of new features	The structure of Enterprise Architect project files is occasionally changed to support more features; when this happens, existing project files must be upgraded to the new format to ensure correct operation and to take advantage of all the new features.
Rename a project	If you want to rename an Enterprise Architect file-based project, you can do so through Windows Explorer.
Compact a project	As with many relational database products .EAP/.EAPX files do not physically release allocated space after data is deleted, therefore from time to time it can be beneficial to perform a 'compact', to reduce the physical size of

	the project file.
Repair a project if it did not close properly	If a .EAP/.EAPX project has not been closed properly, such as during system or network outages, it is possible that the project will reports inconsistencies errors the next time it is opened. To resolve such issues a 'Repair' can be performed to correct any potential problems.

• You can only rename, compact and repair models created as .EAP/.EAPX files with Enterprise Architect. While most DBMS products provide similar functionality, they typically require an elevated level of permissions and therefore usually performed by your Database Administrator (DBA).

# **Check Project Data Integrity**

If you have a failed XMI import, network crash or other unforeseen event that disrupts the integrity of information in the model, it is recommended that you run the Project Integrity Check function to check that your project data is structurally complete.

You can select a variety of items to check. The integrity check examines all database records and ensures there are no 'orphaned' records or inaccurate or unset identifiers. This function does NOT check UML conformance, only the data relationships and repository structure.

You can run the integrity checker first in report mode to discover if anything should be corrected, and then run it again in 'recover/clean' mode.

When Enterprise Architect 'cleans' the model, it attempts to recover lost Packages and elements, and generates a new Package at the model root level called \_recovered\_. Check through any elements that are found and, if required, drag them back to where they belong. If they are not required, delete them.

#### Access

Ribbon	Configure > Model > Integrity > Project Integrity

# Check the data integrity of your project

Ste p	Action
1	Open the project.
2	Select the 'Project Integrity Check' menu option. The 'Project Integrity Check' dialog displays.
3	Select the checkbox for each check to run:  Package Structure  Object Structure  All GUIDs  Cross References  UML 2.0 Migration
4	<ul> <li>Select either:</li> <li>The 'Report Only' option to just view a report on the state of your model, or</li> <li>The 'Recover/Clean' option to recover and clean</li> </ul>

	your project; before selecting this option, back up your project file first
5	To write a log of the integrity check, click on the Save Results button and select a log file.
6	Click on the Go button to run the check.  If you want to display the resulting information in a more readable layout, you can resize the dialog and its columns.

## **UML 2.0 Migration**

The UML 2.0 Migration check enables you to migrate the project from UML 1.3 semantics to UML 2.0 semantics. The migration process currently converts activities that are invocations of operations into called operation actions as per the UML 2.0 specification.

The UML 2.0 Migration option is an exclusive process that does not enable any of the other checks to be selected. When you click on the Go button to perform the migration, a prompt displays for you to confirm the operation.

#### **Notes**

• In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Check Data Integrity' permission to perform a data integrity check

# Reset Table Auto Increment or Identity Columns

This topic explains possible impacts of XML Export/Import on table auto increment columns, and how to re-sequence the columns whose value approaches the maximum value allowed.

## **Impacts**

Impact Due To	Impact
XML Export/Impor t	XML Export/Import can cause gaps in the numbering sequence of auto increment columns.  Each XML Import deletes rows from several tables; the import then adds rows starting from the largest previous value of the auto increment column.  Repeated XML imports can result in the value of the auto increment approaching the maximum value of the database datatype; for example, SQL Server's int datatype has a maximum value of 2,147,483,647.

Replication	Large auto increment values can also arise where the project originated as an EAP replica or design master.
	The Jet engine assigns random values for auto increment columns with each XML Import into the project.
	These random values can approach the maximum range of the repository data type, which could present a problem when the EAP project is transferred to a repository.

#### **Access**

Ribbon	Configure > Model > Integrity > Reset IDs
--------	---

# Re-sequence auto increment columns

Ste	Action
p	

1	Open the project.
2	<ul> <li>Select the 'Reset IDs' menu option.</li> <li>A dialog displays listing all non-empty tables that contain an auto increment or identity column.</li> <li>The 'Rows' column shows the number of rows in the table</li> <li>The 'Maximum ID' column shows the current maximum value of the auto increment column</li> <li>The 'Action' column shows either 'No Action' or 'Reset', depending on how close the column value is to the datatype's maximum</li> <li>Tables requiring a reset are automatically selected in the list.</li> </ul>
3	Click on the Go button to reset the auto increment column values.

- Connection to the project must be via a **direct** connection; IDs cannot be reset while the connection to the repository is via Pro Cloud Server
- Project Auditing must be disabled before IDs can be reset
- MySQL repositories will require re-starting of the

MySQL server so that the reset auto increment columns start from the reset value

- While strict not necessary, Sparx System would recommend that this task is performed when all users are not actively using the Project
- Sparx System recommend that a backup of the Project should be done both before and after performing a Reset of Table Auto Increment columns
- In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Check Data Integrity' permission to reset IDs

# **Upgrade a Project**

The structure of Enterprise Architect project files is occasionally changed to support more features. In such cases, the project might have to be upgraded. Upgrading to the new file structure is a simple and quick process that brings your project to the current level to:

- Ensure correct operation and
- Support all the latest Enterprise Architect features

#### **Initial Check**

When you load a project that was created in an earlier release of Enterprise Architect (for example, an archived project) using a recent release of Enterprise Architect, the system determines whether the project should be upgraded and, if the upgrade is necessary, displays the Upgrade Wizard.

## The Upgrade Project Wizard

The Upgrade Project Wizard takes you through the upgrade process and:

- Advises you of the necessity to upgrade
- Advises you to back up the current project; it is essential

to back up before any changes are made

- Checks which upgrade path is required
- Guides you through the steps to perform the upgrade
- Opens the newly converted project

#### **Notes**

- If you are using replication in your models, and the upgrade wizard detects that the project you are opening is a replica and not a Design Master, a different upgrade path is required
- Once upgraded, the project cannot be opened with the version of Enterprise Architect in which it was created

## **Upgrade Replicas**

Models that have replication features added might have to be upgraded differently from regular projects.

- If the model is a Design Master (the root model of all other replicas) then you can upgrade the model to suit the current version of Enterprise Architect; after upgrading a Design Master you should re-create the replicas, rather than synchronizing
- If the model is not a Design Master, you must first remove the replication features, then upgrade the project in the normal manner; the Upgrade Wizard guides you through the steps

## **Run SQL Patches**

Occasionally, Sparx Systems might release a patch to correct a model fault.

The patch generally checks how many records are to be updated, and reports on what is to be done.

#### **Access**

Ribbon	Configure > Model > Integrity > Run Patch
--------	---

### **Run SQL Patch**

1	Open Enterprise Architect and load the Project that requires the patch applied.
2	Select the 'Run Patch' option.
	The 'Run Patch' dialog displays.

3	Click the Browse button and select the supplied patch file (*.XML) in the file browser.
	Upon loading the select file, the Description will then be loaded with the explanation of what action the patch will perform.
4	Click the Run button to apply the patch to the current Project.

## Rename a Project

If you want to rename a project, you can only do so at the Windows file system level, using Windows Explorer.

## Rename an Enterprise Architect project file

Ste	Action
p	
1	If you have the project open, close it.
2	Ensure no other users have the file open.
3	Open Windows Explorer and navigate to the project.
4	Rename the project file using Windows Explorer.
5	You should keep the file extension to preserve compatibility with the default project type, as installed in the registry at installation time.

# **Compact a Project**

After a period of time, through general use, a project .eap file might occupy more disc space than necessary. You can move the project to a local drive and compact the file to recover the unused space.

#### **Access**

Ribbon	Configure > Model > Integrity > Manage
	.EAPX/.EAP File > Compact
	.EAPX/.EAP File

## **Compact a project**

Ste	Action
p	
1	If you have the project open, shut it down.
2	Ensure no other users have the file open.
3	Select the 'Compact .EAPX/.EAP File' menu

	option.
4	Follow the on-screen instructions to complete the process.

- Always compact projects on a local drive, never on a network drive
- In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have Administer Database permission to compact a project

# Repair a Project

If a project has not been closed properly, such as during system or network outages or on poor network connections, on rare occasions the .eap file does not re-open correctly. A message displays informing you the project is of an unrecognized database format or is not a database file. In such cases, you can move the project file to a local drive and repair it.

#### **Access**

File
------

## Repair a project that was not closed properly

Ste	Action
p	
1	Ensure that all users are logged off the project you are attempting to repair.


2	Copy the project file to a local drive on your workstation.
3	In Enterprise Architect, select 'Start > Desktop > Preferences > Preferences' to display the 'Preferences' dialog.
	On the 'General' page, deselect the 'Use Jet 4.0 - requires restart' checkbox.
4	Close and restart Enterprise Architect - you do not need to open any model, including the one you are repairing.
5	Select the 'Repair .EAPX/.EAP File' menu option, and follow the on-screen instructions.
6	Once you have repaired the project, it is recommended that you perform a data integrity check.

- Always repair projects on a local drive, never on a network drive
- The 'Compact a Project' option can also repair corrupt

.eap files

• In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Administer Database' permission to repair a project

## **Reference Data**



Reference data is used in Enterprise Architect to provide meta-information for the modeler, and is often seen in drop down lists and selection boxes. It includes such things as status codes, requirement types, model authors and more.

For convenience, Enterprise Architect comes pre-configured with useful reference data, but it is best practice to review this existing data when setting up a project and either replace or edit it to ensure it is appropriate for the project.

There are a number of different types of reference data, some of which apply at a repository level - such as status codes and authors - and some that is more technical in nature, such as code engineering and database datatypes.

The reference data can be copied between repositories by exporting it from one repository and importing it into another; this mechanism can save time and ensure consistency between repositories.

Project reference data can be entered and edited through the 'Configure > Reference Data' ribbon panel, and includes:

- Stereotypes
- Tagged Value Types
- Cardinalities
- People

- General Types
- Project Indicators
- Estimation Factors
- Datatypes

• In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Manage Reference Data - Update' permission to update and delete reference items

## **UML Types**

Using the 'UML Types' dialog you can configure stereotypes, Tagged Value types and the cardinality list for your project. In more detail, you can:

- Add, modify and delete stereotypes
- Customize stereotypes' appearance
- Update Shape Scripts and metafiles associated with stereotypes
- Create and modify Tagged Values
- Define cardinality rules

#### **Access**

Ribbon	Configure > Reference Data > UML
	Types

## **Stereotype Settings**

Enterprise Architect has an extensive set of Standard Stereotypes that you can apply to any UML construct. Using the 'Stereotypes' tab of the 'UML Types' dialog, a Technical Developer can also customize the stereotypes for your project by adding, modifying and deleting them. For information on customizing stereotypes, see the *Custom Stereotypes* Help Topic.

Stereotypes can be modified to make use of metafiles (image files) or customized colors, or to make use of the Enterprise Architect Shape Scripts to make new object shapes to determine the shape and dimensions of the object.

#### **Access**

Ribbon	Configure > Reference Data > UML
	Types

## Manage Stereotypes

Option	Action

Stereotype	Type in the name of the new stereotype, or click on an existing stereotype in the list in the right-hand panel.
Group name	For a stereotype that applies to an element feature (an attribute or operation) type in a name under which to group the features that have the stereotype. This is shown on diagrams in the attributes or operations compartment of the element. If you do not provide a group name, the label in the feature compartment defaults to the stereotype name.
Base Class	Click on the drop-down arrow and select an object type, so that the stereotyped object will inherit the base characteristics from that existing object type.
Notes	Type in any notes concerning the stereotype (and not the objects to which the stereotype is to be applied).
None	Select this radio button to use the default object appearance.
Metafile	Select this radio button to use an image file for the appearance of the stereotyped object.

Shape Script	Select this radio button to apply a custom shape to the stereotyped object, which you define using the Enterprise Architect Shape Scripting language.
Assign	Click on this button to select or define the associated metafile or Shape Script to be applied to the stereotyped object.
Remove	Click on this button to remove the associated metafile or Shape Script from the stereotype.
Fill	Click on the drop-down arrow and select a default color for the background of the object.  This color will be applied to all occurrences of any object to which the stereotype has been applied; if the color is subsequently changed, the change is immediately applied to all occurrences of any object to which the stereotype was applied (as for changes to any other property of the stereotype).  However, on elements created with the stereotype, the default color might be overridden by other color definitions of a higher priority that have been applied to

	the element, such as the 'Alternative Appearance' dialog (F4) definition.
Border	Click on the drop-down arrow and select a default color for the object border.
Font	Click on the drop-down arrow and select a default color for the stereotype font.
Reset	Click on this button to reset the stereotyped object appearance definition to the default object appearance.
Preview	Provides a visual representation of the stereotyped object definition.
New	Click on this button to clear the dialog fields so that you can define another stereotype.
Save	Click on this button to save the stereotype definition and add it to the list of current stereotypes.
Delete	Click on this button to immediately remove the selected stereotype from the list of defined stereotypes.

# **Shape Editor**

A Technology Developer can use the Shape Editor to specify custom shapes via a scripting language; that is, to create Shape Scripts. These custom shapes are drawn instead of the standard UML notation. Each script is associated with a particular Stereotype, and is drawn for every element of that stereotype.

#### **Access**

D'11	
Ribbon	Configure > Reference Data > UML
	Types > Stereotypes > [select or specify a
	stereotype]: Shape Script: Assign

#### Reference

Option	Action
Format	The format in which the script is written.
Import	Opens a Windows browser dialog, allowing for a script file to be loaded.

Export	Opens a Windows browser dialog, allowing for a script file to be saved.
Edit window	The area in which a script can be written.
Preview of main	A visual representation of the compiled script. Nothing displays until the Refresh button is clicked.
Next Shape	If a composite shape is defined within the Edit Window, clicking on the Next Shape button pages through the components of the shape.
Refresh	Parses your script and produces a visual example of the shape in the Preview of main window.
OK	Exit from the Shape Editor; don't forget to save your scripts from the 'Stereotype' tab.

• Shape Scripts adopt the same color gradient settings as

normal elements, as defined in the 'Standard Colors' page of the 'Preferences' dialog

- If an element's appearance is modified by a Shape Script, many of the 'Advanced' context menu options for that element are disabled
- Once you have finishing writing your Shape Script, click on the OK button; to save the Shape Script you must click on the 'Stereotypes' tab

# **Tagged Value Types**

Tagged Values are used in a variety of places within Enterprise Architect to specify additional information about an element or connector. The 'Tagged Value Types' tab of the 'UML Types' dialog enables a Technology Developer to rapidly create Tagged Values, using a range of predefined structured Tagged Values to create structured tags that adhere to a specific format. For example, for model features that use the predefined tag Boolean you can use the 'Tags' tab of the Properties window to assign a value of True or False and no other value.

You can also add default Tagged Value names and create predefined reference data Tagged Value types and custom masked Tagged Value types.

Any Tagged Value names created display in the drop-down lists of Tagged Value names in the 'Tagged Value' dialogs for elements, operations and attributes.

#### **Access**

Ribbon	Configure > Reference Data > UML
	Types > Tagged Value Types

# **Create a Tagged Value Type**

Field	Action
Tag Name	Type the new name of the Tagged Value.
Description	Type a description of the Tagged Value.
Detail	Type any additional information necessary.
New	Click to begin creating a new Tagged Value.
Save	Click to save the details of a Tagged Value.
Delete	Click to delete a Tagged Value from the Defined Tag Types list.
Defined Tag Types	A list of previously defined Tagged Values.

### **Notes**

 You can transport these Tagged Value Type definitions between models, using the 'Configure > Model > Transfer
 > Export Reference Data' and 'Import Reference Data' ribbon options; Tagged Value Types are exported as Property Types

# **Cardinality**

The 'Cardinality Values' tab of the 'UML Types' dialog enables you to add, modify and delete values in the default cardinality list.

The cardinality values are used to define the multiplicity of source and target elements in relationships. This is the range of instances of the role that can be active in the relationship; for example, one employee can be assigned to tasks; for the target role you define the range of instances (such as tasks) the employee could be assigned to.

The cardinality values are also used to define the multiplicity of a Classifying element; that is, the number of instances of the element that can exist. For example, the Class element 'Building Walls' might have a multiplicity of 2..n, meaning that at least two walls must exist (to support the roof) but there can be many walls if the building design required it.

The values have these formats:

- \*, or 0..\* zero, one or many instances
- 0..n zero or up to n instances, but no more than n
- n exactly n instances
- n..\* n, or more than n instances.

#### **Access**

Ribbon	Configure > Reference Data > UML
	Types > Cardinality Values

### Reference

Field	Action
Cardinality	Type the new name of the Cardinality Value.
New	Type a description of the Cardinality Value.
Save	Saves the Cardinality value and adds it to the Cardinality List.
Delete	Deletes a Cardinality value from the Cardinality List.
Cardinality List	A list of already defined Cardinality values.

#### **Notes**

• You can transport these cardinality values between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **People**

In your project, you can set up and configure the people and stakeholders involved in and relevant to this model; that is:

- Maintain Authors involved within a project
- Define role types that are captured within Enterprise Architect
- Record information on project resources
- · Capture client details associated with the current model

#### **Access**

Ribbon	Configure > Reference Data > Model
	Types > People

# **Project Authors**

You can define the people who are working on a project, such as the authors of specific elements.

#### Access

Ribbon	Configure > Reference Data > Model
	Types > People > Project Author(s)

#### **Notes**

- If you enter multiple names, Enterprise Architect adds them separately and in alphabetical order to the 'Defined Authors' list; if you then click on one of these names, Enterprise Architect displays that name only in the 'Name(s)' field
- If you type in a role, this is not added to the roles on the 'Project Roles' tab
- You can transport these author definitions between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

### Reference

Field	Action
Name(s)	Type the name of the person registered as a Project Author.  If you are using a Windows Active Directory, you can select names from the directory; click on the button to display the 'Select Users' dialog.  You can also type a list of names separated by semi-colons; this enables you to define a group of people sharing a role, such as a team of Developers, Testers or Analysts.  Do not leave any spaces between the names and the semicolons.
Role	(Mandatory) Enter the role the Project Author plays in the project (such as Designer, Analyst, or Architect). You can type a role name or click on the drop-down arrow and select a role defined through the 'Project Roles' tab.
Notes	Type any additional notes concerning the

	Project Author.
New	Add further Authors.
Save	Add the new Author to the Defined Authors list.
Delete	Removes an Author from the Defined Authors list.
Defined Authors	Review the Project Authors already defined.

### **Select Users**

If your company is using a Windows Active Directory, you can select the Project Author names from the local or corporate-wide directory.

#### **Access**

Ribbon	Configure > Reference Data > Model
	Types > People > Project Author(s) :

#### Reference

Field	Action
Object Types	Opens the 'Object Types' dialog, which provides a choice of object types that can be used.
Locations	Defines the root location from which to begin a search.
Check	Matches object names listed in the Enter

Names	the object names to select section.
Enter the object names to select	Specify object names to search for.
Advanced	Opens the 'Advanced' dialog to provide further search options.  For more information on this dialog, please refer to Windows Help and Support.

#### Use to

• Select Project Authors from Windows Active Directory

#### **Notes**

• Multiple Entries can be typed into the 'Enter the object names to select' section; ensure that objects are separated by semicolons (for example: Name01; Name02)

# **Project Roles**

People associated with a project play a role in analysis, design or implementation, such as Application Analyst, Architect, Developer and Project Manager. Project roles define the activities that resources can undertake.

#### **Access**

Ribbon	Configure > Reference Data > Model
	Types > People > Project Roles

#### Reference

Field	Action
Role	Type or select the name of the role.
Description	Type a description of the role.
Notes	Type any additional information related to the role.

New	Add further Roles.
Save	Add the new role to the Defined Roles list.
Delete	Removes a role from the Defined Role list.
Defined Roles	Review the Project Roles already defined.  The 'Defined Roles' list is available for selection for any element in the model; for example, you can select roles on the 'Project Authors' page of the 'People' dialog, and the Resource Allocation window.  You can also specify other roles on these dialogs, but such roles are not added to the 'Defined Roles' list.

### Use to

• Define role types that are captured within Enterprise Architect

#### **Notes**

- Deleting a role has no effect on any Project Author definition having this role; the deleted role becomes a simple text entry in the Project Author definition
- You can transport these role definitions between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Project Resources**

Resources are, for example, project authors, analysts, programmers and architects. That is, anyone who might work on the system over time, either adding to the model or programming and designing elements of the system outside Enterprise Architect.

#### **Access**

Ribbon	Configure > Reference Data > Model
	Types > People > Project Resources

#### Reference

Field	Action
Name	Type or select the name of the person listed as a resource.  The resource name is available for use in Resource Management.
Organization	Type the name of the organization

	employing the resource.
Role(s)	Type or select the role the resource plays in the project (for example, Designer, Analyst, Architect).
Phone 1, Phone 2, Mobile, Fax	Type the contact telephone numbers for the resource.
Email	Type the email address for the resource.
Notes	Type any additional notes on the resource.
Available Resources	Review resources that have already been defined.
New	Add further resources.
Save	Add a new resource to the Available Resource list.
Delete	Delete a resource from the Available Resources list.

#### Use to

• Record information on project resources

#### **Notes**

 You can transport these resource definitions between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Project Clients**

Project clients are the eventual owners of the software system.

#### **Access**

Ribbon	Configure > Reference Data > Model
	Types > People > Project Clients

### Reference

Field	Action
Name	Type or select the name of the client.
Organization	Type the name of the organization that employs the client.
Role(s)	Type the role the client plays in the project (for example, Manager, Sponsor).
Phone 1,	Type the contact telephone numbers for

Phone 2, Mobile, Fax	the client.
Email	Type the email address of the client.
Notes	Type any additional notes on the client.
Defined Clients	Review clients that have already been defined.
New	Add details of further clients.
Save	Add a new client to the Defined Client list.
Delete	Delete a client record from the Defined Client list.

#### Use to

• Capture client details associated with the current model

#### **Notes**

 You can transport these client definitions between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **General Types**

When you create or edit the properties of an element, you define the type or status of the property by selecting from a drop-down list that initially contains system-provided values. You can add to or replace any of these system values with your own customized values. The properties you can customize are:

- Status
- Constraint
- Constraint Status
- Difficulty
- Priority
- Test Status
- · Requirement
- Scenario
- Maintenance Status

Each of these can be separately managed through the 'General Types' dialog.

#### Access

Ribbon	Configure > Reference Data > Model
	Types > General Types

# **Status Types**

In an element 'Properties' definition, the status of the element in the development management process is defined in the element 'Status' field. You can select the appropriate value from a drop-down list, which initially contains the system values:

- Approved
- Implemented
- Mandatory
- · Proposed and
- Validated

You can add to or replace any of these values with your own custom values. You can also assign a color band to each status type, and define the types of element that can display those colors.

#### Access

Ribbon	Layout > Diagram > Appearance > Configure Status Colors, or
	Configure Status Colors, of Configure > Reference Data > Model Types > General Types > Status

# **Customize Element Status Types**

Option	Description
Status	Type the name of the status.
Description	Type a short description of the status.
Status Type Color	Using the drop-down arrow, select a color to be applied to the current status type.
Preview	Displays a visual representation of an element with the selected status type color.
Restore Default	Restore the status type color to its default setting.
Applies to	By default, status colors only apply to Requirement, Issue and Change elements. You might decide to also apply these colors to other UML elements, such as Use Cases or Classes.  To do this, click on the Applies to button and, in the 'Applied Status Colors' list, select the checkbox against each

	element type to which to apply the status colors.
New	Clear the dialog fields to create a new status.
Save	Save the status, and add it to the Type list.
Delete	Remove the currently selected status from the Type list.
Type	Lists the current status types and descriptions for each status.

#### **Notes**

- To display status colors on your diagrams, you must select the 'Show status colors on diagrams' checkbox on the 'Objects' page of the 'Preferences' dialog
- You can transport the status types (and the colors assigned to status types) between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options
- Requirement, Feature, Issue and Change elements have a status color compartment, whereas the status color for

other elements is applied to the element shadow; to show the element shadows (and hence the status colors), select the 'Element Shadows on' checkbox on the 'Diagram Appearance' page of the 'Preferences' dialog

# **Constraint Types**

In an element 'Properties' definition, each constraint on the element is defined by type in the 'Constraint' field. You can select the appropriate value from a drop-down list, which initially contains the system values:

- Invariant
- Post-condition
- Pre-condition
- Process and
- OCL

You can add to or replace any of these values with your own custom values.

#### Access

Ribbon	Configure > Reference Data > Model
	Types > General Types > Constraint

### **Customize Constraint Types**

Option Des	cription
------------	----------

Constraint	Type the name of the constraint to define.
Description	Type a brief description of the constraint.
Note	Type any further details concerning the constraint.
New	Clear the fields to define a new constraint.
Save	Save the constraint definition and add it to the Defined Constraint Types list.
Delete	Remove the currently selected constraint from the Defined Constraint Types list.
Defined Constraint Types	Lists the currently-defined constraint types and their descriptions.

#### **Notes**

• You can transport customized constraint types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon

options

# **Constraint Status Types**

In an element 'Properties' definition, each constraint's status in the development process is defined in the constraint 'Status' field. You can select the appropriate value from a drop-down list, which initially contains the system values:

- Implemented
- Build
- Validated
- Approved
- · Mandatory and
- Proposed

You can add to or replace any of these values with your own custom values.

#### Access

Ribbon	<ul> <li>Configure &gt; Reference Data &gt; Model         Types &gt; General Types &gt; Constraint         Status Types</li> </ul>
--------	--

### **Customize Constraint Status Types**

Option	Description
Status	Type the name of the constraint status to define.
Make Default	To make the selected constraint status the default for all constraint 'Status' fields, select the checkbox.
New	Clear the fields to define a new constraint status.
Save	Save the constraint status definition and add it to the Type list.
Delete	Remove the currently selected constraint status from the Type list.
Type	Lists the currently available constraint status types.
<b>↑</b>	Move the selected constraint type higher or lower in the Type list.  This defines the ordering used in the Status drop down combo boxes, and in sorting any report or list when the Constraint Status Type is used as the

	sort-by property.
Sort Alphabeticall y	Reorganize the entries in the Type list into alphabetical order.
Restore Defaults	Remove all customized constraint status values and restore the system defaults.

#### **Notes**

 You can transport customized constraint status types between models, using the 'Configure > Model > Transfer
 > Export Reference Data' and 'Import Reference Data' ribbon options

# **Difficulty Types**

Developing a particular element might be a simple task or more complex. In the element Properties definition, the level of difficult of developing that element is defined in the 'Difficulty' field. You can select the appropriate value from a drop-down list, which initially contains the system values 'High', 'Medium' and 'Low'. You can add to or replace any of these values with your own custom values.

#### **Access**

Ribbon	Configure > Reference Data > Model
	Types > General Types > Difficulty

### **Customize Difficulty Types**

Option	Description
Difficulty	
·	Type the name of the Difficulty to define.
Make Default	
	To make the selected Difficulty the
	default for all 'Difficulty' fields, select the

	checkbox.
New	Clear the fields to define a new Difficulty type.
Save	Save the Difficulty definition and add it to the Type list.
Delete	Remove the currently selected Difficulty from the Type list.
Type	Lists the currently available Difficulty types.
	Move the selected type higher or lower in the 'Type' list.  This defines the ordering used in the 'Difficulty' drop down combo boxes, and in sorting any report or list when the Difficulty type is used as the sort-by property.  For example: you have several Change elements on a diagram, and you select 'Diagram View'; then you sort on the 'Difficulty' column. The 'Diagram View' entries are grouped by difficulty, in the order you defined in this 'Type' field.
Sort Alphabeticall	Reorganize the entries in the Type list

У	into alphabetical order.
Restore Defaults	Remove all customized Difficulty values and restore High, Medium and Low.

#### **Notes**

 You can transport customized Difficulty types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Priority Types**

In an element Properties definition, the priority of developing that element is defined in the 'Priority' field. You can select the appropriate value from a drop-down list, which initially contains the system values 'High', 'Medium' and 'Low'. You can add to or replace any of these values with your own custom values.

### **Access**

Ribbon	Configure > Reference Data > Model
	Types > General Types > Priority

### **Customize Priority Types**

Option	Description
Priority	
·	Type the name of the Priority to define.
Make Default	
	To make the selected Priority the default
	for all 'Priority' fields, select the
	checkbox.

New	Clear the fields to define a new Priority.
Save	Save the Priority definition and add it to the Type list.
Delete	Remove the currently selected Priority from the Type list.
Type	Lists the currently available Priority types.
	Move the selected type higher or lower in the 'Type' list.  This defines the ordering used in the 'Priority' drop down combo boxes, and in sorting any report or list when the Priority type is used as the sort-by property.  For example: you have several Change elements on a diagram, and you select 'Diagram View'; then you sort on the 'Priority' column. The 'Diagram View' entries are grouped by priority, in the order you defined in this 'Type' field.
Sort Alphabeticall y	Reorganize the entries in the Type list into alphabetical order.
Restore	

Defaults	Remove all customized Priority values
	and restore High, Medium and Low.

 You can transport customized Priority types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Test Status Types**

All tests defined in the Testing window and 'Test Details' dialog have a status value to show what point in the testing cycle the test has reached. The system values you can select from the test 'Status' field are:

- Not Run
- Pass
- Fail
- Deferred and
- Canceled

You can add to or replace any of these values with your own custom values.

### Access

Ribbon	Configure > Reference Data > Model
	Types > General Types > Test Status

### **Customize Test Status Types**

Option	Description
--------	-------------

Status	
	Type the name of the Test status to define.
Make Default	
	To make the selected test status the default for all test 'Status' fields, select the checkbox.
New	
	Clear the fields to define a new Test status.
Save	
	Save the Test status definition and add it to the Type list.
Delete	
	Remove the currently selected Test status from the Type list.
Type	
	Lists the currently available Test status types.
<b>1</b>	Move the selected type higher or lower in the 'Type' list.
	This defines the ordering used in the test
	'Status' drop down combo boxes, and in
	sorting any report or list when the Test
	Status Type is used as the sort-by
	property.
	For example: you have run several tests on a Package, and you run a Test Details

	report; then you sort on the 'Status' column. The report entries are grouped by test status, in the order you defined in this 'Type' field.
Sort Alphabeticall y	Reorganize the entries in the Type list into alphabetical order.
Restore Defaults	Remove all customized Test status values and restore the system defaults.

 You can transport customized Test status types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Requirement Types**

In a Requirement definition, the requirement is categorized according to type or function, in the 'Type' field of the Requirement 'Properties' dialog. This helps to maintain a single set of typed requirements. You can select the appropriate 'Type' value from a drop-down list, which initially contains the system values:

- Display
- Functional
- Performance
- Printing
- Report
- Testing and
- Validate

You can add to or replace any of these types with your own customized values.

#### Access

Ribbon	Configure > Reference Data > Model
	Types > General Types > Requirement

# **Customize Requirement Types**

Option	Description
Requirement	Type the name of the requirement.
Description	Type a short description of the requirement.
Weight	Type a weighting to apply to the requirement type.
New	Clears the dialog fields so that you can define a new requirement type.
Save	Saves the requirement type details and adds it to the Defined Requirement Types list.
Delete	Deletes a selected requirement type from the Defined Requirement Types list.
Defined Requirement Types	Lists the currently available requirement types.

 You can transport these requirement types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Scenario Types**

In the Scenario definitions for an element each scenario is of a specific type, which you define in the 'Type' field on the 'Scenario' page of the 'Properties' dialog. You can select the appropriate value from a drop-down list, which initially contains the system values:

- Exception
- Alternate and
- Basic Path

You can add to or replace any of these system types with your own customized values.

### Access

Ribbon	Configure > Reference Data > Model
	Types > General Types > Scenario

### **Customize Scenario Types**

Option	Description
Scenario	

Туре	Type the name of the scenario type.
Description	Type a short description of the scenario type.
Weight	Type a value for the weighting to apply to the scenario type.
Notes	Type any additional information to describe the scenario type.
New	Clears the dialog fields so that you can define a new Scenario type.
Save	Saves the scenario type and adds it to the Defined Scenario Types list.
Delete	Deletes a selected scenario type from the Defined Scenario Types list.
Defined Scenario Types	Lists the currently available scenario types to offer in the drop-down list of a 'Scenario Type' field.

 You can transport customized scenario types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

# **Maintenance Status Types**

Model Maintenance items such as Changes, Issues, Defects and Tasks pass through a series of stages whereby each item is raised, assessed, approved, worked on, reviewed and completed. As an item passes through each stage, it can be assigned a Status from this system-provided list:

- Active
- Complete
- Deferred
- Merged
- New (the initial default status)
- No Action
- Paused
- Rejected
- Rework
- Verified

The Maintenance Status values are defined on the 'Maintenance Status' page of the 'General Types' dialog. You can add to or replace any of these values with your own custom values.

### **Access**

Ribbon	Configure > Reference Data > Model
	Types > General Types > Maintenance
	Status

# **Customize Maintenance Status Types**

Option	Description
New	Click on this button to clear the fields to define a new Maintenance status.
Maintenance	Type the name of the Maintenance status to define.
Make Default	To make the selected status the default for all Maintenance item 'Status' fields, select the checkbox.
Save	Save the Maintenance status item and add it to the 'Type' list.
Delete	Remove the currently selected Maintenance status from the 'Type' list.
Type	Lists the currently available Test status types.

	Move the selected type higher or lower in the 'Type' list.  This defines the ordering used in the Maintenance 'Status' drop down combo boxes, and in sorting any report or list when the Maintenance Status Type is used as the sort-by property.  For example: you have set up a number of Chance items and Parkers and Parke
	of Change items on a Package, and you run a report on the Change items; then you sort on the 'Status' column. The report entries are grouped by status, in the order you defined in the 'Type' list.
Sort Alphabeticall y	Reorganize the entries in the 'Type' list into alphabetical order.
Restore Defaults	Remove all customized Maintenance status values and restore the system defaults.

• You can transport customized Maintenance status types

between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options

### **Metrics and Estimation**

TCF values, EFC values and Default Hour Rate for a project are controlled from the 'Estimation Factors' dialog.

Risk, metric and effort types for a project are controlled from the 'Project Indicators' dialog.

For further information on these see the <u>Project</u> <u>Management</u> and <u>Project Resources</u> topics, or specifically:

- Technical Complexity Factors
- Environment Complexity Factors
- Default Hours
- Effort Types
- Metric Types
- Risk Types

### **Maintenance**

Within your project, you can set up Maintenance types that determine the base Problem Types to be used within the model.

### **Access**

Ribbon	Configure > Reference Data > Model
	Types > Maintenance

# **Problem Types**

#### NOT CURRENTLY USED

For the maintenance and change control screens, you can use the 'Maintenance' dialog to set the base Problem Types that are handled. Examples are hardware-related issues, performance problems, software bugs and network problems.

#### Access

Ribbon	Configure > Reference Data > Model
	Types > Maintenance > Problem Types

### **Define Problem Types**

Field	Action
Problem Type	Type in the name of the problem type.
Description	Type a short description of the problem type.

Weight	Provide a weighting to apply to the problem type.
Note	Type any additional information on the problem type.
Defined Types	Displays all of the pre-defined and saved problem types.
New	Click on this button to clear the dialog fields so that you can add a new problem type.
Save	Click on this button to save the scenario details and add it to the 'Defined Types' list.
Delete	Click on this button to delete a selected scenario from the 'Defined Types' list.

• You can transport these problem types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon

options

• You transport the problem types together with test types as a Maintenance Types file

# **Testing Types**

You can use the 'Test Types' tab of the 'Maintenance' dialog to add testing types to the basic set that comes with Enterprise Architect. Typical test types are load tests, regression tests and standard tests.

### **Access**

Ribbon	Configure > Reference Data > Model
	Types > Maintenance > Test Types

### Reference

Field	Action
Test Type	Type the name of the test type.
Description	Type a short description of the test type.
Weight	Type a weighting to apply to the test type.

Note	Type any additional information on the test type.
Defined Types	Displays all of the pre-defined and saved test types.
New	Add a new test type.
Save	Saves the scenario details and adds it to the 'Defined Types' list.
Delete	Deletes a selected scenario from the 'Defined Types' list.

- You can transport these test types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options
- You can either export the test types together with the default problem types, as a Maintenance Types file, or separately as a Test Types file

# **Data Types**

Different programming languages support different inbuilt data types. It is possible for you to manage and extend this set of inbuilt data types for a standard programming language, as well as define new programming languages for use within Enterprise Architect.

### **Access**

Ribbon	Configure > Reference Data > Settings > Coding Datatypes or
	Develop > Preferences > Options > Configure Code Engineering Datatypes

## **Programming Language Datatype Options**

Option	Description
Product Name	Click on the drop-down arrow and select the name of the programming language.
Add Product	Click on this button to display a prompt

	for the name of a new programming language.  Type the name and click on the OK button.
Datatype	Type the language-specific name of the datatype.
Common Type	Type the common (or generic) name of the datatype; for example, the Java boolean datatype has a common datatype Boolean.
New	Click on this button to clear the fields to create a new datatype.
Save	Click on this button to save the newly created or updated datatype.
Delete	Click on this button to delete the selected datatype.  You can delete your own custom data types, but you cannot delete any of the predefined data types.
Defined Datatypes for Programming Languages	Review the list of datatypes for the selected language, and click on any that you want to edit or delete. The details for the selected datatype display in the dialog

fields.

- You do not need to set the options in the 'Size' panel
- Once you have defined at least one datatype for a new language, that language name is added to the drop-down list for the 'Language' fields in the 'Programming Languages Datatypes' dialog, in the Code Template Editor, and in the 'Properties' dialog for each Class element within the model
- You can transport these data types between models, using the 'Configure > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options
- In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Configure Datatypes' permission to update and delete data types

### **Resources Window**

The Resources window is a repository of project-standard and re-usable document generation templates, MDG Technologies, Relationship Matrix profiles, commonly-used model elements, stylesheets, UML Profiles and Patterns. The window provides facilities for creating and modifying these structures and facilities and, in some cases, for applying the facility to the current model directly from the window.

#### **Access**

Ribbon	Start > Desktop > Share > Resources Explore > Portals > Windows > Explore > Resources Configure > Reference Data > Resources
Keyboard Shortcuts	Alt+6

# Resources available through the Resources window

- In the Corporate, Unified and Ultimate editions of Enterprise Architect, if security is enabled you must have 'Configure Resources' permission to maintain Resources window items
- For a number of folders in the Resources window, the right-click context menu also offers a 'Help' option that, when you select it, displays a brief description of the folder

Resource	Description
Document Generation	The Document Generation folder holds a number of sub-folders, each of which provides the facilities for generating a particular type of document or report from your model.  • System Templates - this sub-folder itself has sub-folders containing system-defined report templates, Fragments, Cover Pages, Style Sheets and Table of Contents definitions You can right-click on these template names and select options to display the template contents or to copy the template as the basis of a user-defined template that you work on in the Document Template Editor, under a different name; you can also select the

- 'Override' option to create a copy of the system template as a user template with the same name
- User Templates this sub-folder also has sub-folders for report templates, Fragments, Cover Pages, Style Sheets and Tables of Contents, but these are the templates that you have created yourself using the Document Template Editor, either as new or by copying and editing another template You can right-click on these template names and select options to create, delete, rename, modify, move or copy a user-defined template; you have additional options to mark a report template as a Fragment, or a Fragment as a report template, if they are suitable for this reclassification You can also 'drag and drop' user-defined templates between user-defined groups, and between these groups and the appropriate standard 'type' folders; for example, from 'DavidCover' to 'Cover Pages'
- Technology Templates if you have loaded an MDG Technology containing document templates, those are also listed under the Technology name

- Web Style Templates this sub-folder contains the HTML style templates that you have created as alternatives to the system-supplied <default> template To create a new template, right-click on the folder name and select the 'Create HTML template' option, and provide a template name; this opens the HTML and CSS Style Editor, in which you create the template from HTML fragments
  - You can right-click on the template names and select options to delete the template or modify the template contents
- Defined Documents this folder holds the Resource documents (report specifications) you have created in the Document Report Generator; you can right-click on the document name to generate documents individually or as a batch, open the generated document, or delete the report specification
- Linked Document Templates this folder holds the non-standard Linked Document templates, either user-defined or supplied with each MDG Technology enabled on the system; you can edit or delete any of

these existing templates, or create new ones from scratch or by copying an existing template, including the system-provided Linked Document templates

You can also re-assign the templates to different template groups, either another of the existing groups or a new one that you create as part of the assignment

 Legacy Templates - if you are, or have been, using the original (legacy)
 Enterprise Architect report generator, this sub-folder contains the report templates that you use to generate the documents

You can continue to create, modify, use and delete legacy style templates, but it is recommended that you switch to the later report generator

### MDG Technologies

The MDG Technologies folder lists the MDG Technologies that have been imported directly into the Resources window. Each technology extends the modeling capabilities and facilities of Enterprise Architect.

You can import Technologies into your project by right-clicking on the *MDG* 

Technologies folder and selecting the 'Import Technology' menu option. The 'Import MDG Technology' dialog then gives you the option to import the Technology to:

- 'User', for your individual use; the Technology is imported into the %APPDATA% folder and is not listed in the Resources window
- 'Model', for all project users to access; the Technology is imported into the Resources window

If you have any MDG Technologies in the folder, each has its own subfolder containing the Profiles, Patterns and code modules used in the Technology. You can right-click on these and select options to delete the Technology, review the Patterns or Profiles, or invoke the code modules.

If you remove the Technology, it is removed from the Resources window, the 'MDG Technologies' dialog, and the model.

Consider the fact that some MDG Technologies can be large and might impose some delays on the workstation as they load each time a user connects to the model.

Model Patterns	The Model Patterns folder holds Model Patterns that have been imported into the model from external sources, including those developed within your own organization. Each Pattern XML file will have a matching .rtf file to explain the Pattern to users. Model Patterns generate modeling structures (Packages, diagrams and elements) within your model.
Matrix Profiles	The Matrix Profiles folder contains a list of Relationship Matrix Profiles that you or your team members have created using the Relationship Matrix or Specification Manager. You simply double-click on a Matrix Profile name to quickly open the Relationship Matrix under the settings defined in the Profile.
Favorites	The Favorites folder provides a shortcut to each commonly-used element that you have added to the folder, so that you can quickly and easily locate the elements and add them to diagrams.
Stylesheets	The <i>Stylesheets</i> folder contains XSL stylesheets that you or your team members have imported into the model. These XSL stylesheets support the

optional step of converting XMI files exported from the model into alternative formats such as HTML, XSL or source code. Stylesheets imported here are then available in the drop-down lists on the 'XML Export' dialog and the 'Generate GML Application Schema' dialog. Combined with UML Profiles, this is a powerful means of extending Enterprise Architect to generate almost any content required.

To import a stylesheet:

- 1. Right-click on the folder name and select the 'Import Stylesheet' option.
- 2. Locate and select the stylesheet file in the browser, and click on the Open button.
- 3. Provide a reference name for the file, and click on the OK button.

Once the stylesheet is in the folder, you can select context menu options to reload it (if it has been changed at the source) or delete it.

### UML Profiles

A Profile is a source of modified or extended element and connector types that you have developed from the UML base types. You can import each new Profile into this folder, and then create

elements and connectors of the new types by dragging the icons from the Profile onto a diagram.

Once you have Profiles in the folder, you can select options for arranging them in order of name or type, viewing a Profile description, or deleting a Profile.

It is possible to synchronize the Tagged Values and constraints for any elements created from a Profile element in the Resources window.

Importing and applying Profiles through the Resources window is no longer recommended; from Enterprise Architect release 7.0. it is recommended that you load and apply Profiles as components of MDG Technologies.

#### **Patterns**


The *Patterns* folder is a folder of Design Patterns that you or your team members have imported into the model. A Pattern captures complex new elements and features that you can drag into a diagram without having to retype or reconfigure each element.

Within the folder, the Patterns are grouped by type. Once you have Patterns within a group, you can select options to delete a selected Pattern or all Patterns in

the group, view a Pattern's details, or
apply a Pattern to an empty diagram.

### **Favorites**

If you have any elements that you or your team use frequently - such as the list of Actors in a system - you can add them to the Favorites folder in the Resources window, and use that as the source for conveniently dragging and dropping instances of or links to these elements into other diagrams. This makes it much easier to locate and use the elements as you create and manage your model.



#### Access

Ribbon	Start > Desktop > Share > Resources > Favorites, or Explore > Portals > Windows > Explore > Resources > Favorites, or Configure > Reference Data > Resources > Favorites
Keyboard Shortcuts	Alt+6   Favorites

## **Actions on the Favorites Folder**

Action	Detail
Add an element to the Favorites Folder	<ul> <li>In a diagram, right-click on the element to add</li> <li>From the context menu select the 'Find   Add to Favorites' option</li> <li>Switch to the Resources window and expand the <i>Favorites</i> folder; the added element is listed within its element-type category (such as Class)</li> <li>You add elements to the <i>Favorites</i> folder individually.</li> </ul>
Delete an element from the Favorites Folder	<ul> <li>Right-click on the element within the <i>Favorites</i> folder in the Resources window</li> <li>From the context menu select the 'Delete Favorite' option</li> <li>A confirmation prompt displays; click on the Yes button</li> </ul>
View Properties of an element in the Favorites	<ul> <li>Select and right-click on the element in the folder</li> <li>From the context menu, select the 'Element Properties' option; the</li> </ul>

Folder	element 'Properties' dialog displays
--------	--------------------------------------

• When you have had the *Favorites* folder open for some time and other users might have been adding to it, right-click on the folder name and select the 'Refresh Favorites' option to update your view of the folder with the new contents

## **Sharing Reference Data**

You can conveniently update your models with reference data (including Glossary and Issue information) by exporting the data to and importing the data from .XML files to (for example):

- Copy glossaries from one model to another
- Add additional profiles by merging new stereotypes into the model
- Update reference data from files supplied by Sparx Systems as a maintenance release
- Copy resources, clients and so on from one model to another

You import data into the model automatically or manually from a reference data .XML file, exported from another model or an iteration of the current model.

# Link Reference Data to a Shared Repository

If you have a number of projects that use the same sets of reference data, you can use a central project containing that common data as a shared repository. The common data includes system resources such as Security Users and Groups, Glossary terms or Data Types. Shared repositories make it possible for teams working on multiple projects to leverage a common and consistent set of system resources. Common standards and definitions can be applied across all projects using this repository. Any time a new project is started, that project can automatically inherit some or all of these common resources from the repository; there is no need to establish these resources again for each project.

Shared repositories apply to Database Management System (DBMS) based Enterprise Architect projects and can link all projects residing within one DBMS.

A new DBMS based project in Enterprise Architect is initially created with its own stand-alone repository. A single step process then allows that new project to be linked to the shared repository residing on its DBMS. Any older or pre-existing Enterprise Architect projects can also be linked to the shared repository, taking their resource data from the master version. This then allows for centralized management of the contents of the repository, promoting or enforcing common usage and standards.

Any changes to the shared repository are automatically

available to every participating project.

#### **Access**

D'1 1	
Ribbon	Configure > Model > Transfer > Shared
	Repository

## Set up a shared repository

Ste	Action
p	
1	Create the script file to set up the shared repository, as explained in the next table.
2	Execute the generated SQL script using a third-party tool.

## Select the repository tables to share

Option	Action
--------	--------

Script File	Type in the location into which the script file will be generated by this dialog, or click on the button and search for it.
Main Repository	Type in the name of the current main repository.
Shared Repository	Type in the name of the database to be used as the shared repository.  This name cannot be the same as the name of the main repository.
Table Groups	In the list of table groups that can be linked to the shared repository, select the checkbox against each table group to share in the repository.
Tables in each group	(Read only) Review the list of database tables in the currently-selected table group. All of these tables in the selected group will be available through the shared repository.
Generate	Click on this button to generate the SQL script to link the selected tables of the current (main) repository to the shared repository. The script is generated into the file location you specified in the

	'Script File' field.
View Script	Click on this button to open the generated script file in the default Code Editor, and to close the dialog.
Close	Click on this button to close the dialog.

- This feature is not applicable to projects that are based on local project files (.eap or .feap)
- Shared repositories are supported for MySQL, SQL Server and Oracle

## **Export Reference Data**

When you have a complete project set up, with fully defined project data, it is possible to capture either selected categories or all categories of that data, and export it to a single XML file. You can then review the data, and import it to another project or tool so that you do not have to define it all again. The exported data includes all instances of the selected data type in the project; for example, all defined cardinality values, or all Document Style Templates.

#### **Access**

Ribbon	Configure > Model > Transfer > Export Reference Data
--------	---

## **Select and Export Reference Data**

Ste p	Action
1	On the 'Export Reference Data' dialog, click on the '+' box against each table group you want to expand.

2	Select the checkbox against each table or table group to export.  If you select the top-level, group-name checkbox, all tables in that group are selected for export.
3	Click on the Export button.
4	When prompted to do so, enter a valid file name with a .XML extension.
5	Click on the Save and OK buttons.  This exports the data to the file; you can use any text or XML viewer to examine the file.

- You can resize the 'Export Reference Data' dialog; drag the dialog edges to the size you need
- If there are no instances of a selected data type in the project, the export does not generate any output for that data type in the XML file
- Currently, Standard Complexity Types cannot be directly edited and are therefore effectively standard for all models; they can be listed using the Predefined Reference Data Tagged Value type ComplexityTypes

## **Import Reference Data**

It is possible to import reference data into your model from an .XML file that was exported from another model or from an iteration of the current model, either:

- Manually, whenever you know there is new or changed data to apply, or
- Automatically whenever the model is reloaded into Enterprise Architect (if the file has changed since the previous import)

The automatic import checks if the source file has changed since the last import; if the file has not changed, the import does not proceed. If the file has changed, the changed data is imported; however, you can configure the system to display a prompt for you to allow or cancel the import.

#### Access

Ribbon	Configure > Model > Transfer > Import Reference Data > Import File
	Configure > Model > Transfer > Import Reference Data > Shared File

## Import reference data manually (Import File)

Ste p	Action
P	
1	On the 'Import Reference Data' dialog, click on the 'Import File' tab and on the Select File button, then select the filename to import data from.
	This would be an XML file produced by the Enterprise Architect Data Exporter.
2	If you have selected a valid file, a list of available tables to import displays in the 'Select Datasets to Import' panel.
3	Click on one or more of the tables to import.  Press Ctrl or Shift to click on multiple tables.
4	Click on the Import button to start the process.  A message displays when the import is complete; generally the process is quite fast.

## Import reference data automatically (Shared File)

Ste p	Action
1	On the 'Import Reference Data' dialog, click on the 'Shared File' tab.
2	If you are changing an existing configuration to import from a different XML file, click on the Clear button to clear the dialog fields.
3	Click on the Select File button and browse for the filename to import data from.  This would be an XML file produced by the Enterprise Architect Data Exporter.
4	If you have entered the name of a valid file, a list of tables to import displays in the 'Datasets in File' panel.  Click on one or more of the tables to import. Press Ctrl or Shift as you click on multiple tables.
5	If you prefer to control whether or not the automatic import takes place, select the 'Always prompt before import' checkbox.
6	Click on the Import button to import the reference data now, and to enable the automatic check and import for subsequent reloads.

Concerning General Types data:

- For Statuses, Constraints, Requirements and Scenarios, the imported data is merged with the existing data; if a record already exists it is updated to the new values, and if the record does not exist, a new record is added records are never deleted
- For Constraint Status Types, Difficulty, Test Status and Priority, the complete existing list is replaced by the imported list

Concerning Calendar events and event types, Team Library configurations, Patterns and Gap Matrix Profiles:

• The imported data is merged with the existing data; if a record already exists it is updated to the new values, and if the record does not exist, a new record is added - records are never deleted

Concerning Images in Microsoft SQL Server Repositories:

- Importing images as reference data into a SQLServer repository is not supported when connected via Pro Cloud Server
- To import images as reference data you must have additional MS SQL Server permissions, so that you can perform 'Set Identity On/Off' commands; the role of db ddladmin provides the required permissions; however,

this approach might not be allowed in your environment, so discuss this requirement with your DBA to find an appropriate solution